



Step 2

In the Tasks pane to the left of the window, click the link 'Set up new sync partnerships'. A list of compatible devices will be displayed. If the device you want to work with it not listed, quit Sync Center, ensure the device is connected to the computer and relaunch the program. If it still doesn't appear, check the manufacturer's website to see whether the device is compatible with Vista and/or Sync Center. If the device is now visible in the Sync Center window, select it by single-clicking it and a button labelled 'Set up' will appear at the top of the list. Click this button and Windows Media Player will launch. Depending on the capacity of the device, a message about not meeting the recommended minimum size may be displayed — just click Yes to continue.

**Step 3**

To allow Windows to remain in control of the synchronisation process, ensure the box labelled 'Sync this device automatically' is ticked at the top of the Device Setup dialogue box. Any




playlists which have been configured in Windows Media Player will be added to the list of file to synchronise and displayed in the list to the right. If there are any playlists which you would prefer not to synchronise, simply select it from the list and click the Remove button.

The order of playlists can be adjusted by making a selection from the list and clicking the up and down arrows next to the Priority label in the lower right-hand corner.

Step 4

Additional playlists for synchronisation can be selected by clicking the 'Available playlists' menu and selecting Sync Playlists. Select any playlists and click the Add button.


A random selection of files can be synchronised by ticking the




box labelled 'Shuffle what syncs'. Use the New Auto Playlist button to create new playlist based on your required criteria and add them to the synchronisation list in the same way. Once all of the settings have been configured, click the Finish button. There will be a pause and Media Player will disappear while the initial sync takes place.

Step 5

Launch Windows Media Player manually and the progress of synchronisation will be displayed in the bottom of the screen. Once the process is complete, a message will be displayed to that effect and you will be told that the device can be disconnected. If the device is plugged in whilst Windows Media Player is running in future, synchronisation will automatically take place. It is also possible to manually start synchronisation by clicking the Start Sync button in the lower right-hand corner of the screen. The icon in the upper right of the screen indicates how much storage space is remaining.

**Step 6**

Whenever the Sync Center is launched, the device that has just been configured can be seen in the 'View sync partnerships'



section. Synchronisation can also be achieved from here without the need to launch Windows Media Player; click the Sync All button, or select the device from the list and click Sync. Any problems during synchronisation are listed in the 'View sync conflicts' section, while clicking

the 'View sync results' link will display information about the most recent synchronisation. If the partnership between the Sync Center and a particular device is no longer required, right-click the icon representing the device and select Delete.