

can go to Control Panel > All Control Panel Items > Display and click on "Calibrate Colour" from the left pane of the window.

8.2 Display Empty Removable Drives

Windows 7 does not show empty drives by default. Click Computer in Windows 7 and you might see a strange lack of drives, but don't panic, and don't go returning your newly bought drive thinking its broke. It's just Microsoft trying to be helpful: drives like memory card readers are no longer displayed if they're empty. This does seem like an improvement but it should not be a default setting as it makes things harder to figure out for inexperienced users who are used to see everything right there. To get them back, just Launch explorer. Go to Tools > Folder Options > View and uncheck "Hide empty drives in the computer folder".

8.3 Recover screen space

The new Windows 7 taskbar takes up a lot of screen real estate with its big icons, which isn't a concern but if you are running it on a smallish screen like those of net-books, you can do with recovering some space for applications.

Shrink it to a more manageable size by right-clicking the Start button, then go to Properties > Taskbar > Use small icons > OK.

8.4 Restore the Quick Launch Toolbar

A lot of Windows Vista and XP users will find the absence of a Quick Launch toolbar in Windows 7 annoying because you sort of get used to it. It is disabled by default but it only takes a moment to restore it back.

- Open the "Run" dialog box by pressing [Win] + [R] and type gpedit.msc
- On the left hand pane, Navigate to User Configuration, Administrative Templates, and Start Menu and Taskbar
- Double-click on the "Show QuickLaunch on Taskbar" in the right pane. Select Enable, Click on Apply and then press Ok.
- Right click on Taskbar select Toolbar > New toolbar
- Navigate to C:\Users\ (user name) \AppData\Roaming\Microsoft\Internet Explorer
- Select the Folder "Quick Launch" and click on "Select Folder".

Now You should see Quick Launch Toolbar on Taskbar. To make it look like it would in Windows Vista, right click the taskbar, uncheck "Lock the Taskbar", and you should see the Quick Launch toolbar, probably to the right. Right-click its divider, clear Show Text and Show Title to minimize the