

```

root@kali:~# cat /proc/cpuinfo
processor       : 0
vendor_id      : AuthenticAMD
cpu family    : 6
model         : 2
model name     : QEMU Virtual CPU version 0.14.1
stepping      : 3
cpu MHz       : 1000.007
cache size    : 512 KB
b1t0_bug      : no
b1t1_bug      : no
f00f_bug      : no
f100f_bug     : no
fpu           : yes
fpu_exception : yes
cpuid level   : 4
wp            : yes
flags          : fpu pse tsc mce mce_cpl apic sep mtrr pge mca cmov pat pse36 clflush mxx fxsr sse sse2 syscall nx lm 3dnowprefetch stlb_l1n ssm tlm ustack
bogomips      : 3752.59
clflush size   : 64

root@kali:~#

```

valibha@linux-suse:~\$

File Edit View Search Terminal Help

valibha@linux-suse:~\$ uname -p

1686

valibha@linux-suse:~\$

"The quieter you become, the more you are able to hear."

valibha@linux-suse:~\$ qemu-system-x86_64 -cdrom OS/Images/Win7Final_usb.iso -boot d -s 768 -localtime -usb

qemu-system-x86_64 emulating 64-bit processor on a 32-bit Linux kernel. Note the "lm" in the list of CPU flags shown by a Backtrack Linux guest

If you installed Windows the way it was demonstrated in the workshop in a previous chapter, try running the installed Windows XP with **-cpu n270** added to the end of the command to launch Qemu. Now after the machine starts up, click on the start menu and right-click the "My Computer" entry, then select the "Properties" option. In the general tab of the computer properties window, notice the processor name mentioned in the "Computer" section. You'll find that Windows thinks it's running on an "Atom N270" processor. That's Qemu combined with the command line power of Linux which your Linux friend might be boasting about!

However the output of the **qemu-kvm -cpu ?** command is going to differ from the output of the command: **qemu -cpu ?**. This is because KVM support is not available for all the processor types that Qemu can emulate.

Qemu can emulate architectures other than x86 (Intel) architecture family and quite a lot of them. This would include MIPS, SPARC, ARM and a few others. There's a separate program (binary executable file) for emulating each of those architectures. Just type **qemu-system-** on the command line and press the [Tab] twice. You'll get the list of those programs which can actually emulate the different architectures. The command line parameters that you can pass to those programs are going to be different than qemu or qemu-kvm and you need to figure them out with the main pages.