

Table 2: Comparisons of defragmentation software

	UltraDefrag	Defraggler	MyDefrag	Auslogics Disk Defrag
Licence	GNU GPL	Proprietary (Freeware)	Proprietary (Freeware)	Proprietary
Supported file systems	FAT12, FAT16, FAT32, NTFS, exFAT	FAT32, NTFS, exFAT, ReFS	FAT16, FAT32, NTFS	FAT16, FAT32, NTFS
Supported platforms	Windows NT 4.0, 2000, XP, Server 2003, Vista, Server 2008, Windows 7 and 8 (including 64-bit versions)	Microsoft Windows XP, Server 2003, Vista, Server 2008, and Windows 7 (including 64-bit versions)	Microsoft Windows 2000, XP, Server 2003, Vista, Server 2008 and Windows 7 (including 64-bit versions)	Microsoft Windows XP, Server 2003, Vista, Server 2008, and Windows 7 (including 64-bit versions)
GUI	Yes	Yes	Yes	No
CLI	Yes	Yes	Yes	No
Script	Yes	No	Yes	No
Scheduler	Win TS	Win TS	Win TS	No
Boot time	Yes	Yes	No	No
Auto defrag when idle	Windows Task Scheduler's 'Idle' schedules and options settings will be applied to scheduled tasks.	Windows Task Scheduler's 'Idle' schedules and options settings will be applied to scheduled tasks.	Windows Task Scheduler's 'Idle' schedules and options settings will be applied to scheduled tasks.	Yes

script will continue its execution if no key is pressed.

There are some restrictions to what's possible with boot time scans:

- Encrypted disks are not available for scanning, as the *exe* (*Isass.exe*) that scans encrypted files won't be available during boot time scans.
- While in Windows Safe Mode, UltraDefrag won't be able to show the test on the boot screen.

To enable and disable boot time defragmenter, we can use the GUI window or command prompt by typing the commands *boot-on/boot-off*.

Boot time modes

There are two modes in which a boot defragmenter can run.

Boot time script: Boot time script is nothing but the collection of all the disk defragmentation commands and comments. It can be found at `%windir%\system32\ud-boot-time.cmd`. To edit the boot time script, you can execute the boot-config file using the command prompt, or you can simply click on the boot time script button on the graphical interface. To terminate the boot time script and enter into interactive mode, press ESC any time while the boot time script executes.

Interactive mode: As there is no exit in boot time script, execution will enter into interactive mode once

all the boot script commands are executed. UltraDefrag will wait for the end user input by showing the following command on UltraDefrag command prompt:

Interactive mode: Type 'help' for list of supported commands

To drop from the interactive mode, hit escape. This same interactive console will appear after the boot time execution if no exit command is given. **END**

References

- [1] <http://www.makeuseof.com/tag/automate-your-hard-drive-organization-with-ultraefrag/>
- [2] <http://ultraefrag.sourceforge.net/handbook/Boot.html>
- [3] http://priede.bf.lv/ftp/pub/Utilities/DiskDefrag/UltraDefrag/UltraDefrag_Handbook_5.0.3_a4.pdf
- [4] <http://www.lectiideinformatica.net/tutoriale/utilitare/259-tutorial-video-ultraefrag-prezentare-general-a-overview.html>

By: Palak Shah

The author is a senior software engineer. She loves to explore new technologies, learn innovative concepts, and is also fond of philosophy. She can be reached at palak311@gmail.com.

THE COMPLETE MAGAZINE ON OPEN SOURCE

OpenSource
ForYou

Your favourite magazine on
Open Source is now on the Web, too.

OpenSourceForU.com

Follow us on Twitter@LinuxForYou