

Change the Status of an Entity


For more information on available statuses, see [Entity Status Types](#).

Depending on the server configuration (using the `ShowNoteOnStatusChange` key in the Central Configuration file), you might be asked to provide an action comment when changing the status of an entity. It will be visible in the **History** tab of process, operation, or DFC properties.


To Change the Entity Status in Entity Manager or Project Entity Manager

Select one or more entities and use one of the following options:


- Choose a required status from the toolbar:




- Use the right-click menu and choose **Change Status**:



- Choose **Change Status** from the **Entity** main menu:




- In the case of operations, processes, and DFCs, you can also change the status from the entity properties window:




To Change the Status of an Open Entity

Use one of the following options:


- Choose a required status from the toolbar:




- Right-click the status part of the status bar:



- Right-click the entity in Entity Explorer and choose **Change Status**:




- Choose **Change Status** from the **Entity** main menu:



To Change the Status of Default Entities in Projects or Modules

In **projects**, you can change the status of all the default entities inside the project or single PB module using Project Entity Explorer's **right-click menu** – this works only for the prototype, design in progress, development in progress, or active statuses:



To Change the Entity Status Recursively

You can change the status of the selected entity (process, operation, DFC, screen, layout, or view) and all its child entities. In the case of projects, the recursive status change occurs only within a single project and does not affect entities that are linked from referenced projects. The status change works only for the prototype, development in progress, or active statuses.

The status does not change for any dependent entities that are open in a tab.

When recursively changing the status of a DFC with linked invoked DFCs, the status of invoked DFCs changes only if they have the revision selected on the **Advanced** tab of a step properties. The status of invoked DFCs with **"(all revisions)"** selected does not change.

Select the entity and choose **Change Status Recursively** from the:

- ▶ **Entity** main menu.
- ▶ Entity Manager's **right-click menu** or Project Entity Manager's **right-click menu**.
- ▶ Entity Explorer's right-click menu of screen, view, layout, process, operation, DFC.

Rules

Changing the Status to Prototype

Changing the Status to Development in Progress

Changing the Status to Active

Changing Entity Status to Active (Releasing) with Sign-Off

If the server is configured for electronic signatures, after changing the process, operation, or DFC status to active, you need to electronically sign off on this action. First, a window appears where you can see the history of changes made in the current revision, including those made by other users or in previous revisions (which are grayed out). You can approve or reject such changes.

Approve Entity Release

History:

Date	Action	Employee	Server Name
1/27/2024 5:56 PM	Entity Save		
1/26/2024 9:02 PM	Entity Save	System Administrator (ADMIN)	

Comment:

Save: new step added.

Approve Reject Cancel Help

If changes were approved or rejected, the sign-off window appears, where you can provide a password, reason code, and optionally a comment on the action – the comments appear in the **History** tab of process, operation, and DFC properties.

- ▶ Click **Approve** – the entity status changes to active.
- ▶ Click **Reject** – the entity status does not change.

 Sign Off - Approve

Employee No:

ADMIN

Password:

Reason Code:

(none)

Comment:

Approve

Cancel

 Sign Off - Reject

Employee No:

ADMIN

Password:

Reason Code:

(none)

Comment:

Reject

Cancel

To find out if the sign off on a release has been requested, check the sign-off status on the [status bar](#).
This option can be changed with use of the `RequireSignOffOnRelease` key located in the `ProcessBuilder` section of the Central Configuration file – for details, refer to [Central Configuration Documentation](#).

Change Status Result Window

This window lists all entities for which the **Change Status** or **Change Status Recursively** options have been used. When changing the status of more than one entity, the details of the status change action are grouped into:

- ▶ **Status change succeeded** – the entity status changed.
- ▶ **Status change skipped** – the entity has already been in the required or active status or the status could not be changed because the entity was open in another tab.
- ▶ **Status change or validation failed** – changing the entity status or the entity validation failed. In such cases, validate failed entities and make the appropriate modifications.

Change Status Result			
Name	Revision	Type	Status
Status change succeeded			
 DFC1	REV.001.000	DFC	Prototype
 DFC4	REV.001.000	DFC	Prototype
Status change skipped			
 DFC2	REV.001.000	DFC	Prototype
Status change or validation failed			
 DFC3	REV.001.000	DFC	Design in Progress
 View	REV.001.000	View	Design in Progress
OpenOpen All FailedFinishHelp			

When using the **Change Status Recursively** option, the window lists the status change details also for all child entities:

Change Status Result - PortalTree - REV.001.000 (Screen)				✕
Name	Revision	Type	Status	
Status change succeeded				
 PortalTree	REV.001.000	Screen	Prototype	
Status change skipped				
 PortalOneWindow	REV.001.001	Layout	Active	
 PortalTree	REV.001.001	View	Prototype	
Status change or validation failed				
 PortalTree	REV.001.000	DFC	Design in Progress	
				Open Open All Failed Finish Help

Actions

- **Open** – redirects to the workspace of the selected one or more entities and automatically validates them.
- **Open All Failed** – redirects to the workspace of the entities under the **Status change or validation failed** node and automatically validates them.