

DFC Properties

To Launch the DFC Properties

1. In the Entity Explorer, select a DFC.
2. Choose one of the following options:
 - ▷ Choose **View > Properties** from the [main menu](#).
 - ▷ Use the `F4` [shortcut](#).

You can also open the **Entity Properties** window by selecting a DFC in the [Entity Manager](#) or [Project Entity Manager](#) and using one of the following options:

- ▷ Choose **Properties** from the right-click menu.
- ▷ Use the `Shift+F4` [shortcut](#).

DFC Properties

General Tab

Properties

General | Work Instructions | Advanced | Interface

Code

Subtype

Revision

☒ Default Revision

Description

Valid between

and

Step shown on preview



Version

Version host

Compilation date


☒ Allow editing in Prototype mode


Field	Description
Code	Translated name of the DFC. The name can be up to 80 characters long.
Subtype	Types of the DFC. Use the following subtypes: ▶ Generic ▶ View ▶ Action ▶ Change ▶ Validate ▶ Data ▶ Initialize ▶ Extension ▶ Process ▶ Interface The Labor, Machine, and Background subtypes are visible if you selected one of them when creating the DFC. For more information on the subtypes, see New Entity Wizard.
Revision	The revision of the DFC. This field is read-only.
Default Revision	The revision of the DFC that is used in runtime. It is selected by default for a newly created DFC (next revisions of the DFC are not selected as the default ones).
Description	The description of the DFC.
Valid Between	Enables changing the date range for the validity of the DFC. Values are not validated when changing. If values are incorrect, a warning is displayed during the entity validation.
Step shown on preview	The option is available only if HTML Layout Editor functionality is used. The drop-down menu enables the user to choose a step (available in this DFC) containing HTML Layout. The chosen step will be used in a Preview tool pane as a


	DFC preview or will be displayed on the Preview tool pane when the DFC becomes a sub-DFC of the other one.  If no step is selected, the sub-DFC is presented by a default sub-DFC icon (or a Visualization Image) in the Preview pane. 
Version	An auto-incremented number of a DFC that increases when you modify, save, and then compile the entity. Click Edit Mask to enter a custom mask.
Version host	The name of the last server where a DFC has been modified and then compiled.
Compilation date	The date of the latest DFC revision change.
Allow editing in Prototype mode	If enabled, the entity can be edited in the prototype status. This setting is selected when creating the entity.

Work Instructions Tab

Work instructions defined on the DFC level are visible at every step.



Field	Description
Visibility	The visibility options for work instructions: ▶ <i>Always</i> – work instructions are displayed in runtime. ▶ <i>Never</i> – work instructions are not displayed in runtime. This option is selected by default. ▶ <i>Dynamic</i> – the visibility of work instructions can be dynamically controlled by an indicated session variable of the Boolean type (if the session variable value is set to true, then the work instruction will be displayed). Work instructions in the cancelled or on hold status are not displayed in runtime. For more information, refer to Work Instructions Help.
Display Mode	The configuration of the appearance of the work instructions: ▶ <i>Sidebar</i> – work instructions are displayed in a sidebar panel that can be positioned at four different sides of the screen (in the Docking section).  ▶ <i>Pop-up</i> – work instructions are displayed in a pop-

	up window (the Show Work Instructions button appears only if the <i>Pop-up</i> option is selected). 
	▷ <i>Maximized</i> – if selected, the pop-up window is opened in a full-screen mode. The Size section is grayed out. You can change the default pop-up appearance and behavior in the <code>ficontrols.js</code> file (for more information, refer to the <code>jqModal</code> plugin documentation). Use work instructions in the pop-up mode on devices such as smartphones or tablets.
Docking	The sidebar location of work instructions: top, left, bottom, and right. Available only if the <i>Sidebar</i> display mode option is selected.
Size	The size of the sidebar and pop-up window (width and height separately). If there is more than one size set (from step or DFC), the largest size is chosen. The minimum size that you can set is 100px.
Work Instructions from	The list of available session variable outputs (list of char type) defined as work instructions in all DFC

Session Variable	steps. The session variable returns: a work instruction name or FUID of a specific work instruction revision.
------------------	---

Advanced Tab

Properties

General

Work Instructions

Advanced

Interface

Properties

Created on:

5/6/2024 9:36:36 AM (2 days ago)

Created by:

ADMIN

Modified on:

5/6/2024 4:52:00 PM (1 day ago)

Modified by:

ADMIN

ID:

100002157

FUID:

99db2a0a-cae6-4852-adad-089d148e086e

Field	Description
Properties	Additional properties that you can include using the JSON format.
Created on	Date the entity was created on.
Created by	User who created the entity.
Modified on	Date the entity was last modified on.
Modified by	User who last modified the entity.
ID	ID of the record in the database.
FUID	FUID of the record in the database.

Interface Tab

Using the **Interface** tab instead of previous [External Inputs](#) functionality is recommended.

Properties

General Work Instructions Advanced **Interface**

☒ Enable Interface

Inputs

Name	Data Type	Required
Input1	Char	☒
Input2	Char	☒
Input3	Char	☒

Test Value

Default Value

Outputs

Name	Data Type
Output1	Char
Output2	Char

Allowed output values

Value

11

*

Field	Description
Enable Interface	The Interface functionality is enabled by default for non-active DFCs. The default selection of this check box is controlled by the Enable the DFC interface by default check box (see Advanced tab in Options dialog box). If the input of the Complex or List of Complex data typ exists in the DFC, the Enable Interface check box is selected and grayed out.
(Remove all the unused External Inputs and Outputs)	Removes external inputs and outputs that are not used by any function within a DFC.
Inputs	Gives the possibility to add and remove external inputs that you can use within a DFC. You can provide the input name, set the input data type, and select if the input is required or not. The following sections are available for each external input: ▶ Test Value – the input value used in Advanced Test Run. ▶ Default Value – the value used for non-required inputs if no other value was specified for them. You can also create external inputs while editing a function. For more information, see Function Navigation Right-Click Menu.

Outputs	Gives the possibility to add and remove external outputs that you can use within a DFC. Allowed output values – makes it possible to add values to the entered outputs (except outputs of the Complex data type). You can also create external outputs while editing a function. For more information, see Function Navigation Right-Click Menu.
----------------	---