

# Security Roles

Each user that logs in to DELMIA Apriso and Process Builder can have specific security roles assigned. The availability of certain features in Process Builder depends on what security roles are assigned to the user who is logged in. The user may have more than one role assigned.

| Role name                              | Permission                                                                                                                                                                                                                                                                                                                                                                                                                  |
|----------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Process Functional Author</b>       | <p>The user is permitted to:</p> <ul style="list-style-type: none"> <li>▶ Edit processes, operations, DFCs, and their steps.</li> <li>▶ Edit screens, layouts, and views.</li> <li>▶ Run screens and DFCs in test mode.</li> <li>▶ Edit the user interface of existing elements.</li> <li>▶ Create projects, duplicate and edit project revisions.</li> <li>▶ Compare project revisions and merge them.</li> </ul>          |
| <b>Process Links Configurator</b>      | This role is required to manage the business entities links displayed in the <a href="#">Links</a> workspace.                                                                                                                                                                                                                                                                                                               |
| <b>Process Technical Author</b>        | <p>The user is permitted to:</p> <ul style="list-style-type: none"> <li>▶ Edit functions, inputs, and outputs.</li> <li>▶ Do whatever these roles are permitted to do: Process Functional Author, Process Tester, Process User Interface Author.</li> <li>▶ Create projects, duplicate and edit project revisions.</li> <li>▶ Compare project revisions and merge them.</li> </ul>                                          |
| <b>Process Tester</b>                  | <p>The user is permitted to:</p> <ul style="list-style-type: none"> <li>▶ View processes, operations, DFCs, and their steps in read-only mode.</li> <li>▶ Open screens, layouts, and views in read-only mode.</li> <li>▶ Run screens and DFCs in test mode.</li> <li>▶ Create projects, duplicate and view project revisions.</li> <li>▶ Compare project revisions.</li> </ul>                                              |
| <b>Process User Interface Author</b>   | <p>The user is permitted to:</p> <ul style="list-style-type: none"> <li>▶ View processes, operations, DFCs, and their steps in read-only mode.</li> <li>▶ Open screens, layouts, and views in read-only mode.</li> <li>▶ Edit the user interface of steps.</li> <li>▶ Run screens and DFCs in test mode.</li> <li>▶ Create projects, duplicate and view project revisions.</li> <li>▶ Compare project revisions.</li> </ul> |
| <b>Issue Management Process Author</b> | <p>The user is permitted to:</p> <ul style="list-style-type: none"> <li>▶ Access the Issue Flows Manager and manage fully Issue Flows.</li> <li>▶ Access the Issue Properties and manage fully Issue Properties.</li> </ul>                                                                                                                                                                                                 |

You must be assigned the necessary roles to access M&M screens, which are available from the [Managers](#) menu in Process Builder. The [Security](#) tab of the FlexParts screen displays the existing roles assigned to the selected M&M screen.

For detailed information on security roles, refer to [\*\*\*Role and Skill Configuration Help\*\*\*](#) .