


Step Navigation Diagram Elements

Steps

Types

There are five types of Steps that can appear in a diagram:

Item	Name	Description
	Multipurpose Step	A default generic Step.
	Multipurpose Step with Sub-DFC	A generic Step that contains a Sub-DFC inside, and therefore: ▶ A Process Technical Author can double-click it and go to the Function Navigation diagram ▶ Other users will navigate to the Sub-DFC view
	Step with User Interface	This Step contains a Function with User Interface elements.
	Decision Step	This Step has a routing output and more than one path defined.
	Return Step	This Step should be considered when the "BACK" value is used in runtime.

Structure

Each Step is composed of two bars:

Item	Name	Description
	Name Bar	Contains the Step's name and sequence number.
	Information Bar	Contains icons indicating the types of Functions within the Step on the left, an icon on the right indicating that a Step Description is present, as well as Routing Indicators.

The size of all Steps on the Flow Diagram can be changed. Simply drag the edges to reveal the entire name of a Step or to just make a Step larger.

Special Nodes

Item	Name	Description
	Start Node	The starting point for DFC processing. Only one Start item can be created in the Step Flow.
	Logout/Exit Node	Available in the toolbox. More than one Logout Node can be added. When Step Navigation advances to a Logout Node, the system will end the Function Interpreter session and return the user to the logon screen.

	Stop/End Node	Available in the toolbox. More than one Stop Node can be added. When Step Navigation advances to a Stop Node, the system will end the Function Interpreter session and return the user to the DELMIA Apriso Start page. The Stop Node is added automatically after creating a DFC.
	Back Node	Available in the toolbox. More than one Back Node can be added. In order for a Back node to work, at least one Step has to be defined as a Return Step. When Step Navigation advances to a Back node, the system will complete the Step and return to the nearest previous Step that was defined as a Return Step.
	Skip/Abandon Node	Available in the toolbox. More than one Abandon Node can be added. In order for an Abandon node to work, at least one Step has to be defined as a Return Step. When Step Navigation advances to an Abandon Node, the system will complete the Step and create a new task with the "Abandon" status, and then end the Function Interpreter session. The "Abandon" task will be the same as the previous task, but will start from the Step that was marked as a Return Step.

To Add a Special Node

Drag  (Stop/End),  (Logout/Exit),  (Back), or  (Skip/Abandon) from the [Toolbox](#) into the step navigation workspace or the DFC in Entity Explorer. Adding the  (Stop/End) node is possible also from the [right-click menu](#).

Functions within Steps

Item	Name	Description
	Machine data Input/Output	Communication with machines.
	Query Database	Database queries.
	User Interface	User interface Inputs or Outputs.
	Printing	Printing functionality.
	Processing	Calls a Business Component or Stored Procedure.
	Determination	Determination Function is used.
	Routing Function	Default Routing Function on the Decision Step.

Routing Indicators

Item	Name	Description
	Regular Routing	Indicates routing from one Step to another Step, which is dependant on the Output of a Function contained in a source Step.
	Dynamic Navigation Output	Indicates whether Dynamic Navigation is enabled for the Step. See Step Properties .

Step Descriptions

The user can [add a Step Description](#) for a chosen Step. Its visibility can be toggled by Show/Hide Step Description through the [Right-Click Menu](#).