


EXPERIMENT 7:




The screenshot shows the Arduino IDE interface. The top menu bar includes File, Edit, Sketch, Tools, and Help. Below the menu is a toolbar with icons for checking, compiling, uploading, and erasing, along with a dropdown menu set to 'Arduino UNO'. The main editor window displays a sketch named 'sketch_aug17b.ino' with the following code:

```
1 int number = 0;
2
3 void setup() {
4   Serial.begin(9600); // Initialize serial communication at 9600 baud
5 }
6
7 void loop() {
8   Serial.print("Number is ");
9   Serial.println(number); // Print current number with a newline
10  delay(500); // Wait 0.5 seconds
11  number++; // Increment the number
12 }
13
```

The bottom panel shows the 'Output' window with the following text:

```
Using precompiled core: C:\Users\trish\AppData\Local\arduino\cores\arduino_avr_uno_1854fb47367fe1f0bbc92a1cf35fbde7\core.a
Linking everything together...
"C:\Users\trish\AppData\Local\Arduino15\packages\arduino\tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-gcc" -w -Os -g -flto -fuse-linker-plugin -T
"C:\Users\trish\AppData\Local\Arduino15\packages\arduino\tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-objcopy" -O ihex -j .eeprom --set-section-
"C:\Users\trish\AppData\Local\Arduino15\packages\arduino\tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-objcopy" -O ihex -R .eeprom "C:\Users\tr
"C:\Users\trish\AppData\Local\Arduino15\packages\arduino\tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-size" -A "C:\Users\trish\AppData\Local
Sketch uses 1902 bytes (5%) of program storage space. Maximum is 32256 bytes.
Global variables use 200 bytes (9%) of dynamic memory, leaving 1848 bytes for local variables. Maximum is 2048 bytes.
```

The status bar at the bottom right indicates 'Ln 12, Col 2' and 'Arduino UNO [not connected]'.



OUTPUT:

