To Set Up Home Assistant OS

https://www.youtube.com/watch?v=hAdDtbNMYPM&list=LL&index=6

Things Needed for Home Assistant

- Raspberry Pi (3 or above recommended)
- Micro SD (minimum 32GB)
- Power supply
- An extra laptop/PC

Step 1: Download HomeAssistant OS on micro sd through Raspberry Pi Imager
Step 2: Then plug that micro sd to Raspberry Pi
Step 3: Connect to the network

Once the OS is done, it will show this.



Interface name reference:
- wlp2s0 → WiFi interface name on desktop Linux systems (systemd naming)
- wlan0 → WiFi interface name on Raspberry Pi
- eth0 → Ethernet interface name on Raspberry Pi

Choose either WiFi or Ethernet:

Option A — WiFi
Replace WIFI-NAME and WIFI-PASSWORD with your actual credentials:
network update wlan0 --ipv4-method auto --ipv6-method auto --wifi-auth wpa-psk --wifi-mode infrastructure --wifi-ssid "WIFI-NAME" --wifi-psk "WIFI-PASSWORD"
Note: wpa-psk handles both WPA2 and WPA3 automatically.

Option B — Ethernet
No credentials needed:
network update eth0 --ipv4-method auto --ipv6-method auto

After setting up the connection, verify it by running:
network info
It will show something similar to this:

```
ha > network info
docker:
  address: 172.30.32.0/23
  dns: 172.30.32.3
  gateway: 172.30.32.1
  interface: hassio
host_internet: true
interfaces:
- connected: false
  enabled: false
  interface: eth0
  ipv4:
    address: []
    gateway: null
    method: disabled
    nameservers: []
    ready: false
  ipv6:
    addr_gen_mode: default
    address: []
    gateway: null
    ip6_privacy: default
    method: disabled
    nameservers: []
    ready: false
  llmnr: null
  mac: [redacted]F
  mdns: null
  primary: false
  type: ethernet
  vlan: null
  wifi: null
- connected: true
```

After confirming the network is connected, type **exit** to return to the main OS screen.

Then it will show something like this



Now open a web browser on any device connected to the same network and type:

http://<your_ip_address_HomeAssistant>:8123

Note: You can find the IP from network info output shown earlier, or check your router's DHCP client list. Also if homeassistant.local:8123 doesn't work, try the IP address directly instead

After this, follow this tutorial to set up Home Assistant GUI
https://youtu.be/Z4gvkmJ8q48?si=Q_CZ4Q_fuJ_9Tt3x