

Conducting a SOC 2 Audit Using Hyperproof

Internal Auditors—SOC 2 Type 2

Step	Who	Overview	How to in Hyperproof
CONDUCTING SOC 2 TYPE 2 AUDIT			
Engaging External Auditor	Auditor	Internal Auditor connects with External Auditor. External Auditor sends Document Request List (DRL) to Client.	N/A
Creating the Audit in Hyperproof	Auditor	Auditor creates a new audit in Hyperproof and titles it [YEAR] SOC 2 Type 2 .	- From the left navigation menu, select <i>Audits</i>, and then click New. - Enter a name for the audit. - Click Create.
Formatting DRL as a CSV	Auditor/ Client	Auditor imports DRL into Hyperproof for collaborative review of controls and policies.	- From the left navigation menu, select <i>Audits</i>, and then select your audit. - Select the <i>Requests</i> tab. - Click Import DRL. - Download the CSV template and update it with your requests. Be sure to structure requests in the required format with desired proof in the descriptions and links to controls in the <i>Control ID</i> field.

Step	Who	Overview	How to in Hyperproof
CONDUCTING SOC 2 TYPE 2 AUDIT			
Collecting and Linking Proof to Requests	Client	Client changes request status to indicate they have started working on their requests. Client then links necessary proof to each request. If Client chooses to use labels, those must also be linked to the requests. Once proof has been linked, Client changes request status to Submitted.	1. From the left navigation menu, select <i>Audits</i>, and then select your audit. 2. Select the <i>Requests</i> tab. 3. Assign requests manually or by bulk editing. 4. Change the request status to In Progress (this can also be done by bulk editing). 5. Link proof to the requests manually or via an existing task. If using labels, click Link label to link a label to the request. 6. After proof is linked, change the request status from In Progress to Submitted.
Exporting Audit and Delivering to External Auditor	Auditor	Auditor exports audit, downloads zip file, and securely transfers file to Auditor.	1. From the left navigation menu, select <i>Audits</i>. 2. Select your audit. 3. Select ... (<i>More Options</i>), and then click Export audit.
External Auditor Reviews and Submits Follow-up Actions	External Auditor	External Auditor reviews audit and determines if all requests have been addressed.	N/A

Step	Who	Overview	How to in Hyperproof
CONDUCTING SOC 2 TYPE 2 AUDIT			
Reviewing Follow-up Actions	Auditor	If all requests have been satisfied, Internal Auditor moves on to next steps. If requests have not been satisfied, Internal Auditor updates the DRL, ensures that linked proof is satisfactory, re-exports updated audit, and then delivers to External Auditor for another review.	If requests have not been satisfied, follow steps <i>Collecting and Linking Proof to Requests</i> and <i>Exporting Audit and Delivering to External Auditor</i> on previous page.
Producing SOC 2 Type 2 Report	External Auditor	External Auditor compiles a Type 2 report, done outside of Hyperproof.	N/A
Conducting Post-mortem Audit	Auditor	Auditor and Client meet to determine the successes and failures of the audit, i.e. what went wrong, what went well, and what should be repeated in future audits.	N/A
Closing Audit in Hyperproof	Auditor	Auditor changes the status of the audit to Completed .	1. From the left navigation menu, select <i>Audits</i>, and then select your audit. 2. Select the <i>Details</i> tab. 3. Change the status from Active to Completed.