# VIDEO FREEZE

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-
master\drivers\staging\media\av7110\(linux-master)\(drivers)\((staging)\) (media)
(av7110) video-freeze.rst, line 2)
Unknown directive type "cnamespace".
.. c:namespace:: DTV.video
```

#### Name

VIDEO FREEZE

```
Attention!
```

This ioctl is deprecated.

### **Synopsis**

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\drivers\staging\media\av7110\(linux-master)\(drivers\) (staging) (media) (av7110) video-freeze.rst, line 20)
Unknown directive type "cmacro".
.. c:macro:: VIDEO_FREEZE
```

int ioctl(fd, VIDEO FREEZE)

#### **Arguments**

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-
master\drivers\staging\media\av7110\(linux-master)\(drivers)\((staging)\) (media)
(av7110) video-freeze.rst, line 27)

Unknown directive type "flat-table".

.. flat-table::
    :header-rows: 0
    :stub-columns: 0

- .. row 1

- int fd

- File descriptor returned by a previous call to open().

- .. row 2

- int request

- Equals VIDEO_FREEZE for this command.
```

## **Description**

This ioctl is for Digital TV devices only. To control a V4L2 decoder use the V4L2 ref. VIDIOC\_DECODER\_CMD' instead.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\drivers\staging\media\av7110\((linux-master)\) (drivers) (staging) (media) (av7110) video-freeze.rst, line 46); backlink

Unknown interpreted text role "ref".
```

This ioctl call suspends the live video stream being played. Decoding and playing are frozen. It is then possible to restart the decoding and playing process of the video stream using the VIDEO\_CONTINUE command. If VIDEO\_SOURCE\_MEMORY is selected in the ioctl call VIDEO\_SELECT\_SOURCE, the Digital TV subsystem will not decode any more data until the ioctl call VIDEO\_CONTINUE or VIDEO\_PLAY is performed.

#### **Return Value**

On success 0 is returned, on error -1 and the errno variable is set appropriately. The generic error codes are described at the ref. Generic Error Codes <gen-errors>` chapter.

 $System\,Message: ERROR/3 \ (\texttt{D:\noboarding-resources\sample-onboarding-resources\linux-master\drivers\staging\media\av7110\ (linux-master) \ (drivers) \ (staging) \ (media) \ (av7110) \ video-freeze.rst, line 59); backlink$ 

Unknown interpreted text role "ref".