




HO-EDGE



```
!
!
ip dhcp pool Lan1
 network 10.0.0.0 255.0.0.0
 default-router 10.0.0.1
 dns-server 8.8.8.8
!
!
no ip domain lookup
ip cef
no ipv6 cef
!
multilink bundle-name authenticated
!
!
```


Continue where you left off: Chrome can restore your tabs every time you restart. To turn this on, go to Settings.


HO-EDGE

```
interface Ethernet0/0
ip address 10.0.0.1 255.0.0.0
ip nat inside
ip virtual-reassembly in
duplex auto
!
interface Ethernet0/1
ip address 20.0.0.1 255.0.0.0
ip nat outside
ip virtual-reassembly in
duplex auto
!
interface Ethernet0/2
no ip address
duplex auto
!
interface Ethernet0/3
no ip address
duplex auto
!
ip forward-protocol nd
!
no ip http server
```

ORK
OLOGIES







DC-EDGE

```
DC-EDGE(config)#
DC-EDGE(config)#int e0/1
DC-EDGE(config-if)#ip nat outside
DC-EDGE(config-if)#exit
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#ip dhcp pool lan2
DC-EDGE(dhcp-config)#network 192.168.1.0 255.255.255.0
DC-EDGE(dhcp-config)#default-router 192.168.1.1
DC-EDGE(dhcp-config)#dns-server 8.8.8.8
DC-EDGE(dhcp-config)#exit
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#
DC-EDGE(config)#ip nat inside source static 192.168.1.2 30.0.0.10
DC-EDGE(config)#ip nat inside source static 192.168.1.3 30.0.0.10
% similar static entry (192.168.1.2 -> 30.0.0.10) already exists
DC-EDGE(config)#
*Aug  9 19:54:46.773: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
DC-EDGE(config)#ip nat inside source static 192.168.1.3 30.0.0.20
DC-EDGE(config)#
```

30.0.0.2

DC-EDGE

192.168.1.1

VPC2

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

```
VPC2> ip dhcp
DDORA IP 192.168.1.3/24 GW 192.168.1.1
VPC2> ip dhcp
```

VPC1

Executing the startup file

```
VPC1> ip dhcp
DDORA IP 192.168.1.2/24 GW 192.168.1.1
```

```
VPC1> ship
Bad command: "ship". Use ? for help.
```

```
VPC1> sh ip
```

```
NAME       : VPC1[1]
IP/MASK    : 192.168.1.2/24
GATEWAY    : 192.168.1.1
DNS        : 8.8.8.8
DHCP SERVER : 192.168.1.1
DHCP LEASE  : 86373, 86400/43200/75600
MAC        : 00:50:79:66:68:ef
LPORT      : 20000
RHOST:PORT  : 127.0.0.1:30000
MTU        : 1500
```

```
VPC1>
```

