



SUBNETTING

HR 50-PC

PRODUCTION 120-PC

SALES 250-PC





```
VPC-1
Modified version for EVE-NG.
Press '?' to get help.
Executing the startup file

VPC-1> ip dhcp
DDORA IP 50.0.1.132/26 GW 50.0.1.129

VPC-1> sh ip

NAME       : VPC-1[1]
IP/MASK    : 50.0.1.132/26
GATEWAY    : 50.0.1.129
DNS        : 8.8.8.8
DHCP SERVER : 50.0.1.197
DHCP LEASE  : 86396, 86400/43200/75600
MAC        : 00:50:79:66:68:be
LPORT      : 20000
RHOST:PORT  : 127.0.0.1:30000
MTU        : 1500


VPC-1>

Modified version for EVE-NG.
Press '?' to get help.
Executing the startup file

VPC-2> ip dhcp
DDORA IP 50.0.1.12/25 GW 50.0.1.1

VPC-2> sh ip

NAME       : VPC-2[1]
IP/MASK    : 50.0.1.12/25
GATEWAY    : 50.0.1.1
DNS        : 8.8.8.8
DHCP SERVER : 50.0.1.1
DHCP LEASE  : 86146, 86400/43200/75600
MAC        : 00:50:79:66:68:bf
LPORT      : 20000
RHOST:PORT  : 127.0.0.1:30000
MTU        : 1500
```



```

R1
Sending 5, 100-byte ICMP Echos to 50.0.0.1, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms
R1#sh ip int brief
Interface IP-Address OK? Method Status Prot
ccol
Ethernet0/0 50.0.1.129 YES manual up up
Ethernet0/1 50.0.1.198 YES manual up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down

R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip helper-address 50.0.1.197
^
% Invalid input detected at '^' marker.

R1(config)#int e0/0
R1(config-if)#ip helper-address 50.0.1.197
R1(config-if)#exit
R1(config)#


```

```

R2
R2#sh ip int brief
Interface IP-Address OK? Method Status Prot
ccol
Ethernet0/0 50.0.1.1 YES manual up up
Ethernet0/1 50.0.1.197 YES manual up up
Ethernet0/2 50.0.1.194 YES manual up up
Ethernet0/3 unassigned YES TFTP down down

R2#sh ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PBR

```



```

R3
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms
R3#ping 50.0.1.197
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 50.0.1.197, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms
R3#sh ip int brief
Interface IP-Address OK? Method Status Prot
ccol
Ethernet0/0 50.0.0.1 YES manual up up
Ethernet0/1 50.0.1.193 YES manual up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down

R3#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#int e0/0
R3(config-if)#ip helper-address 50.0.1.194
R3(config-if)#exit

```

R2

```
!!  
!!  
!!  
ip dhcp excluded-address 50.0.0.1 50.0.0.10  
ip dhcp excluded-address 50.0.1.1 50.0.1.10  
ip dhcp excluded-address 50.0.1.128 50.0.1.130  
!  
ip dhcp pool SALE  
  network 50.0.0.0 255.255.255.0  
  default-router 50.0.0.1  
  dns-server 8.8.8.8  
!  
ip dhcp pool PRO  
  network 50.0.1.0 255.255.255.128  
  default-router 50.0.1.1  
  dns-server 8.8.8.8  
!  
ip dhcp pool HR  
  network 50.0.1.128 255.255.255.192  
  default-router 50.0.1.129  
  dns-server 8.8.8.8  
!  
!  
no ip domain lookup  
ip cef  
R2#
```

50.0.0.0/8