



Hybrid Secure Data Storage — User Manual

Version 2.0 · July 2026

Contents

1. Getting Started — Login & Registration
2. Dashboard Overview
3. File Management — Upload, Organize, Search
4. Data Records — Structured Data Tables
5. Companies — Multi-Tenant Management
6. User Management — Roles & Permissions
7. Storage Quotas — Limits & Monitoring
8. Organization Settings
9. Security Features
10. Roles & Permissions Reference

1. Getting Started

Accessing OrgVault

Open your browser and go to: `https://storageapp.boosterappsolutions.com`

Creating an Account

- 1 On the login page, click **"Don't have an account? Create one"**
- 2 Enter your **Full Name**, **Organization Name**, **Email**, and **Password** (min. 12 characters)
- 3 Click **"Create Account"** — you'll be logged in automatically

Note: The first person to register with an organization name becomes the Organization Admin.

Logging In

- 1 Enter your **Email** and **Password**
- 2 Click **"Sign In"**

Sessions last 24 hours. Log out via the **"Sign Out"** button at the bottom of the sidebar.

2. Dashboard

The Dashboard is your home screen, showing a real-time overview of your organization's storage.

Stats Cards

Card	Meaning
Total Files	Number of files across your org or selected company
Folders	Number of organizational folders
Storage Used	Total space consumed (auto-formatted: B → KB → MB → GB)
Synced to Cloud	Files backed up to cloud storage

Recent Files

Shows your 5 most recent uploads. Click **"View all →"** to go to the Files page.

Company Selector

In the top-right header, use the **company dropdown** to switch between company views. Select "All Companies" to see everything, or pick a specific company to scope all views.

3. File Management

Access via **Files** in the left sidebar.

Uploading Files

- 1 **Drag & Drop** files onto the dashed zone, or click to browse
- 2 Optionally assign a **folder** (e.g., `invoices/2024`) and **tags** (comma-separated)
- 3 Files are encrypted with AES-256-GCM before storage

Limits: 500 MB max per file. Upload blocked if storage quota is exceeded.

Folder Navigation

Click a folder card to filter files within it. Use the breadcrumb trail (`Root > invoices > 2024`) to navigate back.

Tag Filtering

Click any tag on a file to filter the list by that tag. Remove the filter by clicking ✕ on the active tag pill.

Search

Use the search bar to find files by name. Results update as you type.

Download & Delete

Hover over a file row to reveal action buttons: ↓ Download (decrypted) and 🗑 Delete (soft-delete, recoverable).

4. Data Records

Store structured data in custom tables. Access via **Data Records** in the sidebar.

Creating a Table

- 1 Click "**New Table**"
- 2 Enter a name (e.g., `Contacts` , `Invoices`)
- 3 Press Enter or click "**Create**"

Working with Records

Add: Select a table → click "**Add Record**" → enter JSON data → Create

Edit: Hover a record →  → modify JSON → Update

Delete: Hover a record →  → confirm

Copy: Use the  button to copy record IDs or JSON data

Example record: `{"name": "John Doe", "email": "john@example.com", "phone": "+234 800 000 0000"}`

5. Companies

Companies are sub-tenants within your organization for data isolation. Access via **Companies** in the sidebar.

Adding a Company

- 1 Click "**Add Company**"

2 Enter the company name

3 Click "**Create**"

Once created, you can assign users to this company, set storage quotas, and files will be scoped.

6. User Management

Access via **Users** in the sidebar. Available to org_admin and superadmin roles only.

Adding Users

1 Click "**Add User**"

2 Fill in name, email, password

3 Select a **role** and optionally assign to a **company**

4 Click "**Create User**"

Editing Users

Hover a user row → click  → change their **role** or **company** inline → click  to save.

Deactivating Users

Hover a user row → click  → confirm. They can no longer log in, but their data is preserved.

7. Storage Quotas

Access via **Settings** → **Storage Quota** section.

Organization Quota

A colored usage bar shows current consumption. Enter a value in GB and click **"Set Quota"**. Set to 0 for unlimited.

Company Quotas

Each company can have its own limit. Enter GB per company → click **"Set"**. Companies with no limit set have unlimited storage (capped only by the org quota).

Who controls quotas: Only org_admin and superadmin can set quotas. Company admins and members can view usage but can't change limits.

8. Organization Settings

Access via **Settings** in the sidebar.

Section	What you can do
General	Change organization name, view organization ID
Storage Quota	Set org and per-company storage limits with usage bars
Security	View encryption and authentication status (read-only)
Danger Zone	Delete organization (restricted)

9. Security

- **Encryption:** AES-256-GCM at rest, unique per-file keys via PBKDF2
- **Passwords:** Argon2id hashing — industry standard
- **Sessions:** 24h access tokens + 7d rotating refresh tokens
- **Rate Limiting:** Brute-force protection on login endpoints
- **Audit Logging:** All mutations logged with user ID, IP, and timestamp
- **Data Isolation:** Org-scoped queries, company-level filtering

10. Roles & Permissions

Role	Badge Color	Capabilities
Superadmin	superadmin	Full access across all orgs. Create superadmins, delete orgs, set quotas.
Org Admin	org_admin	Manage org: users, companies, quotas, all data. Cannot create superadmins.
Company Admin	company_admin	Manage their company: files, records, users in that company.
Member	member	Upload files, create records, edit own data.
Viewer	viewer	Read-only: view files and records, cannot modify.