

Clock Configuration

Project Manager

Software Packs


Pinout




Pinout view



System view







Pinout & Configuration

Clock Configuration

Software Packs

Pinout



Categories A->Z

System Core >

Analog >

Timers >

RTC

TIM1

⚠ TIM2

✔ TIM3

TIM4

Connectivity >

Computing >

Middleware and Software Packs >

TIM2 Mode and Configuration

Mode

Slave Mode Trigger Source Clock Source Channel1 Channel2 Channel3 Channel4 Combined Channels ☐ Use ETR as Clearing Source☐ XOR activation

Configuration

Reset Configuration

✔ NVIC Settings

✔ DMA Settings

✔ GPIO Settings

✔ Parameter Settings

✔ User Constants

Configure the below parameters :



Counter Settings

Prescaler (PSC - 16 bits value) 71

Counter Mode Up

Counter Period (AutoReload Register - .999

Internal Clock Division (CKD) No Division

auto-reload preload Disable

Trigger Output (TRGO) Parameters



Pinout & Configuration

Clock Configuration

Software Packs

Pinout



Categories

A->Z

System Core >

Analog >

Timers >

RTC

TIM1

TIM2

TIM3

TIM4

Connectivity >

Computing >

Middleware and Software Packs >

TIM3 Mode and Configuration

Mode

Slave Mode Trigger Source ☒ Internal ClockChannel1 Channel2 Channel3 Channel4 Combined Channels ☐ XOR activation☐ One Pulse Mode

Configuration

Reset Configuration

☒ Parameter Settings☒ User Constants☒ NVIC Settings☒ DMA Settings

Configure the below parameters :



Counter Settings

Prescaler (PSC - 16 bits value) 7199

Counter Mode Up

Counter Period (AutoReload Register - 4999

Internal Clock Division (CKD) No Division

auto-reload preload Disable

Trigger Output (TRGO) Parameters

Master/Slave Mode (MSM bit) Disable (Trigger input effect not delayed)



Pinout & Configuration

Clock Configuration

Software Packs

Pinout



Categories

A->Z

System Core >

Analog >

Timers >

RTC

TIM1

TIM2

TIM3

TIM4

Connectivity >

Computing >

Middleware and Software Packs >

TIM3 Mode and Configuration

Mode

Slave Mode Trigger Source ☒ Internal ClockChannel1 Channel2 Channel3 Channel4 Combined Channels ☐ XOR activation☐ One Pulse Mode

Configuration

Reset Configuration

Parameter Settings

User Constants

NVIC Settings

DMA Settings

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

Pinout & Configuration

Clock Configuration

▼ Software Packs

▼ Pinout



Categories

A->Z

System Core >

Analog >

Timers >

Connectivity >

CAN

I2C1

☒ I2C2

SPI1

SPI2

USART1

☒ USART2

☒ USART3

USB

Computing >

Middleware and Software Packs >

I2C2 Mode and Configuration

Mode

I2C

I2C

Configuration

Reset Configuration

☒ NVIC Settings

☒ DMA Settings

☒ GPIO Settings

☒ Parameter Settings

☒ User Constants

Configure the below parameters :



▼ Master Features

I2C Speed Mode

Standard Mode

I2C Clock Speed (Hz)

100000

▼ Slave Features

Clock No Stretch Mode

Disabled

Primary Address Length selection

7-bit

Dual Address Acknowledged

Disabled

Pinout & Configuration

Clock Configuration

Software PacksPinout

CategoriesA->Z

System Core

- DMA
- GPIO
- IWDG
- NVIC
- RCC
- SYS
- WWDG

Analog>

Timers>

Connectivity

- CAN
- I2C1
- I2C2
- SPI1
- SPI2
- USART1
- USART2
- USART3
- USB

Computing>

GPIO Mode and Configuration

Configuration

Group By Peripherals

GPIOI2CRCCTIM

Search Signals

Search (Ctrl+F)

☐ Show only Modified Pins

Pin Na...	Signal on ...	GPIO outp...	GPIO mode	GPIO Pull...	Maximum ...	User Label	Modified
PA1	n/a	n/a	Input mode	Pull-up	n/a		☒
PA2	n/a	n/a	Input mode	Pull-up	n/a		☒
PA3	n/a	n/a	Input mode	Pull-up	n/a		☒

?

Select Pins from table to configure them. **Multiple selection is Allowed.**