

DHCP

ŚCIEZKA /etc/default ----->>> konfiguracja pliku isc-dhcp-server

```
GNU nano 7.2                                isc-dhcp-server *
# Defaults for isc-dhcp-server (sourced by /etc/init.d/isc-dhcp-server)

# Path to dhcpd's config file (default: /etc/dhcp/dhcpd.conf).
#DHCPDv4_CONF=/etc/dhcp/dhcpd.conf
#DHCPDv6_CONF=/etc/dhcp/dhcpd6.conf

# Path to dhcpd's PID file (default: /var/run/dhcpd.pid).
#DHCPDv4_PID=/var/run/dhcpd.pid
#DHCPDv6_PID=/var/run/dhcpd6.pid


# Additional options to start dhcpd with.
#       Don't use options -cf or -pf here; use DHCPD_CONF/ DHCPD_PID instead
#OPTIONS=""

# On what interfaces should the DHCP server (dhcpd) serve DHCP requests?
#       Separate multiple interfaces with spaces, e.g. "eth0 eth1".
INTERFACESv4="nazwa_karty_sieciowej"
INTERFACESv6=""
```

Następnie wchodzimy do

/etc/dhcp ----->>> konfigurujemy plik dhcpd.config

Restart = sudo systemctl restart isc-dhcp-server



```
authoritative;

# Use this to send dhcp log messages to a different log file (you also
# have to hack syslog.conf to complete the redirection).
#log-facility local7;

# No service will be given on this subnet, but declaring it helps the
# DHCP server to understand the network topology.

#subnet 10.152.187.0 netmask 255.255.255.0 {
#}

# This is a very basic subnet declaration.

#subnet 10.254.239.0 netmask 255.255.255.224 {
#   range 10.254.239.10 10.254.239.20;
#   option routers rtr-239-0-1.example.org, rtr-239-0-2.example.org;
#}

# This declaration allows BOOTP clients to get dynamic addresses,
# which we don't really recommend.

#subnet 10.254.239.32 netmask 255.255.255.224 {
#   range dynamic-bootp 10.254.239.40 10.254.239.60;
#   option broadcast-address 10.254.239.31;
#   option routers rtr-239-32-1.example.org;
#}

# A slightly different configuration for an internal subnet.
subnet 172.168.15.0 netmask 255.255.255.0 {
    range 172.168.15.100 172.168.15.150;
    option domain-name-servers 172.168.15.1;
    # option domain-name "";
    #option subnet-mask 255.255.255.0;
    option routers 172.168.15.1;
    option broadcast-address 172.168.15.255;
    default-lease-time 600;
    max-lease-time 7200;
}
```