

Project: gHRMPlus

App Settings

Basic Info

App Settings are flags to deliver different versions of apps to different clients.

Location (Declaration)

Helpers\AppSetting.cs

Location (Data)

App_Data\AppSetting.json

Name	Type	Description
LEAVE_AUTO_ADJUSTMENT_DISABLED	boolean	When enabled leave adjustment needs to be done manually. default false
LEAVE_ENTRY_PAGE_SHOW_LEAVE_DAY_DURATION	boolean	When enabled leave entry page will show option leave day duration full/half, default false
OFFICE_EDIT_PAGE_OFFICE_MAPPING_ENABLED	boolean	When enable office mapping can be updated on office edit page, default false
EMPLOYEE_PERSONAL_REPORT_PAGE_EMPLOYEE_CODE_MODIFY_ALLOW_FOR_USER_ROLE	string	An user role than can change employee code on page Employee Personal Report, default empty
LEAVE_TYPE_TOTAL_MAX_LEAVE_DAYS_ENABLED	boolean	When enabled will show option total max leave days on page Leave Type Setup, default false
SERVICE_BOOK_REPORT_HEIGHT_CONVERT_INCHES_TO_CM	boolean	When enabled on Service Book report height data will be converted from inches to cm, default false
EMPLOYEE_EDIT_PAGE_CODE_EDIT_ENABLED	boolean	When enabled employee code will be editable on Employee Edit page, default false
EMPLOYEE_MONTHLY_SALARY_REPORT_TEMPLATE	string	Employee monthly salary report has multiple templates (GT MigraDoc), default empty Note: GT template is an SSRS report with hardcoded components. MigraDoc report is a dynamic report.
DASHBOARD_ENABLED	boolean	When enabled Dashboard is visible on Software home page, default false Note: Currently there are hardcoded employee Ids for which dashboard is visible, as instructed by HR Admin Biplob vai

SUPER_ADMIN_EMPLOYEEID	string	Super Admin is an inactive (Resigned) Employee used by a support person. Since an inactive employee can not access the software, a flag was added on software to give super admin access, default empty
FUND_TRANSFER_APPLICATION_AND_ADVICE_TO_BANK_REPORT_TEMPLATE	string	Fund transfer application and advice to bank report has multiple templates (GSSB), default empty

Note: Default values are set on Helpers\AppSetting.cs file and may be changed.

App Settings on Web Config

Basic Info

App Settings are also added on the Web config file.

```
<add key="SETTING.NAME_OF_SETTING" value="VALUE_OF_SETTING" />
```

Name	Type	Description
EMPLOYEE_GROSS_SALARY_IS_TWICE_OF_BASIC_SALARY	boolean	When enabled on attendance report overtime calculation (gross salary = basic salary x 2) else gross salary is taken from salary configuration, default false
EL_ENCASHMENT_CONFIGURATION_STAGE_DEFAULT	string	On EI encashment configuration page sets Stage field default value, default none
EL_ENCASHMENT_CONFIGURATION_STAGE_DISABLE	boolean	When enable on EI encashment configuration page disables Stage field, default false
EL_ENCASHMENT_ENTRY_STAGE	string	EI encashment configuration page Entry Stage Field value, default "Other"
MANUAL_LEAVE_ENCASHMENT_BLOCK_IF_ENCASHED_DAYS	int	Block Manual Leave Encashment Page Entry if encashed for x days previously, default 0 (For GC only)
EMPLOYEE_ENTRY_HEIGHT_UNIT	string	Unit Type for height on page Employee Setup, default "Cm."
PERSONAL_INFO_EMPLOYEE_REPORT_HIDE_TAB_COMPANYREPORT	boolean	When enabled show tab company report (caption of tab is company code) on page Personal info employee report, default false (True for JCF only)
TRANSFER_OFFICE_ORDER_REPORT_SHOW_BTN_COMPANYREPORT	boolean	When enabled show button for company report on page Transfer office order report, default false (True for JCF only)
EMPLOYEE_TRANSFER_INDICATOR_REPORT_SHOW_BTN_COMPANYREPORT	boolean	When enabled show button for company report on page Employee Transfer Indicator

		Report, default false (True for JCF only)
--	--	--