

Database Migration

Source

Legacy Customer DB

Destination


New Data Warehouse

Use:

- OLE DB Source
- Data Flow
- OLE DB Destination

Add OLE DB Source

- In **Data Flow**, drag **OLE DB Source**
- Double-click it
- Select:
 - **Connection Manager** → choose source DB
- Data Access Mode:
 - **Table or View**
- Select table:
 - Employees
- Click **Preview** to check data
- Click **OK**



OLE DB Source Editor

Configure the properties used by a data flow to obtain data from any OLE DB provider.

Connection Manager
Columns
Error Output

Specify an OLE DB connection manager, a data source, or a data source view, and select the data access mode. If using the SQL command access mode, specify the SQL command either by typing the query or by using Query Builder.

OLE DB connection manager:
f726fa6f16e2563.ssis_db.sa New...

Data access mode:
Table or view

Name of the table or the view:
[dbo].[Employees]

Preview...

Preview Query Results


Query result (up to the first 200 rows):

emp_id	name	salary
1	Raj	50000
2	Anita	60000
3	Amit	55000
4	Sushil	45000
5	Rina	48000
6	Suman	52000
7	Pooja	47000
8	Vikram	61000
9	Ravi	53000
10	Meera	59000
11	Shweta	57000
12	Nitin	55000
13	Neha	62000
14	Siddhant	54000

Close

Add OLE DB Destination

- In **Data Flow**, drag **OLE DB Destination**
- Double-click it
- Select:
 - **Connection Manager** → choose destination DB
- Data Access Mode:
 - **Table or View**
- Create or Select table:
 - ssid_db_emp
- Map the columns
- Click **Preview** to check data
- Click **OK**



Configure the properties used to insert data into a relational database using an OLE DB provider.

Connection Manager

Mappings

Error Output

Specify an OLE DB connection manager, a data source, or a data source view, and select the data access mode. If using the SQL command access mode, specify the SQL command either by typing the query or by using Query Builder. For fast-load data access, set the table update options.

OLE DB connection manager:

F726FA6F16E2563.company_db.sa

New...

Data access mode:

Table or view - fast load

Name of the table or the view:

[ssid_db_emp]


New...

☐ Keep identity☒ Table lock☐ Keep nulls☒ Check constraints

Rows per batch:

Maximum insert commit size:

2147483647



Configure the properties used to insert data into a relational database using an OLE DB provider.

Connection Manager
Mappings
Error Output

The diagram illustrates the mapping between source and destination columns. On the left, a box labeled "Available I..." contains a list of columns: "Name", "emp_id", "name", and "salary". On the right, a box labeled "Available D..." contains a list of columns: "Name", "emp_id", "name", and "salary". Three horizontal arrows connect the columns: one from "emp_id" to "emp_id", one from "name" to "name", and one from "salary" to "salary".

Input Column	Destination Column
emp_id	emp_id
name	name
salary	salary

Final Data Flow

OLE DB Source



OLE DB Destination



Destination DB

A screenshot of the SQL Server Enterprise Manager interface. The top pane shows a query: `select * from ssid_db_emp;`. Below the query, the 'Results' tab is selected, displaying a table with 6 rows and 4 columns: emp_id, name, and salary. The bottom status bar shows a green checkmark and the text 'Query executed successfully.'

	emp_id	name	salary
1	1	Raj	50000
2	2	Anita	60000
3	3	Amit	55000
4	4	Sushil	45000
5	5	Rina	48000
6	6	Suman	52000