
Example of RIP configurations:



Router1:

```
Router>enable
Router#conf ter
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int f0/0
Router(config-if)#ip add 1.1.1.2 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to
up
Router(config-if)#exit
Router(config)#int s0/0/0
Router(config-if)#ip add 1.1.6.1 255.255.255.0
Router(config-if)#clock rate 64000
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Router(config-if)#exit
Router(config)#int s0/0/1
Router(config-if)#ip add 1.1.2.1 255.255.255.0
```

```
Router(config-if)#clock rate 64000
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
Router(config-if)#exit
Router(config)#router rip
Router(config-router)#network 1.0.0.0
Router(config-router)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

     1.0.0.0/24 is subnetted, 1 subnets
C       1.1.1.0 is directly connected, FastEthernet0/0
Router#
```

Router2：

```
Router>enable
Router#conf ter
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int f0/0
Router(config-if)#ip add 1.1.5.2 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to
up
Router(config-if)#exit
Router(config)#int s0/0/1
Router(config-if)#ip add 1.1.2.2 255.255.255.0
Router(config-if)#clock rate 64000
Router(config-if)#no shutdown
```

```
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
Router(config-if)#exit
Router(config)#int s0/0/0
Router(config-if)#ip add 1.1.3.1 255.255.255.0
Router(config-if)#clo rate 64000
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Router(config-if)#exit
Router(config)#router rip
Router(config-router)#network 1.0.0.0
Router(config-router)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router#
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

     1.0.0.0/24 is subnetted, 3 subnets
R       1.1.1.0 [120/1] via 1.1.2.1, 00:00:11, Serial0/0/1
C       1.1.2.0 is directly connected, Serial0/0/1
C       1.1.5.0 is directly connected, FastEthernet0/0
Router#
```

Router3：

```
Router>en
Router#conf ter
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int f0/0
Router(config-if)#ip add 1.1.4.2 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to
up
```

```
Router(config-if)#exit
Router(config)#int s0/0/0
Router(config-if)#ip add 1.1.6.2 255.255.255.0
Router(config-if)#clo rate 64000
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
Router(config-if)#exit
Router(config)#int s0/0/1
Router(config-if)#ip add 1.1.3.2 255.255.255.0
Router(config-if)#clock rate 64000
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
Router(config-if)#exit
Router(config)#router rip
Router(config-router)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to up
Router(config-router)#network 1.0.0.0
Router(config-router)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router#show ip rou
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

     1.0.0.0/24 is subnetted, 6 subnets
R       1.1.1.0 [120/1] via 1.1.6.1, 00:00:02, Serial0/0/0
R       1.1.2.0 [120/1] via 1.1.6.1, 00:00:02, Serial0/0/0
                [120/1] via 1.1.3.1, 00:00:10, Serial0/0/1
C       1.1.3.0 is directly connected, Serial0/0/1
C       1.1.4.0 is directly connected, FastEthernet0/0
R       1.1.5.0 [120/1] via 1.1.3.1, 00:00:10, Serial0/0/1
C       1.1.6.0 is directly connected, Serial0/0/0
```