

WasteFlow

Platform Guide — how the platform works, and every login

PURPOSE	End-to-end walkthrough of every WasteFlow portal, role, and login
AUDIENCE	Internal reference for the WasteFlow team
COVERS	Contractor, Operator, Superadmin, Admin console, Site Portal
LAST UPDATED	18 July 2026

1. How WasteFlow Works — At a Glance

WasteFlow is a skip-hire logistics marketplace. A Contractor raises a pickup request, an Operator accepts and fulfils it, and a Superadmin oversees accounts platform-wide. On top of that original flow, WasteFlow now has a second, organisation-based layer: an Admin console manages Contractor Organisations (each with its own Sites) and Operator Organisations (each with its own fleet and GBP price list), and each Site gets its own Site Manager login to request skips directly, with pricing generated automatically.

- Contractor — raises a pickup request and tracks it through to completion.
- Operator — accepts requests, dispatches a driver, and marks jobs complete.
- Superadmin — oversees every operator/contractor account and KYC status.
- Admin console (new) — manages Contractor/Operator Organisations, fleet, and pricing.
- Site Portal (new) — a single site's self-serve request flow with live GBP pricing.

2. Contractor Flow

Sign up and get approved

1. Go to /signup and choose "Contractor" — enter name, email and password.
2. Verify your email address, then complete the KYC form at /kyc.
3. Once KYC is approved, sign in at /login and land on your dashboard at /contractor.

Request and track a pickup

1. From /contractor/myrequests, start a new request: waste type, location, volume, date window, availability, and notes.
2. Track the request's status on a live timeline: submitted !' accepted by o completed.
3. Once complete, view the site photo and signature captured on collection, and download a full PDF report with a timestamped timeline of every stage.

3. Operator Flow

Sign up and get approved

1. Go to /signup and choose "Operator" — enter name, email and password.

2. Verify your email, then complete the KYC form at /kyc.
3. Once KYC is approved, sign in at /login and land on your dashboard at /operators.

Fulfil a pickup

1. From /operators/requests, review incoming requests and accept the ones you can fulfil.
2. Move the job through its stages: Scheduled !' Arriving !' In Transit.
3. To complete the job, enter the Site Foreman's name, upload a site photo, and capture their signature.
4. The completed job appears in /operators/history, with its own downloadable report.

4. Superadmin — Platform Oversight

The Superadmin role oversees every operator and contractor account on the platform. It signs in through its own dedicated screen at /superadmin (not through the regular /login), and cannot be created through self-serve signup.

- Review and approve/reject KYC submissions, with a reason shown back to the applicant.
- Suspend or reinstate any operator/contractor account.
- View live counts of accounts and pickups by status, and a full activity log.
- Account is provisioned by running seed-superadmin.ts once against the Firebase project.

5. Admin Console — Organisations, Fleet & Pricing

The Admin console is the newest addition: a back-office for managing the multi-tenant structure behind Contractor and Operator organisations. It signs in at /admin, gated to the "admin" or "superadmin" role.

Contractor Organisations

- Create a Contractor Organisation, then onboard its Sites — each with a name, address, and the hazardous/non-hazardous waste types it generates.
- Onboarding a Site automatically creates a real login for that Site's manager (see Section 6).

Operator Organisations

- Create an Operator Organisation, then onboard its Fleet Operators — driver name, mobile number, vehicle registration, licence upload, and which skip sizes their vehicle can carry (Small fleet: 4–14 yard, or Roll-on-roll-off: 20–40 yard).
- Maintain a GBP price list for every skip size, seeded with placeholder prices until real figures are entered.
- Dispatch incoming requests: only fleet operators whose capacity matches the requested skip size can be assigned, and every requested skip/quantity must be fulfilled before dispatch is confirmed.
- Download a Waste Transfer Note (PDF) for any dispatched or completed request.

Account is provisioned by running seed-admin.ts once against the Firebase project.

6. Site Portal — Self-Serve Site Requests

Each Site gets its own login, created for it by an Admin when the site is onboarded — there is no self-signup. The Site Manager signs in at /site-portal.

1. Sign in at /site-portal with the email and password an Admin set up when the site was created.
2. Start a new request: choose an operator, a waste type, then one or more skip size + quantity lines.
3. Watch the GBP total update live as sizes and quantities are chosen, pulled from that operator's price list.
4. Submit — the price is locked in and re-verified server-side against the live price list so it can't be tampered with.
5. Track the site's request history and status (pending !' dispatched !' completed !') on the site manager dashboard.

7. All Login Access Points

PORTAL	LOGIN URL	WHO SIGNS IN	HOW THE ACCOUNT IS CREATED
Contractor	/login	Any contractor	Self-signup at /signup
Operator	/login	Any operator	Self-signup at /signup
Superadmin	/superadmin	Platform staff	seed-superadmin.ts (Admin SDK, one-off script)
Admin console	/admin	Platform staff	seed-admin.ts (Admin SDK, one-off script)
Site Portal	/site-portal	One site manager per site	Created from /admin when a site is onboarded

8. Default Seed Credentials

These are placeholder values written into the seed scripts themselves — they are not fetched from any live account. Run the relevant script once, sign in, and change the password immediately afterwards. Never commit ServiceAccountKey.json to version control.

Superadmin

/superadmin

EMAIL superadmin@wasteflow.co.uk

npx tsx seed-superadmin.ts

PASSWORD ChangeMe123!

Admin console

/admin

EMAIL admin@wasteflow.co.uk

npx tsx seed-admin.ts

PASSWORD ChangeMe123!

9. Data Model at a Glance

COLLECTION	HOLDS
users	Contractor / Operator / Admin / Superadmin accounts, KYC status
wasteRequests	Original single-operator pickup requests and their fulfilment
contractorOrgs / sites	V2 Contractor Organisations and their Sites
operatorOrgs / fleetOperators / priceList	V2 Operator Organisations, fleet, and GBP pricing
siteManagers	One profile per Site Portal login
orgRequests	V2 site-originated requests: sizes, quantities, price, dispatch