ThreatTrace Deployment Guide

Product Introduction


ThreatTrace is a Network Detection and Response (NDR) solution specialized in detecting Advanced Persistent Threats (APTs). It monitors full-network traffic to identify both known and unknown threats, delivering comprehensive cyber threat visibility. The platform integrates signature-based detection with extensive threat intelligence, and excels at deep analysis of files transmitted across the network. Its proprietary detection engine, combined with a customized sandbox for dynamic simulation, enables rapid identification and analysis of:

- Malicious documents
- Malware
- Malicious webpages
- Unauthorized external communications
- Internal network attacks

Deployment and Installation

Deployment

Threat Trace operates in capture/passive listening mode, receiving mirrored traffic for real-time network analysis.




USB Installation


Attached: ISO Image Tool (rufus-3.17p.7z)

rufus-3.17p_.7z
1.35MB


Insert the USB boot device and wait for the following page to appear, then select "Graphical Install."




Select a language



Select your location



Configure the clock



After the installation is completed

Basic Usage Configuration

Configure Management Network


Connect the monitor directly to the device and log in with the admin account for configuration.

Default account and password:


admin/NDR1234!@#$

Or

admin/Admin1234!




Configure Network



Login the Web Management HomePage

In the browser address bar, enter https://<appliance_IP_address> to login the Web Management HomePage.




Activate Product License

The System can only detect traffic and update signature databases after being activated with a license file.

SystemManagement > **System Information**


Import License File



Set up a Monitoring Port

At least one interface must be set as a monitoring port to observe network traffic.


1. **SystemManagement** > **Network Settings** > **Interface Settings**.
2. In the Edit Interface dialog box, set the Interface Type to Monitoring Port.



Upgrade

Version Upgrade


please go to **SystemManagement** > **Version Upgrade**



Pattern Library Upgrade

Online Update

Go to **SystemManagement** > **Pattern Library Upgrade**


ThreatTrace
Monitor Center
Threat Center
Investigation & Analysis
Asset Center
Response Center
Security Reports
System Management
English
Basic Config
Rule Config
Policy Config
Integration
AI Model
Sandbox Mi
Update & M
Version Upgr..
Pattern Librar.
Device Mana...
Storage Main..
Pattern Code Update
Client Update Configuration
Configure Update Source
Preset Update
Pattern Update Source Connectivity Test
Update Source
Manual Update
Pattern Overview
Indicator of Compromise Detection Signature
Current version: 3.102.0.376
Latest version: 3.102.0.398
Last Updated Time: 2026/02/08 09:06:17
Anti-Virus Signature
Current version: 5.100.0.129
Latest version: 5.100.0.149
Last Updated Time: 2026/02/08 09:06:17
Anti-Virus Machine Learning Model
Current version: 3.1.0.027
Latest version: 3.1.0.027
Last Updated Time: 2026/02/08 09:06:17
Network Attack Detection Signature
Current version: 3.0.0.188
Latest version: 3.0.0.217
Last Updated Time: 2026/02/08 09:06:17
Orchestrated RootCause Analyzer
Current version: 3.500.0.037
Latest version: 3.500.0.037
Last Updated Time: 2026/02/08 09:06:17
Engine Overview
Anti-Virus Engine
Current version: 5.5.0.1006
Last Updated Time: 2026/02/08 09:06:17
Indicator of Compromise Detection Engine
Current version: 3.6.3.3007
Last Updated Time: 2026/02/08 09:06:17
Network Attack Detection Engine
Current version: 6.2.0.1010
Last Updated Time: 2026/02/08 09:06:17