
kali
us
30 Apr, 08:05
Enter your username
Enter your password
Cancel
Log In
KALI


1 2 3 4
8:11
Home
File System
Trash

Entramos con usuario root y ejecutamos ifconfig



En Windows



Instalación UFW





Habilitamos con ufw enable, después revisamos con ufw y luego ejecutamos con iptables-L



Configuracion de políticas









```
┌──(root㉿kali)-[/home/kali]
└─# ufw allow ssh
Rule added
Rule added (v6)

┌──(root㉿kali)-[/home/kali]
└─#
```

```
┌──(root㉿kali)-[/home/kali]
└─# ufw allow http
Rule added
Rule added (v6)

┌──(root㉿kali)-[/home/kali]
└─# ufw allow https
Rule added
Rule added (v6)
```

```
┌──(root㉿kali)-[/home/kali]
└─# iptables -A INPUT -p tcp --dport 22 -j ACCEPT
```

```
┌──(root㉿kali)-[/home/kali]
└─# iptables -A INPUT -p tcp --dport 80 -j ACCEPT

┌──(root㉿kali)-[/home/kali]
└─# iptables -A INPUT -p tcp --dport 443 -j ACCEPT
```

Bloqueamos

```
┌──(root㉿kali)-[/home/kali]
└─# ufw deny from 192.168.1.101
Rule added
```

```
┌──(root㉿kali)-[/home/kali]
└─# ufw deny from any to any port 8080
Rule added
Rule added (v6)
```


┌──(root㉿kali)-[/home/kali]
└─# ufw status numbered
Status: active
To Action From
[1] 22/tcp ALLOW IN Anywhere
[2] 80/tcp ALLOW IN Anywhere
[3] 443 ALLOW IN Anywhere
[4] Anywhere ALLOW IN 192.168.1.100
[5] Anywhere DENY IN 192.168.1.101
[6] 8080 DENY IN Anywhere
[7] 22/tcp (v6) ALLOW IN Anywhere (v6)
[8] 80/tcp (v6) ALLOW IN Anywhere (v6)
[9] 443 (v6) ALLOW IN Anywhere (v6)
[10] 8080 (v6) DENY IN Anywhere (v6)