IOS Command Line Interface

```
Router con0 is now available



Press RETURN to get started.









User Access Verification

Username: console
Password:

Router>
Router>
Router>enable
Password:
Router#
Router#
Router#
```

Physical Config CLI Attributes

IOS Command Line Interface

```
Router(config-line)#password telnet
Router(config-line)#
Router(config-line)#login
Router(config-line)#
Router(config-line)#exit
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#exit









Router con0 is now available




Press RETURN to get started.
```

Router0

Physical Config CLI Attributes

IOS Command Line Interface

```
User Access Verification

Username: console
Password:

Router>
Router>
Router>
Router>
Router>enable sceret enable
               ^
% Invalid input detected at '^' marker.

Router>enable secret enable
               ^
% Invalid input detected at '^' marker.

Router>
Router>
Router>
Router>enable
Router#
Router#
Router#enable secrete enable
               ^
% Invalid input detected at '^' marker.

Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#
Router(config)#enable secret enable
Router(config)#
Router(config)#line vty 0 4
Router(config-line)#transport input telnet
Router(config-line)#password telnet
```

IOS Command Line Interface

```
Router>
Router>
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#
Router(config)#username console password console
Router(config)#
Router(config)#line console 0
Router(config-line)#login local
Router(config-line)#
Router(config-line)#exit
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#exit









Router con0 is now available
```

```
Router#
Router#show ip interface brief
Interface              IP-Address      OK? Method Status                Protocol
FastEthernet0/0        50.0.0.10       YES manual up                    up
FastEthernet0/1        unassigned      YES unset  administratively down down
Ethernet1/0            unassigned      YES unset  administratively down down
Ethernet1/1            unassigned      YES unset  administratively down down
Ethernet1/2            unassigned      YES unset  administratively down down
Ethernet1/3            unassigned      YES unset  administratively down down
Router#
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface fastethernet0/1
Router(config-if)#ip address 60.0.0.20 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

Router(config-if)#exit
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

% Incomplete command.
Router#show ip interface brief
Interface              IP-Address      OK? Method Status                Protocol
FastEthernet0/0        50.0.0.10       YES manual up                    up
FastEthernet0/1        60.0.0.20       YES manual up                    up
Ethernet1/0            unassigned      YES unset  administratively down down
Ethernet1/1            unassigned      YES unset  administratively down down
```

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>
Router>
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#
Router(config)#interface fastethernet0/
                                      ^
% Invalid input detected at '^' marker.

Router(config)#interface fastethernet0/0
Router(config-if)#ip address 50.0.0.10 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip interface brief
Interface              IP-Address      OK? Method Status                Protocol
FastEthernet0/0        50.0.0.10       YES manual up                    down
FastEthernet0/1        unassigned      YES unset  administratively down down
Ethernet1/0            unassigned      YES unset  administratively down down
Ethernet1/1            unassigned      YES unset  administratively down down
Ethernet1/2            unassigned      YES unset  administratively down down
Ethernet1/3            unassigned      YES unset  administratively down down
Router#
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
```

Ctrl+F6 to exit CLI focus

Copy Paste