

Terminal

X

```
Router>
Router>
Router>
Router>
Router>
Router>
Router>enable
Router#
Router#
Router#
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
Router(config)#
Router(config)#
Router(config)#
Router(config)#interface fastEtherne 0/0
                                     ^
% Invalid input detected at '^' marker.

Router(config)#interface fastethernet0/0
Router(config-if)#ip address 50.0.0.10
% Incomplete command.
Router(config-if)#ip address 50.0.0.10 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#
Router(config)#
Router(config)#
Router(config)#
Router(config)#exit
```

Terminal



```
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#
Router#
Router#
Router#show ip interface brief
Interface                IP-Address      OK? Method Status          Protocol
FastEthernet0/0          50.0.0.10       YES manual up              down
FastEthernet0/1          unassigned      YES unset  administratively down down
Router#
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router#
Router#
Router#
Router#show ip interface brief
Interface                IP-Address      OK? Method Status          Protocol
FastEthernet0/0          50.0.0.10       YES manual up              up
FastEthernet0/1          unassigned      YES unset  administratively down down
Router#

Router con0 is now available
```

```
Router>
Router>
Router>
Router>enable
Router#
Router#
Router#
Router#confiure terminal
      ^
% Invalid input detected at '^' marker.

Router#
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#interface fastethernet0/1
      ^
% Invalid input detected at '^' marker.

Router#interface fastethernet0/1
      ^
% Invalid input detected at '^' marker.

Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface fastethernet0/1
Router(config-if)#ip address 50.0.0.20 255.0.0.0
% 50.0.0.0 overlaps with FastEthernet0/0
Router(config-if)#ip address 60.0.0.10 255.0.0.0
Router(config-if)#no shutdown
```

```
Router(config-if)#ip address 50.0.0.20 255.0.0.0
% 50.0.0.0 overlaps with FastEthernet0/0
Router(config-if)#ip address 60.0.0.10 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

Router(config-if)#
Router(config-if)#
Router(config-if)#show ip interface brief
      ^
% Invalid input detected at '^' marker.

Router(config-if)#exit
Router(config)#
Router(config)#
Router(config)#
Router(config)#
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#
Router#
Router#show ip interface brief
Interface          IP-Address      OK? Method Status      Protocol
FastEthernet0/0    50.0.0.10      YES manual  up          up
FastEthernet0/1    60.0.0.10      YES manual  up          down
Router#
```