

-More--

```
Archivo Máquina Ver Entrada Dispositivos Ayuda
#include <linux/kernel.h>
#include <linux/module.h>
#include <linux/hash.h>
#include <linux/gcd.h>
#include <asm/param.h>
#include <linux/jiffies.h>
int simple_init(void){
   printk(KERN_INFO "Loading Kernel Module\n");
   printk(KERN_INFO "%lu\n", GOLDEN_RATIO_PRIME);
   printk(KERN_INFO "Hz; %d\nJiffies: %lu\n", HZ, jiffies);
   printk(KERN_EMERG "Emmmmergency");
   return 0;
void simple_exit(void){
   printk(KERN_INFO "Removing Kernel Module\n");
   printk(KERN_INFO "%lu\n", gcd(3300,24));
   printk(KERN_INFO "%lu\n", jiffies);
module_init(simple_init);
module exit(simple exit);
MODULE_LICENSE("GPL");
MODULE_DESCRIPTION("Simple Module");
MODULE_AUTHOR("SGG");
osc@ubuntu:~$
```

```
Archivo Máquina Ver Entrada Dispositivos Ayuda
#include <linux/kernel.h>
#include <linux/module.h>
#include <linux/hash.h>
#include <linux/gcd.h>
#include <asm/param.h>
#include <linux/jiffies.h>
int simple_init(void){
   printk(KERN_INFO "Loading Kernel Module\n");
   printk(KERN_INFO "%lu\n", GOLDEN_RATIO_PRIME);
   printk(KERN_INFO "Hz; %d\nJiffies: %lu\n", HZ, jiffies);
   printk(KERN_EMERG "Emmmmergency");
   return 0;
void simple_exit(void){
   printk(KERN_INFO "Removing Kernel Module\n");
   printk(KERN_INFO "%lu\n", gcd(3300,24));
   printk(KERN_INFO "%lu\n", jiffies);
module_init(simple_init);
module exit(simple exit);
MODULE_LICENSE("GPL");
MODULE_DESCRIPTION("Simple Module");
MODULE_AUTHOR("SGG");
osc@ubuntu:~$
```





	Entrada Dispos	vos A	yuda
Module	Size	Used	ьу
simple	16384	0	
ppdev	20480	0	
intel_powerclamp	16384	0	
vboxvideo	53248	1	
ttm	98304		xvideo
drm_kms_helper	155648		xvideo
snd_intel8x0	40960	0	1-4-10-0
snd_ac97_codec	131072		_intel8x0
input_leds	16384	0	
serio_raw	16384	0	
joydev 07 bu-	20480	0 4 1	071
ac97_bus	16384		_ac97_codec
drm	364544		,drm_kms_helper,uboxuideo
snd_pcm	106496	z sna 0	_ac97_codec,snd_intel8x0
8250_f intek	16384 32768	0	
parport_pc			au namont na
parport	49152 32768		ev,parport_pc
snd_timer	16384	1 snd	
fb_sys_fops snd	81920		_kms_helper
	16384		_ac97_codec,snd_intel8x0,snd_timer,snd_pcm _kms_helper,vboxvideo
syscopyarea soundcore	16384	z arm 1 snd	
sysfillrect	16384		_kms_helper,vboxvideo
sysinnect sysimgblt	16384		_kms_helper,vboxvideo _kms_helper,vboxvideo
vboxguest	286720		_xwideo
i2c_piix4	24576	0 0	XVIUED
mac_hid	16384	ŏ	
ib_iser	49152	ŏ	
rdma_cm	49152	1 ib_	iser
iw_cm	45056	1 rdm	
ib_cm	45056	1 rdm	_
ib_sa	36864		a_cm,ib_cm
ib_mad	49152		cm,ib_sa
ib_core	106496		a_cm,ib_cm,ib_sa,iw_cm,ib_mad,ib_iser
ib_addr	16384		a_cm,ib_core
More			

```
osc@ubuntu:~$ sudo rmmod simple
osc@ubuntu:~$ dmesg | tail -11
    6.8085811 IPv6: ADDRCONF(NETDEV CHANGE): enp0s3: link becomes ready
    6.8937901 cgroup: new mount options do not match the existing superblock, will be ignored
    9.3320101 floppy0: no floppy controllers found
   35.5464801 simple: module verification failed: signature and/or required key missing - tainting
kerne l
   35.5470101 Loading Kernel Module
   35.5470111 11400862456688148481
   35.5470121 Hz: 250
               Jiffies: 4294901137
  286.2394901 Removing Kernel Module
  286.2394921 12
  286.2394921 4294963810
osc@ubuntu:~$ lsmod | head -n 4
Module
                        Size Used by
                       20480
ppdev
intel_powerclamp
                       16384 0
vboxvideo
                       53248 1
osc@ubuntu:~$
```