
description: Welcome to the Midnight-Market Knowledge Base!

Overview

Our Knowledge Base is designed to provide you with all the support and information you need for Midnight-Market products and services.

Here, you'll find in-depth guides, troubleshooting advice, and expert tips to help you get the most out of our digital solutions.

Whether you're looking for user manuals, answers to frequently asked questions, or professional guidance, our Knowledge Base is your go-to destination.

Disabling Windows Defender, Secure Boot And UAC

Disabling Antivirus Software

To ensure a smooth installation and operation of the software, it is important to temporarily disable any active antivirus programs. This prevents potential conflicts that may interfere with the installation process or the software's performance.

◆ Preliminary Step: Remove Conflicting Anti-Cheat Programs

If you have the following anti-cheat programs installed, it is recommended to **uninstall** them, as they are known to cause compatibility issues with many game modifications:

- **Faceit AC** (CS:GO)
- **Vanguard AC** (Valorant)

Removing these programs will help avoid potential disruptions and ensure optimal functionality.



How to Turn Off Antivirus

{% embed url="https://www.youtube.com/embed/IYKJZm_ixIQ" %}

Disabling Secure Boot



How to Disable Secure Boot on Most Motherboards

Secure Boot is a security feature designed to prevent unauthorized software from loading during startup. However, in some cases, you may need to disable it for software modifications or hardware compatibility reasons. The exact steps can vary depending on your motherboard manufacturer, but the general process remains similar across most systems.

Steps to Disable Secure Boot:

1 Enter the BIOS/UEFI Setup

- Restart your computer.
- During boot, press the designated key to enter the BIOS/UEFI (**Del**, **F2**, **F10**, or **Esc**). The key may be displayed on the boot screen or found in your motherboard manual.

2 Locate the Secure Boot Option

- Navigate to the **Boot**, **Security**, or **Authentication** tab using the arrow keys.
- Look for an option labeled **Secure Boot**.

3 Disable Secure Boot

- Select **Secure Boot** and change the setting to **Disabled**.
- Some motherboards require switching **OS Type** to **Other OS** or **Legacy Mode** to unlock this option.

4 Save Changes and Exit

- Press the appropriate key (usually **F10**) to save the changes.
- Confirm the changes and allow your system to restart.

Additional Notes:

- On some systems, you may need to **clear Secure Boot keys** before disabling it. This option is often found in the same menu.
- If you have trouble locating the Secure Boot setting, refer to your **motherboard manual** or the manufacturer's website for detailed instructions.

Disabling UAC

How to Disable User Account Control (UAC)

User Account Control (UAC) is a security feature in Windows that helps prevent unauthorized changes to the system. However, in some cases, you may need to disable it temporarily. Below are the steps to turn off UAC.

Steps to Disable UAC:

1 Open User Account Control Settings

- Press the **Windows key** and search for **Change User Account Control Settings**.
- Click on the matching result (as shown in the image below).



2 Adjust the UAC Slider

- Once inside the **User Account Control Settings**, locate the **slider** that moves up and down.
- Move the slider **all the way down** to the lowest setting.
- Click **OK** to apply the changes (as shown in the image below).



Additional Notes:

- By following these steps, you can successfully disable UAC when necessary.
- If you encounter issues, ensure you have **administrative privileges**.

Installing VC Runtimes

Essential Dependencies for Running Cheats

To ensure that your cheats run smoothly and without errors, it is **absolutely necessary** to have **VC Runtimes** and **DirectX** installed. These are essential system components that many cheats rely on. Without them, you may encounter issues such as crashes, missing DLL errors, or failed executions.

Install All Required Runtimes

To simplify the process, we've Given you a website to all the necessary dependencies in one easy-to-install package. Just follow these steps:

1. **Download the file** from the link below.
2. **Extract the contents** if required.
3. **Run the .bat file** and choose the option to install all runtimes. The same is done for DirectX

 [**Download All Runtimes**](#)

 [**Download DirectX**](#)

In Rare cases you'll need .Net Frameworks as well you might as well install it now

 [Download .Net Frameworks](#)

Installing these essential components will help eliminate compatibility issues and ensure everything runs smoothly. 

How to Disable Virtualization (VT-x / AMD-V)

Steps for Most Systems

1. **Restart your PC.**
2. **Enter BIOS/UEFI Setup:**
 - Press one of these keys repeatedly during startup:
 - **DEL / F2 / ESC / F10** (depends on manufacturer)
3. **Navigate to the CPU/Advanced/Processor tab.**
4. **Look for virtualization settings:**
 - Intel: **Intel VT-x, Intel Virtualization Technology**
 - AMD: **SVM Mode, AMD-V**

5. **Set it to Disabled.**
6. **Save & Exit:**
 - Press **F10** or navigate to **Save & Exit**, then confirm.

Uninstalling ACE, VGK & FaceIT

How to Uninstall ACE Anti-Cheat VGK, Anti-Cheat & FACEIT Anti-Cheat

Uninstall Anti-Cheats

- **Close All ACE, FACEIT & VGK Processes**
- Press **Win + R**, type **appwiz.cpl**, and press Enter
- Find ACE, VGK & **FACEIT Anti-Cheat**, right-click it, and select **Uninstall**
- Restart your PC

Apex Glow

Please follow the [PC setup Guide](#)

Download [Loader Here](#). Password is "apex"

1. Launch the Loader.
2. Insert your license key.
3. Follow the guide in the CMD panel that pops up.
4. Enjoy!

Apex Lite

Please follow the [PC setup Guide](#)

[Download Loader](#) Password is "apex"

- Launch the Loader.
- Insert your license key.
- Follow the guide in CMD panel that pops up.
- Enjoy!

Apex Full

Please follow the [PC setup Guide](#)

[Download Loader](#) Password is "apex"

- Launch the Loader.
- Insert your license key.
- Follow the guide in CMD panel that pops up.
- Enjoy

Aimbot not working? try this!

use it on real players not bots!

Crusader R6

Please refer to the [**PC Setup Guide**](#)

1. **Download the loader using this link. The password for the archive is 123.**
([**https://uniqueloader.com/r6s/**](https://uniqueloader.com/r6s/))
2. **Extract the files from the archive and place them in a separate folder. The folder name should be written in English letters, it is recommended to place this folder in the root of the C drive.**
3. **Run the cheat loader as administrator.**

4. Insert your key into the "Serial Key" field and click "Sign In".
5. After a short loading, you will see the R6S icon.
6. Click the "Start Injection Process" button.
7. The message "Please Open Rainbow Six Siege" will appear, it's time to launch the game. Be sure to run the DirectX 12 version of the game!
8. When the game starts, press the "Insert" key while in the main menu.
9. The cheat menu will appear in front of you. The key to close/open the menu is Insert.

****IMPORTANT!****

- If you plan to use Crusader with a spoofer, always run the cheat loader first, and then the spoofer.

Common Issues

Here we have collected popular problems and ways to fix them:

1. Uninstall Faceit anti-cheat and Riot Vanguard using "Add or Remove Programs". Anti-cheats prevent cheats from working;
2. Disable all antiviruses on your computer, and also completely disable Windows Defender (Real-time Protection).
3. Disable Windows Defender
4. If you have problems with launching/injection, then you need to download [**this file****](#). ** Run the file and restart your PC, then try to run the cheat again. You should also disable kernel isolation and vulnerable driver blocking in Windows Defender.
5. To run the cheat, you must also disable Reputation-based Protection.
6. Open the start(windows) menu and search for "Reputation-Based Protection." Open this window, In the window that opens, disable all options.
7. Also, if you have problems with cheat injection or other problems during the game (ESP lags, etc.), then try switching the screen mode to "Borderless / Windowed" in the game settings.

Counter Strike 2 BS

Please refer to the [**PC Setup Guide**](#)

Download the [**Loader**](#)

1. Close Steam and any remote desktop apps. (Anydesk/Teamviewer)
2. Paste the key you were provided and press the "Inject" button.
3. After the client is closed, you can start Steam and the game.

Press the INSERT button to open the cheat menu.

Predator CS2

1. Creating an Account

1. Visit the [Predator Systems](#).
2. Click on Register in the top-right corner.
3. Fill out your Username, Email, and Password.
4. Confirm your email via the verification link sent to your inbox.
5. Once verified, your registration will be complete.

2. Activating Your Subscription

1. Log into your Predator Systems account.
2. Navigate to the Products tab.
3. Copy your License Key from the email you received after purchase.
4. Paste the key into the designated box on the website.
5. Click the Check Mark icon to activate your subscription.

3. Downloading the Loader

1. Go to the Panel section on the website.
2. Before downloading, disable your antivirus or Windows Security to prevent flagging.
 - Go to Windows Security.
 - Navigate to Virus & Threat Protection.

- Click Manage Settings and turn off Real-time Protection.
 - Optionally, add the downloaded file to Exclusions.
3. Click the Download button.
 4. If your browser flags the file, click Show More and select Keep Anyway.

4. Installing the Loader

1. Open the downloaded file.
2. Click Yes on any popup prompts.
3. The Predator Systems Loader will open.
4. Log in with your username and password.
5. Click Load to begin the injection process.

5. Launching CS2 with Predator Systems

1. The loader will automatically open Steam.
2. Select your Steam account and launch CS2.
3. The loader will inject the software while waiting for the game to launch.
4. Use the default Insert key to open the Predator Systems menu in-game.

6. Configuring Predator Systems

- Navigate to the Aimbot tab.
- Enable the Master Switch.
- Customize Per Weapon Settings or Global Settings.
- Adjust Dynamic FOV, Recoil Control System (RCS), and Trigger Bot Delay.
- Enable Smoke Check and Flash Check for more accurate aiming.
- Customize Hit Groups and Aim Preference.

7. Troubleshooting

- Ensure your antivirus is turned off or the file is added to exclusions.
- Restart both the loader and the game if issues persist.
- Contact Predator Systems Support through their website for additional help

NC EFT PRO / LITE / NC DayZ Pro

Please refer to the [**PC Setup Guide**](#)

[DOWNLOAD LOADER](#)

 Step 1: Turn Off & Uninstall Antivirus/Anti-Cheat Programs

Before proceeding, **disable or uninstall** any of the following:

- Avast
 - AVG
 - Malwarebytes
 - **Nord VPN** (built-in antivirus)
 - **Vanguard** (Valorant Anti-Cheat)
 - **ACE** (Arena Breakout Anti-Cheat)
 - **ESEA Client / FaceIT** (CS2 Competitive Anti-Cheat)
 - McAfee
-

Step 2: Retrieve Your Product Key

After purchase, you should have received a product key.

Copy or keep this key handy—you'll need it for registration.

Step 3: Download the Loader

1. Go to: <https://loadergen.com/download>
 2. Click **"Download"**
 3. Once downloaded:
 - Right-click the file → **"Show in Folder"**
 - Right-click the loader → **"Run as Administrator"**
-

Step 4: Register an Account

1. Open the loader
 2. Go to the **"Sign Up"** tab
 3. Fill in your:
 - Username
 - Email
 - Password
 - **Product Key**
 4. Click **"Register"**
 5. You'll get a confirmation message once registered successfully
-

Step 5: Using the Loader


- **Products Tab:** View the cheat you purchased

- **Redeem License Key:** Add new keys here after your subscription expires
- **Risk Status:** Check if the game is safe to inject cheats
- **Change Log:** See updates or changes from the dev team
- **Injection Tab:**
 - Click "**Load**" to inject the cheat
 - **Inject before launching the game**
- **Settings Tab:**
 - Install the **Game Spoofer**
 - Access other configuration options
 - **Make sure the game launcher is offline before spoofing**

Troubleshooting

If for any reason the game crashes/fails to inject or even BSOD. you can fix 99% of problems by increasing the injection delay on the Loader. as shown in the picture below. once the loader closes open the game from steam immediately, dont waste any time and launch the game \

The key to open and close the menu is INSERT. Regarding Spoofer, it's on by default. You can turn it off IF YOU WANT TO by mirroring the settings below. Using the built-in spoofer is highly recommended.



Maze Products

[SWBF2 Loader](#)

[BattleField 4 Loader](#)

[Deadlock Loader](#)

1. Download the loader
2. Open your game.
3. Open the loader.
4. Insert the key/serial you got from your order in the loader.
5. Software should be successfully injected & a menu should appear in the middle of your screen
6. Insert to open and close menu.\

Arma 3 1PC / ARK / Sugar Elite / LITE / Chams++ / Hunt Showdown 1PC

Please refer to the [PC Setup Guide**](#)**

[Download Loader Here](#)

1. Run the loader as administrator.
2. Copy the license key received from the seller and paste it into the 'license key' field.
3. Click the 'activate' button and wait for a notification of successful activation.
4. After successful activation, you will be redirected to the cheat launch page, where you need to click the 'inject' button.
5. After clicking the 'inject' button, wait for the cheat initialization to complete successfully.
6. After the cheat loads, a window with the message 'preparing mapper...' will appear.
7. Start the game after the message 'awaiting game window'.
8. After you have loaded into the game's main menu, wait 15 seconds and press the key indicated in the console.

Windows 11 Additional steps.

1. Download this [file](#)
2. Run win11_driver_OFF.reg
3. Disable Core Isolation in Windows settings.
Settings -> Privacy & security -> Windows Security -> Device security -> Core Isolation
4. Restart the PC, then inject again.

Troubleshooting Steps

1. Issue: The loader crashes on startup.
Solution: Restart the loader, reinstall the loader, reboot Windows.
2. Issue: The loader won't start or always gives an 'unexpected error' message on startup.
Solution: Check your internet connection/use a VPN within your region for the key (CIS - Kazakhstan, Belarus, Russia).
If you are from Ukraine, you must use a VPN to one of the countries listed above because our servers are blocked in your country due to the current global situation.
3. Issue: The loader closes after the cheat is initialized.
Solution: Disable all antivirus programs, Windows Defender, and any other protection that interacts with the system for its security.

4. Problem: The cheat menu does not appear after the message that the cheat has been successfully launched.\

Solution: Try running the game launcher as an administrator.

Find the game launcher file (Steam/BSG launcher, etc.), right-click on it and select 'Properties'.

Go to the 'Compatibility' tab.

Check the box for 'Run this program as an administrator' and click 'Apply'.

Try launching the cheat again.

If this doesn't help, try doing the same with the game's executable files.

5. The computer restarts when launching the cheat.

Solution: SYNC the time on your computer TWICE (THIS IS IMPORTANT!).

EFT KD Dropper

Please refer to the [PC Setup Guide**](#)**

Loader [DOWNLOAD](#) You must set the resolution to 1920X1080p on both Escape From Tarkov (EFT) and the Windows desktop.

Post FX needs to be toggled off and color on Windows/Nvidia/AMD drivers needs to be set to stock.

Must set the main menu background to WOODS (NOT LABS, NOT FACTORY) WOODS is the only one that works.

While using KD DROPPER Please do not have any DMA or Single PC Cheat active.

Turn on Auto Ram Cleaner in EFT's Game settings tab while using to help prevent crashes from extended use.

Step 1: Get a bleed while at full HP by killing yourself with a grenade. Then don't heal after the raid. NOTE: Having a friend stab you with a cultist knife to get toxin also works and will allow you to KD Drop at the same speed for longer periods. As bleeds will eventually heal. Toxin does not.

Step 2: Go to the main menu and start the bot after setting how many raids you want it to run for max is 250.

Step 3: A lower KD.

COD Rage chair

Please refer to the [PC Setup Guide](#)

Download the [Loader Here](#)

1. **Launch the Loader as admin**
2. **Insert your License key**
3. **Wait until it tells you the driver has loaded and to start the game**
4. **Start the game and enjoy!**

My Game Keeps Crashing

Enable GPU scheduling.,

Search on windows graphics settings and then turn on GPU scheduling, hardware accelerated graphics.,

turn off frame generation go to call of duty settings and find it in settings,

Disable dlss,

Disable image scaling,

All located in graphics settings in cod,

reinstall vc redist and dxwaresetup,

Run [ALLFIX.BAT](#)

if any other issues delete loader, re-download and place on desktop

Klar Products

Follow the [PC PREP guide](#)

☐ [Click here to download.](#)

Launch the Loader:

- Right-click on the loader and select **Run as Administrator**.

Register an Account:

- When prompted, enter the **username** and **password** you want to use. (Note: Spaces are **not** allowed in the username or password).
- Press-Register.

How to Inject:

- Open Loader as Admin
- Login
- Choose Product
- Press Load (***Wait until you receive MessageBox saying "Open game"***)
- Open the game.
- Press **INSERT** to open/close the Menu

FAQ and Error Codes:

- See the common issues and troubleshooting [guide here](#).

Immunity Pubg

Please refer to the [**PC Setup Guide**](#)

[**Download Loader**](#) Password is "pubg"

Instructions:

1. **Disable all antivirus programs** *before downloading the loader*.
2. **Turn off Secure Boot** in your BIOS settings.
3. **Download the loader above**.
4. **Turn off flow control** in your system settings.
5. Make sure game is in borderless and insert is the menu

Common Issues & Fixes:

1. **ESP Extending to Second Monitor:** Unplug the second monitor.
2. **Menu Acting Erratically:** Unplug the second monitor and reinject.

Rust Cyber

Download [Loader Here](#)



Please Read Carefully Before First Launch!



To ensure proper setup and avoid issues, follow these steps **before running the software**:



Pre-Launch Checklist

1. Disable Windows Defender

We recommend using [DControl](#) for an easy and effective disable.

2. Turn Off All Third-Party Antivirus Software

Any active antivirus may interfere with the software or cause false detections.

3. Disable or Uninstall Third-Party Anti-Cheats (e.g., FACEIT / Vanguard)

If FACEIT is installed, open Command Prompt as Administrator and run:

```
sc stop faceit
```

4. Set “Small Dump” in System Settings

- Navigate to: [Control Panel](#) > [System](#) > [Advanced System Settings](#) > [Startup and Recovery](#)

- Under “Write debugging information,” select:

Small memory dump (256 KB)

1. Edit Registry: Disable Vulnerable Driver Blocklist

- Open the Registry Editor and go to:

```
HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\CI\Config
```


- Locate the key: [VulnerableDriverBlocklistEnable](#)

- **Set its value to 0** by double-clicking the entry and changing the value data.

If you can't find the vulnerable driver block list, download this file and confirm it is on 0

Visual Reference


Use the image below to verify the correct location and value:



Set "Small Dump" in System Settings


Follow these steps to configure your system for a small memory dump:

1. Press **Win + R** on your keyboard
2. Type **SystemPropertiesAdvanced** and press **Enter**
3. In the window that appears, under **Startup and Recovery**, click **Settings**
4. Under **"Write debugging information"**, select:
 - **Small memory dump (256 KB)** from the dropdown menu
5. Click **OK** to save and close




First Launch Instructions

1. **Open the archive** you received after purchasing your key
 **Archive password:** 123
2. **Run the loader**
 - Open the file inside the archive: `svchost.exe`
 -  Do **not** extract it — just open it directly from the archive
 - A console window will appear with the label:



3. **Wait for the key input window to appear**

- A window will pop up with a field to enter your product key
- It may look like this:




Restart your PC if prompted

4. **Restart your PC if prompted**
- If a restart request appears, restart and repeat steps 2–3

5. **Enter your product key**

- Paste the key you received after purchase
- Click **Start**

6. **Watch for driver status confirmation**



Launch the game

7. **Launch the game**
- Once you click **Start the game**, the label will change to **Initialization**
 - Wait for the cheat to initialize — the cheat menu will appear when ready

8. **Log into a server and play**

 Important Tips:

- Excessive reports from other players may also trigger a ban

Troubleshooting: If "Start the game" Doesn't Appear

If the message "**Driver is not started**" stays on screen and nothing happens, something is blocking the software on your PC. Common causes include:

1. Windows Defender is still enabled
2. Third-party antivirus software is running
3. Third-party anti-cheats like **FACEIT** or **Vanguard** are installed or active
4. "Small Dump" was not set correctly in system settings

Make sure all of the above are properly disabled or configured as outlined in the setup guide.

If the "Initialization Failed" Label Appears

If the cheat shows the message "Initialization failed", it could be due to the following:

1. **Exploit Protection in Windows Defender is Enabled**
 - Make sure all exploit protection features in **Windows Defender > App & Browser Control > Exploit Protection** are turned off
 2. **Random Initialization Failure**
 - Occasionally, the initialization may fail by chance
 - Try restarting both the **cheat** and the **game**
 3. **Cheat Is Not Yet Updated for the Game Version**
 - If you see "Initialization failed" after **2–3 tries (if it still fails after that just keep going) or in rare cases** the game may have received an update
 - Wait for a cheat update to be released
-

Recommendations for Use

1. **Limit your in-game FPS to match your monitor's refresh rate**
&#xNAN;(This is not the same as enabling vertical sync)
 - For a **60 Hz** monitor → set FPS to **60**
 - For a **144 Hz** monitor → set FPS to **144**

This prevents rendering extra frames, which improves cheat performance and stability.

2. **Play as legit as possible**
 - Even if undetected, **mass reports** from other players will often lead to account bans
 - Avoid obvious or blatant cheating behavior

NFA Rust accounts

- Locate the code sent to your email and on the website.

- take the code and paste it into the loader linked below.

Download [Loader Here](#)

****NOTICE****: When you make a purchase, you'll receive a key that isn't initially linked to any account. Once you enter the key into the loader, it will be bound to an account and a one-hour warranty will begin. This warranty only covers account invalidity and game bans that are present within the first 5 minutes of activating the warranty. If a game ban occurs after that initial 5-minute window or at any point after the time of purchase, we will not provide compensation. To claim warranty on an account, you must submit proof of the issue by opening a support ticket

Temp Spoofer

Please follow the PC Prep guide [found HERE](#)

Download [Loader HERE](#)

Revo DMA 2 PC

:rotating_light:Loader [Download](#) :rotating_light:

1. Prepare Your DMA System

- **Disable Virtualization Features** (if not needed):
 - For AMD CPUs: Disable SVM (Secure Virtual Machine) and IOMMU in the BIOS.
 - For Intel CPUs: Disable VT-d and Intel Volume Manager in the BIOS.
- **Disable Quick Start & Safe Start** in BIOS.

- **Disable NX-Bit / XD-bit** (if available) in CPU settings.
- **Enable CSM** (Compatibility Support Module) in BIOS if needed.
- **Set PCI Slot to Gen1** (Advanced > PCI Settings) for better compatibility.

2. Install Required Software

- **Visual C++ Redistributable Runtimes:**
 - Download and install the all-in-one package from [here](#).
 - This ensures all necessary runtime libraries are installed.
- **Windows Defender Control:**
 - Download DControl from [here](#).
 - Run the tool to disable Windows Defender.

3. Adjust Graphics Settings for *Escape from Tarkov*

- **Locate the Graphics.ini File:**
 - Navigate to `C:\Users\UserName\AppData\Roaming\Battlestate Games\Escape from Tarkov\Settings\Graphics.ini`.
 - Adjust the resolution settings to match your monitor's native resolution to avoid issues with ESP or other visual elements.
 - Save the file after making changes.

4. Windows Settings

- **Disable Core Isolation:**
 - Go to **Windows Security > Device Security > Core Isolation**.
 - Turn off **Memory Integrity**.
- **Power Settings:**
 - Set your power plan to **High Performance** in **Control Panel > Power Options**.

5. DMA Memory Mapper (MMAP)

- **Download REVO DMA Memory Mapper:**
 - Download the tool from [here](#).
 - Run the REVO MMap Tool on main PC to generate mmap file.
 - Then move mmap file to where REVO is running from on 2nd PC.
 - You can delete the REVO MMap Tool afterwards.

6. Test DMA Card Speed

- **Download REVO DMA Test Tool:**
 - Download REVO Tools and run REVO DMA Test Tool. Get from [here](#).
 - Run the tool with Option 3 to test the speed of your DMA card.
 - Ensure that the throughput and read/write speeds are optimal. **5K+ RPS = Good.**

- If speeds are lower than expected, check your hardware connections and BIOS settings.
- Confirm you are using a quality high speed cable.

DIRECT DMA 2 PC

Instructions for launching

1. Download the loader and move it to a location convenient for you on the second computer.

Ensure your browser's antivirus or Windows antivirus has not blocked the file. [Download link](#)

1. If you have any problems with the size of the window that opened on the second computer, try setting the exact screen resolution on both computers.

Scaling in Windows must be set to 100% on both PCs!

1. Download and install DirectX SDK + Visual C++ on the second PC

[Download DirectX SDK](#) [Download Visual C++](#). If you have a problem with DirectX SDK install, please read [this guide](#)

1. Download our support guide and make benchmarks of your devices

[Download DirectSupport](#)

1. Procedure:
 - Start the game
 - Launch the loader

If you have any other questions, please open a ticket in our Discord. We'll be happy to answer them.

Arma 3 & Reforger DMA 2 PC

1. Head on over to the PrometDMA Discord: <https://discord.prometcheats.cc>

2. Verify yourself by pressing the green "Verify" button and add "Midnight" followed by your key into the box
3. After waiting a couple of seconds, a few channels should pop up. Download the launcher in the channel #customer-area

{% embed url="https://www.youtube.com/watch?v=HIWT_nkOTyk" %}

DayZ & Hunt+

create an account on [https://gaslight.pro/**](https://gaslight.pro/) -> redeem the key
-> download loader -> launch your game on first pc then
when you're in the menu / ingame select the cheat and load**

NEW NF GUIDE

Nightfall Fuser Setup Guide (Second PC)

1. Download Required Files

Download the Nightfall DMA loader.
Extract it to a clean folder on your second PC.

2. Launch the [**DMA Loader**](#)

Run the loader as administrator.
It will automatically check for your DMA card.

If everything is working, you'll see confirmation that the card is detected.




If there's an error:

- Make sure the card is connected properly
- Install USB drivers for your card
- Try different USB ports or cables if needed

3. Follow the Fuser Images

Refer to the screenshots below to finish setup using the fuser.

Make sure you're using the correct resolution and overlay settings based on your setup.



Nightfall No-Fuser


Setup Guide (NVIDIA Guide Only)

***Note:** This guide is for NVIDIA GPU users using GeForce Experience. If you're using AMD or Intel, you'll need to use [Sunshine](#) instead. Nightfall does not provide a tutorial for Sunshine, but you can find many on YouTube or Google.*


1. Enable Game Streaming on the Game PC

Open GeForce Experience on your game PC.

Enable **GameStream** in the settings.\



Afterwards, go ahead and click the Add button in the same location to add the following "game" to GeForce Experience:



Click **Add** and select your desktop or any app so that your full desktop can be streamed, not just a game window.

2. Install Moonlight on the Second PC

Download and install **Moonlight** from <https://moonlight-stream.org/>

This will let you stream the full desktop of your game PC to the second PC.

3. Download Required Files on the Second PC


Download the **Nightfall DMA loader** and extract it to a clean folder.

4. Start the [**DMA Loader**](#)

Run the loader as administrator.

Log in with your key.

If your DMA card is connected correctly, you'll see a confirmation screen.



If there's an error:

- Double-check the physical connection
- Install the required USB drivers
- Try switching ports or cables if needed


5. Open Moonlight and Configure It

Open Moonlight on the second PC.

Go to settings and set the **resolution** and **FPS** to match your main gaming monitor's native resolution and refresh rate.

All displays — the Game PC monitor, the game settings, and the second PC monitor — must use the **same resolution and refresh rate**.

If they don't match, the radar visuals will not align properly.



6. Connect to the Game PC and Start the Game

In Moonlight, your game PC will appear as a streamable device.

Connect using the **Desktop** option that was added earlier.

Once connected, launch the game on your game PC normally.

Troubleshooting and quality of life improvements

Common issues along with their solutions are listed here. Make sure to work your way through them before asking questions in case of errors or anything not functioning!

- Visuals do not align or are drawn in the wrong locations: Make sure both PC's have the same resolution set, the game is running in fullscreen/borderless windowed AND the right resolution is set in Moonlight.
- Visuals are drawn on the monitor of the second PC, but I want to use my primary monitor to game: An option is to connect both the game PC and the second PC to the same monitor that you want to use for gaming. Workflow would go a little something like this: Start game PC, log in, start second PC, switch monitor input to second PC, log in, start DMA loader, start Moonlight and connect Moonlight to your game PC. This way, it's like using the main PC as normal, but with visuals.
- Moonlight is lagging: Both PC's should ideally be connected to the internet (and your home network) via ethernet. WLAN is not ideal for game streaming in the slightest, so that is probably the cause. Other than that, disable VSYNC ingame, set the game to fullscreen and make sure the GPU is running below 80% usage. Turn down graphics settings if it's running at 80% or higher
- Moonlight won't let me tab out: Since Moonlight version 4, tabbing out is broken. They have a workaround for it: Press CTRL+SHIFT+ALT+D while tabbed in
- Moonlight freezing: Personal experience is that it's caused by using borderless fullscreen on Moonlight. Fullscreen fixes the issue
- Moonlight enables mouse acceleration on game PC: There are workarounds for this on the Moonlight discord. If you can't figure it out, leave the owner a message on Discord

- Visuals are not drawn at all (including FPS / frametime on the top left corner): Make sure to log into the loader first before starting Moonlight. Then, before connecting, make sure the Moonlight client status on the loader says "Loaded!".

Nitecore Rust DMA 2PC

Download [Loader](#)

Download the loader and run it

Bun R6 DMA 2PC

Install loader on second pc:

Run Loader:

Put in Provided PIN:

Wait for it to be green and successful

Read steps below after finished launch siege and then run bun.exe (with the logo)

IMPORTANT:

If you have a fuser please go to bun.ini (white file with cogwheel) scroll all the way down please locate Monitor_Num= and change it to 1

For QB issues make a ticket go to task manager, find the rainbowsix process, right click open file location send the rainbowsix.exe in ticket with PIN Proof of Purchase and username (all provided under your order.)

For AIM: Please locate the KMBOX section in bun.ini scroll down to kmbox and input the proper information. You will see kmbox-ver=1 or 2 or 0 1 means kmbox net 2 means bpro 0 means nothing, just insert your port for kmbox bpro or your IP/PORT for kmbox net.

MENU KEY: Delete Navigation/select: Arrow keys to move up and down within the menu right arrow key to select/toggle yes or no

Any further issues not explained in the guide please make a ticket in our discord:

Evo COD

Download [Loader here](#)

1. run the loader
2. Enjoy!

Setting up your DMA Card

- Disable Virtualization & SVM (**AMD**)
- Disable IOMMU (AMD CBS > NBIO Common Options > NB Configuration > IOMMU) (**AMD**)
- Disable Virtualization & VT-d (**INTEL**)
- Disable Intel Volume Manager. (**INTEL**)
- Disable Quick Start & Safe Start.
- Disable NX-Bit / XD-bit (if available, CPU Settings Secure Virtual Machine)
- Enable CSM* *(May help in some applications.)
- Set PCI Slot of Card to From Auto to Gen1 (Advanced > PCI Settings)

Recommend Windows Settings (Primary computer)

- Disable Windows Security: Core Isolation

Ensure all the steps above are done and you can proceed.

Platform Role	Desktop
Secure Boot State	Off
Firmware Configuration	Elevation Required to View
Windows Directory	C:\Windows
System Directory	C:\Windows\System32
Boot Device	C:\Users\Administrator\OneDrive
Locale	United States
Hardware Abstraction Layer	Version = 1.0.0.1001.0.8668
User Name	DESKTOP-SSP\NirajGupta
Time Zone	Eastern Standard Time
Installed Physical Memory (RAM)	4.0 GB
Total Physical Memory	4.0 GB
Available Physical Memory	2.4 GB
Total Virtual Memory	12.0 GB
Available Virtual Memory	10.0 GB
Page File Space	0 bytes
Kernel DMA Protection	Off
Virtualization-based security	Not enabled
Device Encryption Support	Elevation Required to View
Hyper-V - VM Monitor Mode Extensions	Yes
Hyper-V - Second Level Address Translation Extensions	Yes
Hyper-V - Virtualization Enabled in Firmware	No
Hyper-V - Data Execution Protection	Yes

Make sure these settings are turned off on the main PC as well.

Step-by-Step Instructions:

1. Power Off and Unplug the PC

- Shut down your computer completely.
- Unplug it from the power outlet.
- Disconnect all peripherals (monitor, keyboard, etc.).

2. Open the PC Case

- Use a screwdriver to remove the screws on the side panel (usually the left side).
- Slide the panel off to access the internal components.

3. Locate an Available Expansion Slot

- Look for an empty SLI or PCIe slot on the motherboard (based on your motherboard).
- Remove the metal slot cover on the back of the case for that slot.

4. Insert the DMA Card

- Align the card's connector with the slot.
- Firmly but gently push the card down into the slot until it's fully seated.
- Secure the card with a screw at the back bracket if necessary.

5. Close the Case

- Replace the side panel and screw it back in place.

6. Reconnect and Boot Up

- Plug in the power cable and peripherals.
- Turn on your PC.

If you're confused about any install steps refer to the video below.

{% file

src="https://3836189522-files.gitbook.io/~files/v0/b/gitbook-x-prod.appspot.com/o/spaces%2FekaliTvRrCmmHBxrjep9%2Fuploads%2FapybJSkApdFPFUQx4vfl%2FIMG_3272.mov?alt=media&token=5004522c-2504-41c3-a624-cafbe72b28d6" %}



THE IMAGE ABOVE IS MIRRORED MAKE YOU PLUG IT IN TO THE FARTHEST FROM THE MOTHERBOARD!!

Once the DMA card is installed

1. Plug one end of the provided USB-C cable into the DATA port on the DMA card.
2. Plug the other end into the second PC.

Final Step

Run the Speed Test

1. [Download](#) this driver onto your second PC
2. [**Download and open**](#) the provided Speed Test program on the second PC.
3. Once it's open, **press 1 on your keyboard**.
4. This will **start the speed test** and begin communicating with the DMA card, as shown in the image below.

```
[SYMBOL] Initialized symbol subsystem (Microsoft).
Initialized 64-bit Windows 10.0.19041
[OK] DMA Initialization
[i] Attempting to locate process smss.exe...
[i] Process smss.exe running @ PID 568
[i] Attempting to enumerate process modules...
[i] smss.exe @ 0x7ff6a3c70000
[i] ntdll.dll @ 0x7ff693a30000
[OK] Process Lookup
[i] Retrieving Physical Memory Map...
00000000 - 0fffff
00000000 - 0fffff
00000000 - 0fffff
00000000 - 0fffff
00000000 - 0fffff
00000000 - 0fffff
00000000 - 0fffff
00000000 - 0fffff
00000000 - 0fffff
00000000 - 0fffff
[OK] Memory Map
[i] Running Speed Test for 5 seconds...
[i] 5713
[i] 5728
[i] 5734
[i] 5773
[i] 5795
[OK] Speed Test
[i] Running Throughput Test on 100,000 pages (this may take a moment)...
[OK] Throughput Test
== Speed Test Results (4kB Reads) ==
Total Read Speed: 5,759/sec
Total Reads: 20,743
Failed Reads: 0 (0.00%)
Fastest Read: 149 µs
Slowest Read: 272 µs
Average Read: 174 µs
[i] Test Result: PASS
== Throughput Test Results (4kB Reads) ==
Total Read Throughput: 196.34 MB/s
Total Pages: 100,000
Failed Pages: 0 (0.00%)
[i] Test Result: PASS
[i] Overall Test Result: PASS
[CORE] SHUTDOWN COMPLETED (000000002D05040).
```

You're now ready to start cheating, open a DMA cheat loader of your choice and have fun.

TROUBLESHOOTING

VM ININIT FAILURE

In most cases, flipping the cable 180 degrees in the data port resolves about 90% of connection issues.

If that doesn't work, make sure the cable is fully inserted into the port until you hear the Windows connection sound—this typically fixes the remaining 10% of problems.

Slow Speeds or card failing.

This could be one of two things: either your second PC doesn't meet the hardware requirements to support the DMA card, or the card isn't seated properly in the PCIe slot. Try switching it to a different PCIe slot if available—some slots provide better compatibility or bandwidth, depending on your motherboard.

How to get your DNA ID

Download the the [**DNA Grabber**](#)

1. Insert cable into Jtag/Update port
2. Open the Tool and head over to Retrieve DNA ID
3. Open the config and select either 35T or 75T depending on your card and Click Retrieve DNA ID
4. Click Copy and give it to us in a ticket and well build your FW

Congrats! you successfully grabbed your DNA

description: >- All of this will be done on the Second-PC unless specifically instructed otherwise.

How to Flash a 35T DMA Card

For Squirrel 35T / Captain 35T DMA

1. Make sure the DMA is properly inserted in a PCIe slot on the Gaming-PC.
2. Make sure that the Gaming-PC is powered on.
3. Plug the DMA USB-Cable into the "Update" port or "JTAG" on the DMA Card and the other end into the 2nd-PC.

Download DMA Flash Files: [**DMA-Flash-Files**](#)


4. Go into the Flash Tools folder and open "zadig-2.8.exe".
5. In Zadig open "Options" - Tick "List All Devices" and select "Quad RS232-HS (Interface 0)"

-> It is important that you select "Interface 0"!

-> If you do not see the "Quad RS232-HS" options and instead see a "FTDI SuperSpeed-FIFO Bridge" it most likely means that you are plugged in the Data port and not the Update Port.

• Make sure the driver where the arrow is pointing at says WinUSB ("Version number") and press Replace Driver.

-> Make sure that it says that the installation was successful and it looks like the after picture.



Go into the OCD folder.

Copy your firmware file into Flash Tools folder and change the Flash_screamer config to that name. as shown in the image below.

Name	Date modified	Type	Size
 bscan_spi_xc7a35t.bit	7/2/2020 8:52 AM	BIT File	256 KB
 cygusb-1.0.dll	6/2/2022 9:49 PM	Application exten...	124 KB
 cygwin1.dll	6/2/2022 9:49 PM	Application exten...	3,456 KB
 flash	6/2/2022 9:49 PM	Windows Batch File	1 KB
 flash_screamer	4/25/2024 10:58 AM	CFG File	1 KB
 jtagspi	6/2/2022 9:49 PM	CFG File	1 KB
 openocd	6/2/2022 9:49 PM	Application	20,090 KB
 xilinx-xc7	6/2/2022 9:49 PM	CFG File	2 KB
 0072cdc01339085c_EACBE_75T.b	3/28/2023 11:02 AM	BIT File	2,024 KB

Undo

Cut

Copy

Paste

Delete

Select All


Right to left Reading order

Show Unicode control characters

Insert Unicode control character >

Open IME

Reconversion



Double click flash.bat file → Might take up to 5 minutes.

Make sure it looks like in the picture below!

```

C:\WINDOWS\system32\cmd.exe

C:\Users\user1\Desktop\elitegame\Screamer\DMASTuff\Ocd>openocd -f flash_screamer.cfg
Open On-Chip Debugger 0.10.0+dev-01289-g8833c889 (2020-06-26-21:35)
Licensed under GNU GPL v2
For bug reports, read
    http://openocd.org/doc/doxygen/bugs.html
DEPRECATED! use 'adapter driver' not 'interface'
Info : auto-selecting first available session transport "jtag". To override use 'transport select <transport>'.
DEPRECATED! use 'adapter speed' not 'adapter_khz'
Error: libusb_open() failed with LIBUSB_ERROR_NOT_SUPPORTED
Info : ftdi: if you experience problems at higher adapter clocks, try the command "ftdi_tdo_sample_edge falling"
Info : clock speed 10000 kHz
Info : JTAG tap: xc7.tap tap/device found: 0x0362d093 (mfg: 0x049 (Xilinx), part: 0x362d, ver: 0x0)
Info : JTAG tap: xc7.tap tap/device found: 0x0362d093 (mfg: 0x049 (Xilinx), part: 0x362d, ver: 0x0)
Info : Found flash device 'issi is25lp256d' (ID 0x0019609d)
Warn : device needs paging or 4-byte addresses - not implemented
Info : Found flash device 'issi is25lp256d' (ID 0x0019609d)
Warn : device needs paging or 4-byte addresses - not implemented
Info : Found flash device 'issi is25lp256d' (ID 0x0019609d)
Warn : device needs paging or 4-byte addresses - not implemented
Info : Found flash device 'issi is25lp256d' (ID 0x0019609d)
Warn : device needs paging or 4-byte addresses - not implemented
Info : sector 0 took 88 ms
Info : sector 1 took 98 ms
Info : sector 2 took 108 ms
Info : sector 3 took 109 ms
Info : sector 4 took 103 ms
Info : sector 5 took 101 ms
Info : sector 6 took 97 ms
Info : sector 7 took 84 ms
Info : sector 8 took 98 ms
Info : sector 9 took 102 ms
Info : sector 10 took 103 ms
Info : sector 11 took 108 ms
Info : sector 12 took 99 ms
Info : sector 13 took 97 ms
Info : sector 14 took 110 ms
Info : sector 15 took 89 ms
Info : sector 16 took 91 ms
Info : sector 17 took 102 ms
Info : sector 18 took 95 ms
Info : sector 19 took 91 ms
Info : sector 20 took 107 ms
Info : sector 21 took 100 ms
Info : sector 22 took 91 ms
Info : sector 23 took 82 ms
Info : sector 24 took 109 ms
Info : Found flash device 'issi is25lp256d' (ID 0x0019609d)
Warn : device needs paging or 4-byte addresses - not implemented
shutdown command invoked

```

7. After Shows Shutdown Command invoked in the last line, Change to the Data USB-Port on the DMA.

8. Fully shutdown Main PC and wait 3-5 Minutes

9. Run **DMA Speed Test** File as Admin.


If, DMA test shows reading means DMA Working.


You are done with the flashing guide.

description: >- This guide will cover the cabling and setup process for the godlike touch fuser.

Setting up your godlike Fuser


Resolution check





Before doing anything with the fuser. Ensure that the two systems you intend on using with the fuser are set to the same resolution and refresh rate.

Hardware Install



1. Connect the Fuser to the **yellow** power port using the provided power cable.
2. Attach your primary display, which you'll use throughout your experience, to the **red**-labeled display port.
3. Connect an HDMI cable from your main PC (via either the GPU or motherboard) to the **blue**-labeled HDMI port.
4. Connect another HDMI cable from your second PC (via either the GPU or motherboard) to the **purple**-labeled HDMI port.
5. Turn on the Fuser by pressing the power button on the front (not labeled in the image).

Settings Page



****Blue****: Enable or disable fusion

****Purple****: Mode selector

****Red****: Switch between displays when not actively fused

****Yellow****: Adjust the intensity of the overlaying display


White: Work in Progress, refer to our discord.

Resolutions Page



Select your desired resolution and refresh rate from this page.

Conclusion



Active display fusion is confirmed when all four lights on the front panel are illuminated. This completes the instructions for the 4K Fuser. If you have any questions or encounter any issues, please feel free to reach out to us [here](#).

Troubleshooting

Issue: All four lights on the front of the Fuser are solid, but the monitor displays a black screen.

Steps to Resolve:

1. In both Windows display settings and your GPU's application settings, set both displays to 1920×1080 resolution at 60Hz.
2. Restart both PCs by performing a full power cycle.
3. Disconnect your main monitor, then plug it back in.
4. Reconnect the Fuser properly, ensuring all three cables are securely in their correct ports.
5. Make sure the Fuser is powered on, then press the EDID button.
6. Wait approximately 30 seconds, then press the 1K60 option.
7. If the main display remains black, repeat step #3.
8. If your display is functioning correctly, gradually increase the refresh rate and resolution until you reach your desired settings.

Button Fuser setup

Thank you for choosing Midnight-Market for your cheesing needs.

Please check out our DMA Cards and other products at Midnight-market.ca

Fuser Information

Recommended Cables:


2x 8K HDMI Cables - [Purchase Here](#)

1x HDMI -> DisplayPort Cable - [Purchase Here](#)

Supported Resolutions:


1920x1080, 2560x1440, 3840x2160, 2560x1080, 3440x1440

– 4k@60Hz – 2k@144hz – 1k@240Hz -




Indicator Lights :

- 【D1】: Power light (normal when always on)
- 【D2】: Fusion overlay function on/off indicator light
- 【H2】: HDMI2 slave input signal light (normal if always on)
- 【H1】: HDMI1 host input signal light (normal if always on)




Interface :

- 【 HDMI Output 】: Connect the Gaming PC monitor
- 【 HDMI1 INT 】: Connect the Gaming PC graphics card
- 【 HDMI2 INT 】: Connect the 2nd PC graphics card
- 【 UART 】: Update / Flash Port
- 【 DC12V 】: Power supply via power cord (default 12V2A)



Fuser Key Functions




Key Functions :

- **【Power】**: Power switch
- **【K1】**: Short press: Cycle through resolutions, 1920*1080, 2560*1440, 3840*2160, 2560*1080, 3440*1440, factory default 1920*1080
- **【K1】**: 3 Second Press: (press and hold until displayed): the current resolution and refresh rate are displayed in the upper left corner of the screen, with host information on the top and slave information on the bottom.
- **【K2】**: Short press: cycle to switch the upper layer RGB cutout intensity, 0-20 levels in total, 21 levels, factory default 0 (0 also cuts out the picture)
- **【K3】**: Short press: Restore the upper layer RGB cutout strength to the factory default 0
- **【K4】**: Short press: turn on/off the fusion overlay function


Flashing Fuser


1. Prep your gaming system by ensuring that only your gaming monitor is plugged into your PC, once this is done boot up your gaming PC.

2. Download and install Monitor Asset Manager ([mi_setup.exe](#))




3. Download and Run as Admin Monitor Asset Manager ([MonInfo.exe](#))







4. Once Monitor Asset Manager loads, Select the first Display ID




5. Click File -> Save As




6. Select your Save Location and save .bin file (naming does not matter)
7. Open the Device Manager




8. Plug in the Power Cable to the Fuser
9. Connect the USB-C to the UART
10. Connect the other end of the USB to your Gaming PC



11. Power on the DMA Kings Fuser
12. Go back to the Device Manager and right click any device and **scan for hardware changes**



13. Locate Ports (COM & LPT) and notate which COM port the Fuser is assigned to, in this case COM9 (Note: you may have other devices in this so be sure to check which device is the Fuser)



14.

Download and Run as Admin ([flasher](#))  DMAKings_FuserFlash_V1.0.exe

15. Flash the DMA Kings Fuser with your Monitors .bin File

1. UART COM: Select the COM Port of the Fuser from - Step 12
2. Select your Gaming Monitor Screen Size / Resolution
3. Select Load Config
4. Click Select Config - Locate your .bin file you saved in - Step 6
5. Finally Click [Inject Config] to Flash your Fuser Device.
 - Note your screen will go black momentarily during the injection process
 - After injection, your screen will come back and the tool will give you a message, just press OK.
6. Unplug the USB-C cable from the Fuser device

The screenshot shows the DMAKings Injection V1.0 software interface. Red arrows and numbers 1 through 5 highlight specific controls:

- 1**: Points to the UART COM dropdown menu, which is currently set to COM4.
- 2**: Points to the Screen Size selection area, where 3440x1440 is selected.
- 3**: Points to the Method selection area, where Load Config is selected.
- 4**: Points to the Select config button.
- 5**: Points to the Inject Config button.

The interface includes fields for Manual Config (MOD Name, Pixelclock, Mhz, MFR Name, HDP, HBlank, HFP, HSW, S/N, VDP, VBlank, VFP, VSW, MFG Date) and a section for FW Injection Mode with a text input field, a Select FW button, and an Injection FW button.

16.


You can now connect your Fuser to your machines.


17. Please make sure to set the refresh rates of both the Gaming PC Monitor and 2nd PC monitor it is recommended to have the same refresh rate on both to have the best experience.

No display before / after flashing Fuser / other things

1. Use K1 key to cycle between the display resolutions, give it a few seconds after each press.
2. If you are still not getting any display, disconnect the fuser and set your monitor display to 1920x1080
3. Re-attach the fuser and cycle through to the factory setting 1920x1080
4. You should now have video, we recommend you reflash your device after this step.

Make sure both screens are set to the same resolutions/HZ and scale layout





Rust Ban Help

What Bans are there in Rust?

Game Ban:

This is a ban applied by Rust's developers or anti-cheat systems like Easy Anti-Cheat (EAC). It prohibits you from accessing Rust on any server that employs EAC.

HWID Ban:

Hardware Identification (HWID) bans are more severe as they tie your ban to your computer's hardware.

Server IP Ban:

Some servers may ban your IP address if you're caught cheating. This prevents you from accessing that specific server again.

How to bypass each ban?

****Game Ban:****

If you receive a Game Ban in Rust, your account is permanently restricted from accessing any servers protected by Easy Anti-Cheat (EAC). EAC is highly aggressive, often issuing both Game and HWID bans simultaneously upon a single violation. To bypass a Game Ban, you'll generally need to purchase a new Rust account. Websites like G2G.com offer full-access accounts, while platforms like LZT.Market provide temporary accounts.

****HWID Ban:****

A Hardware ID (HWID) ban is even more severe, targeting your computer's hardware and preventing gameplay, even if you create or buy a new Rust account. Due to EAC's aggressive enforcement, HWID bans commonly accompany game bans after the first violation.

Before bypassing a HWID ban, it's essential to thoroughly remove all traces of Rust and associated files using powerful tools like **Revo Uninstaller**. Follow these steps:

1. **Initiate Uninstall:**
 - Right-click Rust and select "**Uninstall**".
2. **Initial Analysis and Uninstall:**
 - Skip creating a restore point.
 - Perform the built-in uninstall process.
 - Select "**Advanced**" scanning mode and press "**Scan**".
3. **Delete Leftover Registry Items:**
 - Review detected registry entries.
 - Click "**Select All**", then "**Delete**", and proceed with "**Next**".
4. **Remove Leftover Files and Folders:**
 - Select all leftover files and folders.
 - Click "**Delete**" and then "**Finish**" to finalize the process.

After completing these steps, proceed by using an HWID spoofer. You can use our **Temporary Spoofer** for short-term use or our **Perma Spoofer**, which permanently masks your computer's unique hardware identifiers but requires a Windows Reinstall, allowing you to safely play Rust again without detection on new accounts.

****IP Ban:****

If you're IP banned from a Rust server, your IP address has been blocked from accessing that specific server, typically due to cheating. You can bypass this type of ban by using a Virtual Private Network (VPN). However, some servers actively block VPNs, so it's recommended to use a residential VPN for the best results.

Note: When you receive a Game Ban, server administrators can often see your previously game-banned account linked to your new account through your IP. This means that even if you purchase a new account, you might still face manual server bans if admins recognize your banned history some good VPNs to counter this are: [Star Residential VPN \(Good for Legit Play\)](#) [Mysterium Dark \(for rage play\)](#)

EFT Ban help

What Bans are there in EFT?

Error 229 Ban:

This is a ban applied by BSG or anti-cheat systems like Battle Eye (BE). It prohibits you from accessing EFT on that account. **(Don't bother emailing BSG to get unbanned. They don't unban.)**

HWID Ban:

Hardware Identification (HWID) bans are more severe as they tie your ban to your computer's hardware. HWID bans typically happen when the cheat you were using gets detected in a ban wave.

How to bypass each ban?

Error 229 Ban:

If you receive a ban on EFT, it means your account is banned from playing the game entirely. The simplest way to bypass this ban is to purchase a new EFT account. Websites like G2G.com offer full access accounts, while LZT.Market provides temporary accounts. Be sure to [Revo Uninstall](#) both BSG Launcher & EFT Game.

HWID Ban:

A HWID ban is more severe as it's tied to your computer's hardware. Even if you create a new account, you won't be able to play EFT on the banned hardware. To bypass this ban, you can use a HWID spoofer. Options like [Perma Spoofer](#) & [TEMP SPOOFER](#) are effective for EFT & other games. Be sure to [Revo Uninstall](#) both BSG Launcher & EFT Game. **Selecting Powerful Uninstall for both.** Then reinstall BSG & EFT While using a spoofer on a new account is REQUIRED. Going forward you will need to use a spoofer to even open the BSG launcher. Failure to do so will result in an instant ban or delay HWID Ban. (Can range from a few hours to a few days)

Guidelines to Avoid Bans in EFT

Follow these tips to keep your account safe:

1. **Moderate Your Stats:** Balance your headshot %, PMC/Scav kills, and K/D ratio.
2. **Limit PMC Kills:** No more than 10 PMC kills per hour. High velocity of reports => Very fast ban
3. **Minimize Reports:** Avoid gameplay that could lead to being reported.

4. **Play Time Matters:** Accounts with higher play hours are less likely to be banned.
5. **EOD/Unheard Accounts:** EOD /Unheard Edition accounts are generally less likely to get reported.
6. **Usage of Risky Functions:** Risky functions triggering tripwires on EFT's server side may cause you to be flagged for a ban.

DayZ Ban Help

Information about Bans, Servers, and Tools Used

Server Bans

- Server bans are not related to game bans.
 - If banned on one community server, you can still play on others, including official servers.
 - Some servers share ban lists. For example:
 - If banned on **Rearmed**, you may get banned on **Kryptic**, since Kryptic uses Rearmed's ban list.
-

CFF Tools

CFF Tools is a paid admin tool (cftools.com) that collects extensive player data on community servers. Data collected includes:

- Hit count and % in each bone
- Kill/death ratio (KD)
- Hours played
- All nicknames used
- Alternate accounts

Admins can also share ban data, including community-wide ban lists.

Custom PBOs

Some servers implement custom PBOs (e.g. Server Side Anti-cheat). These tools track:

Logs

- **Kill Logs:** Killer, victim, distance, weapon, positions
- **Item Logs:** Grabs, usage, drops, storage
- **Interaction Logs:** Looting, shooting, damage dealt/taken
- **Playtime Logs:** Login/logout times, disconnect reasons

Detections

- **Position Detection:** Detects teleport/speed cheats via velocity
- **Magic Bullets Detection:** Suspicious kills with low-caliber bullets from long range
- **No Recoil Detection:** Unnatural aim angles
- **Tracer Drawing:** Bullet trajectory tracing (live and logged)
- **Dupe Detection:** Item ID duplicates; warns on stash-before-restart behaviors

Tracking

- MAC address logs
 - IP range logs
 - File trace logs (Steam, DayZ settings, temp folders)
 - Geo-location tracking
-

How to Avoid Bans

Cheat Features to Avoid

- **Speed Hack:** Detected by anti-cheat bots
- **Magic Bullets/Silent/Murder Mode:** Easy to catch
- **Change Day Time:** Can look suspicious to admins spectating
- **No Recoil:** Affects aiming behavior
- **Free Cam/No Clip:** Leaves detectable "items"
- **Teleport:** Often detected by server-side tools

Legit-looking Behavior Tips

- **Discord:** Use separate accounts for cheat and legit servers
- **Looting:** Don't run straight to stashes—act natural
- **ESP:** Don't move your view directly toward enemies
- **Game Sense:** Avoid obviously tracking players
- **Account:** Use aged accounts with real playtime, not idle hours

Tip: You can buy CFF Tools to check your own stats—but **never tell an admin**.

Evade Server Bans

Getting banned on a community server can lead to being chain-banned elsewhere. Here's how to avoid detection:

Steps

1. **Delete Traces:** Use Revo Uninstaller or reset Windows via USB (preferred)
2. **Spoof IP:** If dynamic IP doesn't work, use a **private proxy**
3. **Nickname:** Double-check launchers for name changes
4. **New Account:** Must be aged with real hours (check G2G or LoLZ)

Alt Tip: Join a server with a VPN. Even if you get kicked, your account links with 500+ others—confusing admins.

Things That Can Be Tracked

- IP
 - Game nickname
 - Steam name
 - MAC address
 - IP range
 - Geo-location
 - File traces (%temp%, appdata, Steam userdata)
-

Let me know if you'd like this exported as a markdown file or formatted for a different platform.

Gray Zone Ban Help

NO TLDR. Read everything!!!

Okay, I wanted to take some time to warn people here who will use ANY Cheat in Grayzone Warfare. From the looks of it the game is not only utilizing EAC but also Anybrain Anti Cheat. This is a new AC in the market that is attempting to use AI to detect players. The claims they made a year ago might be something to take seriously for some of you who would like to stay under the radar and keep your accounts clean.

What is Anybrain?

Anybrain is a leveled-up version of Fairfight. The idea is to utilize AI to do what Fairfight does in 6 months down to 5 minutes. So they **claim**.

Why Am I reading this?

Here is the problem, currently they are NOT issuing bans even though people are using shoot-through walls, insane aimbots, Speed hacks, etc. Features, a company like Anybrain wouldn't take more than 3 minutes to detect and ban. **(According to their claims)** This leads us to believe they are collecting data. A lot of data... **Data such as:** Streamers AKA Top 1% People who spam PVE to do only Quests but are good at it > Top 10% etc. People who are playing legit but good at PVP (PVP Data for the top 10%) People who cheat in RAGE settings so they know what Aimbot, Speedhack, and Magic Bullets data look like. (Smooth 1 users I'm

looking at you ) If you believe they will ban people at some point... Which you should cause EAC in this game is... Well, let's say not effective. It would help if you didn't do anything that will give them invalid/non-human data such as:

- Wallbanging AI/Players Constantly
- Shooting at AI/Players with a shitty weapon that is not meant to be shot at that distance.
- Using Aimbot (This is one of the most insane things they claim they can detect, smooth does not help here, flat out don't use it.)
- Using any type of misc; No Recoil > Spread > Sway.

Until they start issuing bans all of this is nothing more than speculation. However, from what they share it's clear to make such assumptions. **(This was written on May 6th 2024)**

YOU HAVE BEEN WARNED

We warn so you don't come crying when you are banned asking "Why is my account banned" when all you do is go to town with 300 bullets and spam AI all day with Aimbot.

B550 Warning

A rare issue has been identified with certain B550 motherboards—mainly ASUS models—where a security driver incorrectly flags DMA devices, regardless of the firmware used. This can result in bans when playing games that use Easy Anti-Cheat (EAC). Although the majority of reports involve ASUS boards, a few isolated incidents have occurred with other brands, though these are extremely uncommon.

Other chipsets like the B450 and B650 are entirely unaffected by this issue. The problem appears consistently across all types of DMA firmware, including Basic (CFW), Premium (Valorant CFW), and Ultimate (Emulated FW).

For a more reliable and worry-free experience, choosing a non-B550 motherboard is your safest bet. If you do opt for a B550 board—especially an ASUS model—be sure to test thoroughly in low-risk environments first. For most users, the chances of encountering this issue remain very low.

How to downgrade from win 11 to 10

Why should i downgrade from windows 11 to 10?

1. **Stronger Virtualization & Kernel Protections** – Microsoft is doubling down on security with Hypervisor-Protected Code Integrity (HVCI), making it even tougher to modify system behavior or run unsigned code.
2. **Automatic Update Enforcement** – Windows 11 24H2 aggressively forces updates, meaning even if you disable updates, it might re-enable them, breaking tools or bypasses over time.
3. **Restricted Driver Support** – The update tightens driver signing enforcement, preventing older or custom drivers from working—this kills many low-level workarounds for automation, spoofing, or exploits.
4. **AI & Cloud-Based Detection** – Microsoft is integrating more cloud-based security features, making it easier for them to detect unusual behavior, block unsigned software, and even remotely enforce security patches.

How do I downgrade?

1. Back Up Important Files

Before reinstalling, save important files to an external drive or a cloud service like Proton Drive, Google Drive, or OneDrive.

2. Create a Windows 10 Installation USB

- Download the Windows 10 Media Creation Tool from [Microsoft's website](#).
- Plug in a USB drive (16GB Recommended).
- Run the tool and select "Create installation media" → Choose USB flash drive → Let it finish.

3. Boot from the USB

- Restart your PC and enter BIOS/Boot Menu (usually by pressing F2, F12, DEL, or ESC during boot).
- Select your USB drive as the boot device.

4. Install Windows 10

- Click Install Now and choose Custom Installation.
- Select your main drive (delete old partitions if needed) and install Windows.

5. Finish Setup

- Let Windows install and set up your user account.
- Install drivers and updates.
- Restore your backed-up files.

6. (Optional) Disable Security Updates to Avoid Forced Windows 11 Upgrade

- Download Chris Titus' Windows Utility from [GitHub](#).
- Run the script and go to the Tweaks section.
- Disable Windows Updates and Telemetry to prevent forced upgrades to Windows 11.

If all is done correctly you'll be on a fresh windows 10 install.

If you're confused and don't understand a certain part refer to this [Video](#)