



Equity Production Component User's Guide

Version 8.0

Copyright

Copyright © 2011 Allegro Development Corporation. All rights reserved.

Your right to copy this documentation is limited by copyright law and the terms of the software license agreement. As the software licensee, you may make a reasonable number of copies or printouts for your own use. Making unauthorized copies, adaptations, compilations, or derivative works for commercial distribution is prohibited and constitutes a punishable violation of the law.

Trademarks

Allegro and Connect are either registered trademarks or trademarks of Allegro Development Corporation in the United States and/or other countries.

The names of actual companies and products mentioned herein may be trademarks or registered marks - in the United States and/or other countries - of their respective owners.

The names of companies, products, people, and/or data used in window illustrations and sample output are fictitious and are in no way intended to represent any real individual, company, product, or event, unless otherwise noted.

Warranty disclaimer

Allegro Development Corporation disclaims any warranty regarding the sample data or code contained in this documentation, including the warranties of merchantability and fitness for a particular purpose.

Limitation of liability

The content of this manual is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Allegro Development Corporation. Allegro Development Corporation assumes no responsibility or liability for any errors or inaccuracies that may appear in this manual. Neither Allegro Development Corporation nor anyone else who has been involved in the creation, production or delivery of this documentation shall be liable for any indirect, incidental, special, exemplary or consequential damages, including but not limited to any loss of anticipated profit or benefits, resulting from the use of this documentation or sample code.

License agreement

Use of this product is covered by a license agreement provided with the software product. If you have any questions, please call the Allegro Product Support Department at 214-237-8000.

Publication date

July 2011

Part number

PRP-EQPUG-008000

Contents

Introduction.....	6
What's in this guide?	6
Symbols and conventions	8
Additional resources	8
 Part 1: Parameter Setup	 10
Chapter 1: Overview	11
Integration with other components	12
Chapter 2: Equity Production Component Setup	13
Before you use the Equity Production Component	13
Setting up the Equity Production Component	15
 Part 2: Procedures	 20
Chapter 3: Production Forecast	21
Create Production Forecast Based on Field Production Volume	21
Create Production Forecast Based on Historical Volume	24
Revise Default Production Forecast Based on Field Estimates	26
Revise Default Production Forecast Based on Pipeline Maintenance	28
Chapter 4: Natural Gas Balancing (Wellhead).....	31
Balance WIOs to Determine Right-to-Market Quantities	31
Revise WIO Balancing Right-To-Market Quantities	33
Chapter 5: Gas Available For Sale	35
Create Gas Available for Sale Notifications for Take-In-Kind WIO	35
Revise Gas Available for Sale Notification for Take-In-Kind WIO	37
Chapter 6: Production Measurement	39
Enter Daily Production Measurement Quantities by Property	39
Chapter 7: Production Positions	41
Review Summary of PRODUCTION Positions and WIO Balancing	41
Chapter 8: Nominations	43

CONTENTS

Create and Adjust Nominations Due to Production Variances	43
Review and Adjust Nominations Due to Production Variances	44
Chapter 9: NG Operator Actualization	47
Calculate Shipper Allocation Based on Point Operator Statement	47
Chapter 10: Production Variance	50
Analyze Variance between Production Forecast and Daily Production Estimate	50
Chapter 11: Pipeline Variance	52
Analyze Variance between Daily Production Estimates and Production Actuals	52
Part 3: EquityProd Class	55
Parameters	55
Icons	55
Chapter 12: Equity Production Parameters View	56
View access procedure	56
Standard panes and columns	57
Standard selection criteria	60
View-specific time periods	61
Part 4: EquityProdForecast Class	63
Parameters	63
Icons	63
Chapter 13: Production Positions View	64
View access procedure	64
Standard panes and columns	64
Standard selection criteria	70
View-specific time periods	70
Part 5: EquityProdBalance Class	72
Parameters	72
Icons	72
Chapter 14: Balancing View	74
View access procedure	74
Standard panes and columns	74

Standard selection criteria	78
View-specific time periods	78
Chapter 15: Nominations View	79
View access procedure	79
Standard panes and columns	79
Standard selection criteria	83
View-specific time periods	84
Part 6: EquityProdNotifications Class	86
Parameters	86
Icons	86
Chapter 16: Shipper Notification View	87
View access procedure	87
Standard panes and columns	87
Standard selection criteria	90
View-specific time periods	91
Part 7: EquityOpActual Class	93
Parameters	93
Icons	93
Chapter 17: Operator Actuals View	95
View access procedure	96
Standard panes and columns	96
Standard selection criteria	99
View-specific time periods	99
Part 8: EquityProdMeasurement Class	102
Parameters	102
Icons	102
Chapter 18: Gathering System Measurement View	105
View access procedure	105
Standard panes and columns	105
Standard selection criteria	107
View-specific time periods	108

CONTENTS

Chapter 19: Production Measurement View 109

 View access procedure 109

 Standard panes and columns 109

 Standard selection criteria 112

 View-specific time periods 112

Chapter 20: Gathering System Actuals View 113

 View access procedure 113

 Standard panes and columns 113

 Standard selection criteria 121

 View-specific time periods 121

Chapter 21: Pipeline Variance View 123

 View access procedure 123

 Standard panes and columns 123

 Standard selection criteria 125

 View-specific time periods 125

Chapter 22: Production Variance View 127

 View access procedure 127

 Standard panes and columns 128

 Standard selection criteria 129

 View-specific time periods 129

Glossary 133

INTRODUCTION

Introduction

Welcome to the Equity Production component, an important part of your energy transaction and risk management system. You can use the Equity Production component to capture production forecasts, calculate gas balancing, capture production estimates, create nominations, and capture actual volumes.

If the Equity Production component is integrated with other Allegro components (e.g., Contract, Trade, Natural Gas, Power, and other logistics components), you can define marketing and gathering arrangements, track and schedule equity oil or gas production positions, and automate production estimates and balancing.

This introduction is divided into the following sections:

- [*What's in this manual*](#)
- [*Symbols and conventions*](#)
- [*Additional resources*](#)

What's in this guide?

This guide is designed to give you an understanding of how to use the features of the Equity Production component and how it integrates with the Allegro system.

The guide is divided into the following parts:

- [*Part 1, Parameter Setup*](#), provides information about setting up your Equity Production component.
- [*Part 2, Procedures*](#), provides information about the various procedures that you can use in conjunction with Equity Production.
- [*Part 3, EquityProduction Class*](#), provides information about the structure of each View associated with the EquityProduction class of the Equity Production component, including View access procedures, a description of the standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.
- [*Part 4, EquityProdForecast Class*](#) provides information about the structure of each View associated with the EquityProdForecast class

of the Equity Production component, including View access procedures, a description of the standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.

- [*Part 5, EquityProdBalance Class*](#), provides information about the structure of each View associated with the EquityProdBalance class of the Equity Production component, including View access procedures, a description of the standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.
- [*Part 6, EquityProdNotifications Class*](#), provides information about the structure of each View associated with the EquityProdNotifications class of the Equity Production component, including View access procedures, a description of the standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.
- [*Part 7, EquityOpActual Class*](#), provides information about the structure of each View associated with the EquityOpActual class of the Equity Production component, including View access procedures, a description of the standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.
- [*Part 8, EquityProdMeasurement Class*](#), provides information about the structure of each View associated with the EquityProdMeasurement class of the Equity Production component, including View access procedures, a description of the standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.

INTRODUCTION

Symbols and conventions

This guide was written using US English. For definitions of unfamiliar terms, see the glossary in this guide.

This guide uses the following symbols to make specific types of information stand out.

Symbol	Description
	The light bulb symbol indicates helpful tips, shortcuts, and suggestions.
	The warning symbol indicates situations you should be especially aware of when completing tasks. Typically, this includes cautions about performing steps in their proper order, or important reminders about how other information in the system may be affected.

This guide uses the following conventions to refer to sections, navigation, and other information.

Convention	Description
Data >> Print	The (>>) symbol indicates a sequence of actions, such as choosing items from a menu, toolbar, or palette, or pressing buttons in a window. This example directs you to go to the Data menu and choose Print.
TAB or ENTER	Small capital letters indicate a key or a key sequence.

Additional resources

Use the following tools to learn how to use Allegro. Many of the documentation resources are provided in online format, either as an online help file or as an Adobe Acrobat .PDF file.

To learn about Allegro:

To view information about Allegro screens, choose Help >> Contents and Index.

To view electronic guides in Adobe Acrobat PDF format, contact Allegro support for the location of the manual.

PART 1: PARAMETER SETUP

Part 1: Parameter Setup

This part of the documentation provides information about setting up your Equity Production component for initial use.



*You will need to complete these setup procedures prior to using the procedures described in the **Part 2 Procedures** section, which describes on-going tasks specific to the Equity Production component.*

The setup procedures generally need to be completed once, but you can refer to the information at other times for instructions on modifying existing entries.

The following information is discussed:

- [Chapter 1, "Overview,"](#) provides an overall flow of Equity Production information and describes how the Equity Production component integrates with other Allegro components.
- [Chapter 2, "Equity Production Component Setup,"](#) explains the tasks you must complete to setup your Equity Production component for initial use.

Chapter 1: Overview

You can use the Equity Production component to forecast and build nominations, perform gas balancing, and capture and allocate actual volumes.

The Equity Production component is an incremental feature of your overall Allegro solution, and represents one of many components that Allegro offers in providing solutions to your company.

This part of the documentation provides an overall flow of Equity Production information and provides further information about integration of the Equity Production component with other Allegro components.

The following information is discussed:

- [Integration with other components](#)

Integration with other components

The Equity Production component integrates with other Allegro components, which, if licensed, provide additional functionality to your system.

Property integration If you're also using Allegro to forecast production volumes, perform working interest owner balancing,, estimate what will be available to nominate to the pipeline and to submit estimated nominations to TIK owners,, use the Property Component to define the relationships between the producing properties.

Natural Gas integration If you're also using Allegro to forecast production, manage ownership and seller arrangements, the resulting physical natural gas positions can be scheduled using the Natural Gas component.

Other Allegro Components

The remaining Allegro components are not directly integrated with the Property component but are supported through their interrelationship with other components.

- Systems Admin
- Connect
- Messaging
- Document

Chapter 2: Equity Production Component Setup

The default options and parameters that you choose before processing transactions into your Equity Production component will ensure that information flows as expected when you begin using the system to operate your business.

This part of the documentation explains the tasks you must complete to setup your Equity Production component for initial use.

The following information is discussed:

- [Before you use the Equity Production component](#)
- [Setting up the Equity Production Component](#)



After you've completed a setup procedure, you can choose Data >> Print to print the setup record and verify the information.

Before you use the Equity Production Component

Global Parameter Set Up

Before proceeding, you should have completed the following global set up procedures:

- Set up time period
- Set up product
- Set up product class
- Set up product type
- Set up unit
- Set up location type
- Set up location
- Set up country
- Set up county
- Set up city

CHAPTER 2: EQUITY PRODUCTION COMPONENT SETUP

- Set up region
- Set up state/province

If you haven't completed each of the preceding tasks, do so before continuing. If you haven't completed each of the preceding tasks, do so before continuing. Refer to the applicable user guides for more information.

Contract Parameter Set Up

Before proceeding, you should have completed the following contract administration set up procedures:

- Set up company
- Set up counterparty
- Set up counterparty class
- Set up address
- Set up address code
- Set up contact class
- Set up exempt class
- Set up pay method
- Set up payment terms
- Set up salutation
- Set up pressure status
- Set up volume terms

If you haven't completed the preceding tasks, do so before continuing. Refer to the *Contract Component User's Guide* for more information.

Property Parameter Setup

Before proceeding, if you license the Allegro's Property component, you should have completed the following property set up procedures:

- Property
- Basin
- District
- Down class
- Field

- Prop class
- Prop status
- Prop type
- Prospect

If you haven't completed the preceding tasks, do so before continuing. Refer to the *Property Component User's Guide* for more information.

Natural Gas Parameter Setup

Before proceeding, you should have completed the following natural gas setup procedures:

- Set up pipeline
- Set up NG point
- Set up NG service
- Set up service rate and fee
- Set up NG interconnect
- Set up NG transport
- Set up NG loss

If you haven't completed the preceding tasks, do so before continuing. Refer to the *Natural Gas Component User's Guide* for more information.

Setting up the Equity Production Component

To set up	Refer to
Forecast statuses	Creating a Forecast status
Meters	Creating a Meter
Tanks	Creating a Tank
Tank Straps	Creating Tank Straps

After you've set up all required parameters, you should print reports to verify that information was entered correctly. You can use Data >> Print for each set up View.

Creating a Forecast status

The forecast status is the user-defined forecast source.

CHAPTER 2: EQUITY PRODUCTION COMPONENT SETUP


Generally forecasts are originated by the production department (e.g., Forecast Status = PRODUCTION) and then subsequently refined by the marketing department (e.g., Forecast Status = MARKETING). Each Forecast Status is assigned to a level with higher level forecasts given precedent over lower level statuses. Only the highest level Forecast Status is used in processes.

Typically, three or more forecast statuses will be defined:

- One forecast which is very high level and may be used for annual budgeting. This forecast status might not be scheduled; it is just captured for comparison purposes.
- PRODUCTION, the forecast generated by the Production department. This forecast is usually reviewed and revised monthly to reflect changes to the production.
- MARKETING, the forecast generated by the Marketing department. Typically the Marketing department takes the forecast from the Production department and modifies it using additional information gathered about the expected production from the properties. They will factor in scheduled maintenance (down times) and considerations from conversations with the various operators.

To create a forecast status:

1. Open the Property Parameters View (Navigation Sidebar >> Property >> Parameters >> Property Parameters).



The screenshot shows a software interface with two tabs: 'Property Parameters' (selected) and 'Workflow'. Below the tabs is a table titled 'Forecast statuses'. The table has five columns: 'Forecast status', 'Description', 'Sc', 'Status level', and 'Connection'. There are two rows of data: 'Marketing' with 'Marketing' description, a checked 'Sc' box, status level '1', and an empty 'Connection' field; and 'Production' with 'Production' description, a checked 'Sc' box, status level '2', and an empty 'Connection' field.

Forecast status	Description	Sc	Status level	Connection
Marketing	Marketing	☒	1	
Production	Production	☒	2	

2. Choose Pane >> Forecast Statuses.
3. Choose Data >> Select to retrieve existing records.
4. Enter forecast status record(s).
5. Choose Data >> Update to update record(s) to database.


Creating a Meter

PART 1: PARAMETER SETUP

Meters are linked to a Property to identify the measurement device used to measure the output (volume) from the property.

To create a meter:

1. Open the Properties View (Navigation Sidebar >> Property>> Parameters >> Equity Production Parameters).



Meter	Description	Pipeline	Point	Meter type	Downstream meter	Line size	Plate diameter	Orifice factor	Meter constant	Spec grav	Diff range
101902	Abbeville 3-3	Henry	Abbeville	Production							
101903	Abell 5-5	Santa Rosa	Abell	Production							
101908	Agua Dulce Stratton 4-3	Gulf Plains	Agua Dulce Stratton	Production							
101909	Anderson 10-6	Artesia	Anderson	Production							
101910	Andrews 13-2	Dollarhide	Andrews	Production							
101911	Andrews North 1-3	Fullerton	Andrews North	Production							


2. Choose Data >> Select to retrieve existing records.
3. Chose Pane >> Meters.
4. Use Home >> Insert to enter meter record(s) (see [Meters pane](#) for detailed column descriptions).
5. Choose Data >> Update to update record(s) to database.

Creating a Tank

Tanks are used for crude products only. Within tanks, you also establish tank strappings to translate tank gauge readings into volumes expressed in BBLs.

To create a tank:

1. Open the Equity Production Parameters View (Navigation Sidebar >> Property >> Parameters >> Equity Production Parameters).



Tank	Description	Location	Region	District	Capacity	Field	Product type	Height	Base volume	Tank incr	Height unit	Volume unit
1001	Bangchak Refinery		SE Asia		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1002	Botlek ExxonMobil		NW Europe		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1003	Europoort Nereco (BP/Chevron)		NW Europe		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1004	Pasadena ConocoPhillips		US Gulf		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1005	Pasadena ExxonMobil		US Gulf		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1006	Pennis Shell		NW Europe		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1007	Q8 Refinery Kuwait		NW Europe		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl

2. Choose Pane >> Tanks.
3. Choose Data >> Select to retrieve existing records.

4. Enter tank record(s) (see [Tanks pane](#) for detailed column descriptions).
5. Choose Data >> Update to update record(s) to database.

Creating a Tank strap

Tank strappings are used to translate tank gauge readings into volumetric measurements.

To create a tank strap:

1. Open the Equity Production Parameters View (Navigation Sidebar >> Property >> Parameters >> Equity Production Parameters).

Workflow		Equity Production Parameters	
Tank straps			
	Tank	Height	Quantity
▶	1001	36.00000000	14.83688890
	1001	72.00000000	14.83688497
	1001	108.00000000	14.83688366
	1001	144.00000000	14.83688245
	1001	170.00000000	14.57488235
	1002	36.00000000	14.83688890
	1002	72.00000000	14.83688497
	1002	108.00000000	14.83688366

2. Select a tank from the Tanks tab.
3. Choose Pane >> Tank straps.
4. Choose Data >> Select to retrieve existing records.
5. Use Home >> Insert to enter tank strap record(s) (see [Tank straps pane](#) for detailed column descriptions).
6. Choose Data >> Update to update record(s) to database.

PART 2: PROCEDURES

Part 2: Procedures

This part of the documentation provides information about the various procedures that you can use to optimize your supply and market planning decisions.

The following information is discussed:

- [Chapter 3, "Production Forecast"](#), provides procedures for entering and viewing production forecasts.
- [Chapter 4, "Natural Gas Balancing"](#), provides procedures for balancing interests, adjusting imbalances and creating nominations.
- [Chapter 5, "Gas Available for Sale"](#), allows you to create and revise gas available for sale (GAFS) notifications for take-in-kind interest owners.
- [Chapter 6, "Production Measurement"](#), explains how to enter daily production measurement quantities.
- [Chapter 7, "Production Positions"](#), allows you to review a summary of PRODUCTION positions and associated balancing details.
- [Chapter 8, "Nominations"](#), provides procedures for estimating and configuring nominations for submission to the pipeline.
- [Chapter 9, "NG Operator Actualization"](#), explains how to default and allocate operator best available quantities.
- [Chapter 10, "Production Variance"](#), explains how to use the Production Variance view to review forecasted versus estimated quantity variance by operator.
- [Chapter 11, "Pipeline Variance"](#), explains how to use the Pipeline Variance view to review estimated versus actual quantity variance by pipeline and point.

Chapter 3: Production Forecast

This part of the documentation provides procedures for capturing forecasts.

Prior to the month of production, forecasts of production should be entered into the Production Forecast View. Using the volumes captured here, the system will calculate monthly volumetric positions representing working interest owner (WIO) entitlements. Forecast volumes can be entered into Allegro in several ways:

- Manual entry in the Production Forecast View
- Loaded via an interface from a legacy forecasting system
- Prior month forecasts used as default

Different types of production forecasts can be captured. The different types are set up in the Property Parameters view (Navigation sidebar >> Property >> Parameters >> Property Parameters >> Forecast Status pane).

Typically, there are three types of forecasts:

- A very high level forecast used for annual budgeting. This forecast status might not be scheduled; it is just captured for comparison purposes.
- The forecast generated by the Production department. This forecast is usually reviewed and revised monthly to reflect changes to the production.
- The forecast generated by the Marketing department. Typically the Marketing department takes the forecast from the Production department and modifies it using additional information gathered about the expected production from the properties.


The following information is discussed:

- [Create Production Forecast Based on Field Production Volume](#)
- [Create Production Forecast Based on Historical Volume](#)
- [Revise Default Production Forecast Based on Field Estimates](#)
- [Revise Default Production Forecast Based on Pipeline Maintenance](#)

Create Production Forecast Based on Field Production

Volume

1. Open the Production Forecast view (Navigation sidebar >> Property >> Properties >> Production Forecast).
2. Choose Pane >> Prod Forecasts.
3. Choose a time dimension to filter the analysis (e.g., Time Range) from Parameters sidebar >> Time Period>> Time Column.
4. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period>> Time Period.
5. Filter the query request further by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [“Standard Selection Criteria”](#) for more details.
6. Choose Data >> Select to retrieve forecast results.
7. Verify estimated field production volume for each property meter is entered in a production forecast.



Property	Meter	Beg time	End time	Forecast status	Quantity	Unit	Time unit	Product	Validation	Operator
Angus		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	231.000000	bbl	DAY	E TX Sweet		Hess
Pelican		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	122.000000	bbl	DAY	E TX Sweet		Shell
Franklin		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	250.000000	bbl	DAY	LLS		Total Fina Elf Expl
Abbeville 3-3	101902	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,764.000000	mcf	DAY	NG		Delta Petroleum
Abell 5-5	101903	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,793.000000	mcf	DAY	NG		Energy Corp
Abell 5-7	102982	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,821.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 4-3	101908	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,877.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 4-5	102984	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,906.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 6-9	103395	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,934.000000	mcf	DAY	NG		Energy Corp
Anderson 10-6	101909	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	5,132.000000	mcf	DAY	NG		Energy Corp

8. From the Parameters sidebar, select the Forecast Status to use for next month's default production forecast.
9. Use the Equity Production Parameters View (Navigation sidebar >> Property >> Parameters >> Equity Production) to confirm that a status level is associated with the desired forecast status.

Property Parameters

Workflow

Forecast statuses

	Forecast status	Description	Sc	Status level	Connection
▶	Marketing	Marketing	☒	1	
	Production	Production	☒	2	

10. From the Parameters sidebar, select the source Forecast Status, Time Period, and Unit to use for the default forecast.
11. Choose Default Forecast to default production forecast records. Forecast records identify the Product associated with the production meter.

If a forecast record displays in RED, Allegro has encountered a problem and will identify the reason in the Validation column.



Forecast records should not span multiple production months.

12. If no records default in, choose Home >> Insert to add forecast records for new production.
13. Choose Data >> Update to save newly entered records to the database.
14. Use Home >> Insert to enter OBO Forecast records for GAFS received by outside operators.
15. Choose Data >> Update to save OBO Forecast records.
16. Choose Calculate Positions or allow grid computing to calculate the owner's share of the production for the current selection and perform the following updates:
 - All forecast quantities for properties linked to the same pipeline / point (gas) or location (crude) are combined together.
 - For gas properties, an energy factor can be used to convert the production forecast in volume units to energy or vice versa.
 - For gas properties, pressure base is determined to convert the pressure base associated with the property to the pressure base associated with the pipeline.

CHAPTER 3: PRODUCTION FORECAST

- For crude properties, the production forecast volume is converted to a mass based on the specific gravity and quality parameters.
 - The marketing portion of the production forecast is determined using the marketing arrangements.
 - On the first occurrence of running Calculate Position, a new Position is created with a Position Type = PRODUCTION.
 - FORECAST quantities are created in the ngquantity (gas) or physicalquantity (crude) tables.
17. Confirm the create position process displays Seller's Interest production position in Natural Gas Scheduling (Navigation sidebar >> Logistics >> Natural Gas >> Natural Gas Scheduling).

Create Production Forecast Based on Historical Volume

Forecasts can be defaulted based on prior month's quantities as long as those quantities are also entered as a forecast.

1. Open the Production Forecast view (Navigation sidebar >> Property >> Properties >> Production Forecasts).
2. Choose Pane >> Prod Forecasts.
3. Choose a time dimension to filter the analysis (e.g., Time Range) from Parameters sidebar >> Time Period>> Time Column.
4. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period>> Time Period.
5. Filter the query request further by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [*"Standard Selection Criteria"*](#) for more details.
6. Choose Data >> Select to retrieve forecast results.
7. Verify historical volume for each property meter is entered in a production forecast.

Workflow Production Forecast										
Prod forecasts										
Property	Meter	Beg time	End time	Forecast status	Quantity	Unit	Time unit	Product	Validation	Operator
Angus		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	231.000000	bbl	DAY	E TX Sweet		Hess
Pelican		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	122.000000	bbl	DAY	E TX Sweet		Shell
Franklin		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	250.000000	bbl	DAY	LLS		Total Fina Elf Expl
Abbeville 3-3	101902	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,764.000000	mcf	DAY	NG		Delta Petroleum
Abell 5-5	101903	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,793.000000	mcf	DAY	NG		Energy Corp
Abell 5-7	102982	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,821.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 4-3	101908	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,877.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 4-5	102984	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,806.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 6-9	103395	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,834.000000	mcf	DAY	NG		Energy Corp
Anderson 10-6	101909	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	5,132.000000	mcf	DAY	NG		Energy Corp

Use the Property Parameters View (Navigation sidebar >> Property >> Parameters >> Property Parameters) to confirm that a status level is associated with the desired forecast status.

Property Parameters Workflow				
Forecast statuses				
Forecast status	Description	Sc	Status level	Connection
Marketing	Marketing	☒	1	
Production	Production	☒	2	

From the Parameters sidebar, select the source Forecast Status, Time Period, and Unit to use for the default forecast.

- From Parameters sidebar >> Time Period>> Time Period, select the time period for which you are creating the forecast.
- Choose Default Forecast to default production forecast records.

The Default Forecast process looks for all properties set up in the Property Gathering pane (For more information, refer to the Properties User's Guide). For each property, it will attempt to locate a forecast from the source month. If one does not exist, a production forecast of zero will be created. If a forecast for the source month exists, the default process copies a prior month's volumetric forecasts to any target month. For example, forecasts used in January can be used as a starting forecast for March.

This process can also copy the same month's volumetric forecasts from one Forecast Status to a different Forecast Status. For example, a January production forecast can be used as a starting January marketing forecast.

Because Allegro requires selecting a single Product Type prior to the defaulting process, each Product Type must be defaulted individually.

Allegro allows update to any defaulted quantity. Adjustments may be

needed as consideration for changing field or pipeline operations that affect the upcoming production month quantity. In instances where a new property has come online and no historical forecasted volume can be found, the system will populate a record with zero quantity. Therefore, after the default forecast, sorting the forecasts by ascending quantity will show those properties requiring manual quantity population.

If no records default in, choose Home >> Insert to add forecast records for new production.

Choose Data >> Update to save newly entered records to the database.

Use Home >> Insert to enter OBO Forecast records for GAFS received by outside operators.

Choose Data >> Update to save OBO Forecast records.

Choose Calculate Positions or allow grid computing to calculate the owner's share of the production for the current selection and perform the following updates:

- All forecast quantities for properties linked to the same pipeline / point (gas) or location (crude) are combined together.
- For gas properties, an energy factor can be used to convert the production forecast in volume units to energy or vice versa.
- For gas properties, pressure base is determined to convert the pressure base associated with the property to the pressure base associated with the pipeline.
- For crude properties, the production forecast volume is converted to a mass based on the specific gravity and quality parameters.
- The marketing portion of the production forecast is determined using the marketing arrangements.
- On the first occurrence of running Calculate Position, a new Position is created with a Position Type = PRODUCTION.
- FORECAST quantities are created in the ngquantity (gas) or physicalquantity (crude) tables.

Confirm the create position process displays Seller's Interest production position in Natural Gas Scheduling (Navigation sidebar >> Logistics >> Natural Gas >> Natural Gas Scheduling).

Revise Default Production Forecast Based on Field Estimates

PART 2: PROCEDURES

1. Open the Production Forecast view (Navigation sidebar >> Property >> Properties >> Production Forecasts).
2. Choose Pane >> Prod Forecasts.
3. Choose a time dimension to filter the analysis (e.g., Time Range) from Parameters sidebar >> Time Period>> Time Column.
4. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period>> Time Period.
5. Filter the query request further by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [“Standard Selection Criteria”](#) for more details.
6. Choose Data >> Select to retrieve forecast results.
7. Verify estimated field production volume for each property meter is entered in a production forecast.

Workflow Production Forecast										
Prod forecasts										
Property	Meter	Beg time	End time	Forecast status	Quantity	Unit	Time unit	Product	Validation	Operator
Angus		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	231.000000	bbl	DAY	E TX Sweet		Hess
Pelican		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	122.000000	bbl	DAY	E TX Sweet		Shell
Franklin		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	250.000000	bbl	DAY	LLS		Total Fina Elf Expl
Abbeville 3-3	101902	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,764.000000	mcf	DAY	NG		Delta Petroleum
Abell 5-5	101903	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,793.000000	mcf	DAY	NG		Energy Corp
Abell 5-7	102982	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,821.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 4-3	101908	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,877.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 4-5	102984	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,906.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 5-9	103395	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,934.000000	mcf	DAY	NG		Energy Corp
Anderson 10-6	101909	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	5,132.000000	mcf	DAY	NG		Energy Corp

From the Parameters sidebar, select the Forecast Status to use for next months default production forecast.

Use the Property Parameters View (Navigation sidebar >> Property >> Parameters >> Property Parameters) to confirm that a status level is associated with the desired forecast status.

Property Parameters Workflow				
Forecast statuses				
Forecast status	Description	Sc	Status level	Connection
Marketing	Marketing	☒	1	
Production	Production	☒	2	

CHAPTER 3: PRODUCTION FORECAST

From the Parameters sidebar, select the Forecast Status, Time Period, and Unit to use for the default forecast.

Choose Default Forecast to default production forecast records.

If no records default in, choose Home >> Insert to add forecast records for new production.

Choose Data >> Update to save newly entered records to the database.

Enter adjustments to default volume based on field production maintenance.

Use Home >> Insert to enter OBO Forecast records for GAFS received by outside operators.

Choose Data >> Update to save OBO Forecast records.

Choose Calculate Positions or allow grid computing to calculate the owner's share of the production for the current selection and perform the following updates:

- All forecast quantities for properties linked to the same pipeline / point (gas) or location (crude) are combined together.
- For gas properties, an energy factor can be used to convert the production forecast in volume units to energy or vice versa.
- For gas properties, pressure base is determined to convert the pressure base associated with the property to the pressure base associated with the pipeline.
- For crude properties, the production forecast volume is converted to a mass based on the specific gravity and quality parameters.
- The marketing portion of the production forecast is determined using the marketing arrangements.
- On the first occurrence of running Calculate Position, a new Position is created with a Position Type = PRODUCTION.
- FORECAST quantities are created in the ngquantity (gas) or physicalquantity (crude) tables.

Confirm the create position process displays Seller's Interest production position in Natural Gas Scheduling (Navigation sidebar >> Logistics >> Natural Gas >> Natural Gas Scheduling).

Revise Default Production Forecast Based on Pipeline Maintenance

PART 2: PROCEDURES

1. Open the Production Forecast view (Navigation sidebar >> Property >> Properties >> Production Forecasts).
2. Choose Pane >> Prod Forecasts.
3. Choose a time dimension to filter the analysis (e.g., Time Range) from Parameters sidebar >> Time Period>> Time Column.
4. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period>> Time Period.
5. Filter the query request further by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [“Standard Selection Criteria”](#) for more details.
6. Choose Data >> Select to retrieve forecast results.
7. Verify historical volume for each property meter is entered in a production forecast.

Workflow Production Forecast										
Prod forecasts										
Property	Meter	Beg time	End time	Forecast status	Quantity	Unit	Time unit	Product	Validation	Operator
Angus		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	231.000000	bbl	DAY	E TX Sweet		Hess
Pelican		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	122.000000	bbl	DAY	E TX Sweet		Shell
Franklin		9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	250.000000	bbl	DAY	LLS		Total Fina Elf Expl
Abbeville 3-3	101902	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,764.000000	mcf	DAY	NG		Delta Petroleum
Abell 5-5	101903	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,793.000000	mcf	DAY	NG		Energy Corp
Abell 5-7	102982	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,821.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 4-3	101908	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,877.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 4-5	102984	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,906.000000	mcf	DAY	NG		Energy Corp
Agua Dulce Stratton 5-9	103395	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	4,934.000000	mcf	DAY	NG		Energy Corp
Anderson 10-6	101909	9/1/2007 12:00 AM	10/1/2007 12:00 AM	PRODUCTION	5,132.000000	mcf	DAY	NG		Energy Corp

From the Parameters sidebar, select the Forecast Status to use for next month's default production forecast.

Use the Property Parameters View (Navigation sidebar >> Property >> Parameters >> Property Parameters) to confirm that a status level is associated with the desired forecast status.

Property Parameters Workflow				
Forecast statuses				
Forecast status	Description	Sc	Status level	Connection
Marketing	Marketing	☒	1	
Production	Production	☒	2	

CHAPTER 3: PRODUCTION FORECAST

From the Parameters sidebar, select the Forecast Status, Time Period, and Unit to use for the default forecast.

Choose Default Forecast to default production forecast records.

If no records default in, choose Home >> Insert to add forecast records for new production.

Choose Data >> Update to save newly entered records to the database.

Enter adjustments to default volume based on pipeline maintenance.

Use Home >> Insert to enter OBO Forecast records for GAFS received by outside operators.

Choose Data >> Update to save OBO Forecast records.

Choose Calculate Positions or allow grid computing to calculate the owner's share of the production for the current selection and perform the following updates:

- All forecast quantities for properties linked to the same pipeline / point (gas) or location (crude) are combined together.
- For gas properties, an energy factor can be used to convert the production forecast in volume units to energy or vice versa.
- For gas properties, pressure base is determined to convert the pressure base associated with the property to the pressure base associated with the pipeline.
- For crude properties, the production forecast volume is converted to a mass based on the specific gravity and quality parameters.
- The marketing portion of the production forecast is determined using the marketing arrangements.
- On the first occurrence of running Calculate Position, a new Position is created with a Position Type = PRODUCTION.
- FORECAST quantities are created in the ngquantity (gas) or physicalquantity (crude) tables.

Confirm the create position process displays Seller's Interest production position in Natural Gas Scheduling (Navigation sidebar >> Logistics >> Natural Gas >> Natural Gas Scheduling).

Chapter 4: Natural Gas Balancing (Wellhead)

This part of the documentation provides procedures for balancing owner-level positions resulting from prior period over or under deliveries relative to entitled marketing quantities.

The following information is discussed:

- [Balance WIOs to Determine Right-to-Market Quantities](#)
- [Revise WIO Balancing Right-to-Market Quantities](#)

Balance WIOs to Determine Right-to-Market Quantities

After production is actualized for a time, imbalances will eventually arise because allocated actualized volumes rarely equal entitlement volumes.

Entitlement volumes are calculated as gross monthly production x each owner's ownership percentage.

In a perfect world, entitlement volumes should equal actual volumes, but because take-in-kind (TIK) owners do not always nominate the volume that they are entitled to, actual volumes will differ from their entitlement volumes.

When an imbalance exists at the Property, one or more owners will be in a short position (cumulative actual volume is less than cumulative entitled volume), and one or more owners will be in a long position (cumulative actual volume is greater than cumulative entitled volume). The total Property imbalance is always zero.

The Balance Interest function is used to calculate right to market adjustments so that the cumulative imbalance will return back to zero for each owner. If an owner is in a short position, then the calculated right to market adjustment will be positive. If the owner is in a long position, the calculated right to market adjustment will be negative. The final right to market (RTM) quantity is equal to the right to market percentage times the total monthly production. Right to market percentage is equal to the entitlement percentage plus the right to market adjustment.


For anyone owner who is in an imbalance long position (they owe the other

CHAPTER 4: NATURAL GAS BALANCING (WELLHEAD)

owners), they can only have their right to market percentage reduced up to a certain maximum percentage (MaxBalance Interest column). Typically in the USA this is equal to 25%.

To calculate the right to market percentages:

1. Open the Balancing view (Navigation sidebar >> Property >> Equity Production >> Balancing).
2. Select Display Volume or Display Energy in the Parameters sidebar to add those columns to the table.
3. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period >> Time Period.
4. Filter the query request by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [“Standard Selection Criteria”](#) for more details.
5. Choose Data >> Select to retrieve results. Allegro will respond by retrieving existing balancing records matching your selection criteria.
6. Use Grid Computing or click the Balance Interests icon to calculate the right to market positions.



The screenshot shows the 'Balancing' view in the Allegro software. The table displays balancing records for three properties: Abbeville 3-3, Abell 5-5, and Abell 5-7. Each property has multiple rows representing different operators and their associated balancing data.

Operator	Property	Owner	Seller	Work Int	Balance Int	Market Int	Max Balance Int	Override MaxBalance Int	Fore
Abbeville 3-3									
Delta Petroleum	Abbeville 3-3	Aspen Group Resour	Delta Petroleum	0.25000000	0.00000000	0.25000000	0.25000000		PRC
Delta Petroleum	Abbeville 3-3	Delta Petroleum	Delta Petroleum	0.30000000	0.00000000	0.30000000	0.25000000		PRC
Delta Petroleum	Abbeville 3-3	Matrix Oil	Delta Petroleum	0.45000000	0.00000000	0.45000000	0.25000000		PRC
				1.00000000	0.00000000	1.00000000			
Abell 5-5									
Energy Corp	Abell 5-5	Edge Petroleum	Energy Corp	0.41250000	0.00000000	0.41250000	0.25000000		PRC
Energy Corp	Abell 5-5	Energy Corp	Energy Corp	0.17500000	0.00000000	0.17500000	0.25000000		PRC
Energy Corp	Abell 5-5	Newfield Exploration	Energy Corp	0.05000000	0.00000000	0.05000000	0.25000000		PRC
Energy Corp	Abell 5-5	Range Energy	Energy Corp	0.36250000	0.00000000	0.36250000	0.25000000		PRC
				1.00000000	0.00000000	1.00000000			
Abell 5-7									
Energy Corp	Abell 5-7	Edge Petroleum	Energy Corp	0.41250000	0.00000000	0.41250000	0.25000000		PRC
Energy Corp	Abell 5-7	Energy Corp	Energy Corp	0.17500000	0.00000000	0.17500000	0.25000000		PRC
Energy Corp	Abell 5-7	Newfield Exploration	Energy Corp	0.05000000	0.00000000	0.05000000	0.25000000		PRC
Energy Corp	Abell 5-7	Range Energy	Energy Corp	0.36250000	0.00000000	0.36250000	0.25000000		PRC
				1.00000000	0.00000000	1.00000000			

When this process is invoked, the system sums historical entitlements, less the sum of historical actuals plus any adjustments, to calculate an imbalance value at the start of the month being balanced.

Based on the imbalance volume, the property's min/max balance interest percentages, and any owner overrides to the min/max balance interest percent, the system will calculate a make-up adjustment, + or -.

7. Check the Balance status definition checkbox. If Balance status definition checkbox is not checked, confirm that the property is automatically or manually balanced.
8. Enter adjustments to WIO balances-Adjustment column.
9. Choose the Balance Interests icon to rerun Balance Interests to incorporate adjustments.
10. Choose Data >> Select to view the updated Balances with adjustments incorporated.
11. Confirm Create Nomination process invoked automated streaming of PRODUCTION positions or click the Create Nomination icon to create nominations using PRODUCTION positions.

When this process is invoked, Allegro creates nominations (paths) based on details set up in NG Pipelines view of Logistics. Streaming provides automatic movement of gas from a specified receipt point to a specified delivery point using a specified pipeline service.

Auto streaming paths gas from the initial production position pipeline receipt point (CTP in Gathering tab) to a delivery point further downstream, typically the point of interconnect from the gathering system into a processing plant or a mainline pipeline system.

Auto-streaming precludes the need for manual pathing and calculates fuel, fees and other costs associated with the pipeline service.

12. Confirm PRODUCTION position streamed to NGStreamDetail Delivery Point.

Revise WIO Balancing Right-To-Market Quantities

If you need to revise interest owner balancing quantities, data from one or more properties may be highlighted, deleted and re-balanced within the

Balancing view.

If, after the production position for a property has been established for a month, the DOI or market group(s) change, you must Delete the balancing rows for that property in the Balancing view and rerun Calculate Position and Balance Interest processes. This is the only way you will see ownership changes reflected in the Balancing view

To revise WIO balancing:

1. Open the Balancing view (Navigation sidebar >> Property >> Equity Production >> Balancing).
2. Select Display Volume or Display Energy in the Parameters sidebar to add those columns to the table.
3. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period >> Time Period.
4. Filter the query request by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [*“Standard Selection Criteria”*](#) for more details.
5. Choose Data >> Select to retrieve results. Allegro will respond by retrieving existing balancing records matching your selection criteria.
6. Delete all WIO records for each property as needed.
7. Choose the Balance Interests icon to rerun Balance Interests to calculate new WIO Entitlement and Right-to-Market quantities.
8. Confirm the Balance Status checkbox for the revised balance record is checked.

Chapter 5: Gas Available For Sale

This part of the documentation allows you to create and revise gas available for sale (GAFS) notifications for take-in-kind interest owners.

The property Operator is responsible for notifying each “take-in-kind” (TIK) owner of their anticipated share of production for the upcoming month. The notification is commonly known as the GASF or Gas Available for Sale letter. Stipulating the TIK owner’s share of production enables that owner to make a reasonably accurate pipeline nomination.

Operator’s may be required to make interim GASF notifications if there are significant changes in production quantities throughout the month.

The following procedures are discussed:

- [*Create Gas Available for Sale Notifications for Take-In-Kind WIO*](#)
- [*Revise Gas Available for Sale Notification for Take-In-Kind WIO*](#)

Create Gas Available for Sale Notifications for Take-In-Kind WIO

You can create a gas available for sale notification document to email or fax to take-in-kind owners.

To create a gas available for sale notification:


1. Open the Shipper Notification View (Navigation sidebar >> Property >> Equity Production >> Shipper Notification).

Document types and formats are created in the Document Parameters View. Prior to creating this notification, verify that the correct document types and parameters exist.

2. Choose Pane >> Nominations.
3. Choose Pane >> ShipperNotification.
4. Choose Pane >> Production.


CHAPTER 5: GAS AVAILABLE FOR SALE

5. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period >> Time Period.
6. Filter the query request by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [“Standard Selection Criteria”](#) for more details.
7. Choose Data >> Select to retrieve nomination records.



TIK Owner	Begin time	End time	Quantity	Point Desc	Point	Product	Unit	Time un
Energy Corp	10/1/2007 12:00 AM	11/1/2007 12:00 AM	9318.00	Branch	Branch	NG	mmbtu	DAY
Energy Corp	10/1/2007 12:00 AM	11/1/2007 12:00 AM	143797.00	GREEN CANYON BLOCK 237 - BUYBACK	040002308 GREEN CANYON B	NG	dth	DAY

8. In the Nominations pane, select a record to add notification information
9. In the ShipperNotification pane, enter Notification details for the take-in-kind owner contact.



Shipper	Notification	Contact
Energy Corp	EMAIL	Andy Tsai

10. In the standard selection criteria for this View (Index sidebar), select Pipeline and/or Point and/or Shipper.
11. Choose Create Notification to create a notification-GASF document for take-in-kind working interest owners.
12. Confirm that the Notification Date is populated in the Nominations pane.
13. Choose Collaboration >> Documents to confirm that the document pane is populated with a gas available for sale document.
14. Use the Print options in the ribbon to view and print GAFS Document from Documents pane (if needed).
15. With a record selected, choose Send Notification to email or fax the notification document to the take-in-kind owner contact.

Revise Gas Available for Sale Notification for Take-In-Kind WIO

You can revise gas available for sale notifications.

To revise a gas available for sale notification:

1. Open the Shipper Notification View (Navigation sidebar >> Property >> Equity Production >> Shipper Notification).

Document types and formats are created in the Document Parameters View. Prior to creating this notification, verify that the correct document types and parameters exist.

2. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period >> Time Period.
3. Filter the query request by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [“Standard Selection Criteria”](#) for more details.
4. Choose Data >> Select to retrieve nomination records.
5. In the Nominations pane, select a record to add notification information.
6. In the ShipperNotification pane, edit Notification details for the take-in-kind owner contact.
7. In the standard selection criteria for this View (Index sidebar), select Pipeline and/or Point and/or Shipper.
8. Choose Create Notification to create a notification-GASF document for take-in-kind working interest owners.
9. Confirm that the Notification Date is populated in the Nominations pane.
10. Choose Collaboration >> Documents to confirm that the document pane is populated with a gas available for sale document.

CHAPTER 5: GAS AVAILABLE FOR SALE

11. Use the Print options in the ribbon to view and print GAFS Document from Documents pane (if needed).
12. With a record selected, choose Send Notification to email or fax the notification document to the take-in-kind owner contact.

Chapter 6: Production Measurement

This part of the documentation explains how to enter daily production measurement quantities.

During the production month, 8/8ths production quantities are recorded. Production measurement records reflect the daily estimated production quantity for each meter associated with a property.

The measurements are considered “estimates” because they are subject to change upon actualization by the point Operator. The operator actualization process is described in [Chapter 9, “NG Operator Actualization”](#).

Allegro’s term “production measurement” is not the same as wellhead measurement. Production measurement is the estimated sales volume at the CTP allocated back to a property (or meter) level. Volumetric losses associated with field or production flow lines are not captured within Allegro’s Equity Production component.

Allegro requires a production measurement record each day during the production month. If a measurement quantity is not available for any given day, Allegro requires entry of a zero quantity.

When production measurement records are processed, Allegro updates the Estimate Date with the effective date of the measurement record.

The following procedure is discussed:

- [Enter Daily Production Measurement Quantities by Property](#)

Enter Daily Production Measurement Quantities by Property

A measurement record is used to describe a set of metered measurement quantities associated with a meter for a given time period.

To establish a production measurement record:

1. Open the Production Measurement view (Navigation sidebar >> Property

CHAPTER 6: PRODUCTION MEASUREMENT

>> Equity Production >> Production Measurement).

2. Select a unit of measure to use when defaulting in the actual measurement from Parameters sidebar >> Unit.
3. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period >> Time Period.
4. Filter the query request by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [“Standard Selection Criteria”](#) for more details.
5. Choose Data >> Select to retrieve existing records.

Workflow Gathering System Measurement Production Measurement										
Meter measurement										
Meter	Beg time	End time	Me	Quantity	Unit	Time unit	Source	Product	Measure date	Measure
101902	1/1/2007 12:00	12/31/2007 12:0	☒	440.000000	original	DAY		AL Sour	9/5/2007 12:00	100001
102496	1/1/2007 12:00	12/31/2007 12:0	☒	320.000000	original	DAY		Arab Extra Light	9/5/2007 12:00	100002
102214	1/1/2007 12:00	12/31/2007 12:0	☒	175.000000	original	DAY		KS Sweet	9/5/2007 12:00	100003
103033	1/1/2007 12:00	12/31/2007 12:0	☒	860.000000	original	DAY		Mixed Sour	9/5/2007 12:00	100004
103543	1/1/2007 12:00	12/31/2007 12:0	☒	3,400.000000	original	DAY		Basrah Heavy	9/5/2007 12:0	100005

6. Select Home >> Insert to add a new record.
7. Enter NG Meter Measurement production estimate quantity for each property in the *Meter measurement* pane (see [Meter measurement](#) for detailed column descriptions).

Required information includes *Meter identifier*, *Beg/End Time*, *Unit*, *Product*, *Measure Date*, and *Measure*.

The system will default the following columns, but they can be overridden: *Quantity*, *Time unit*, *Meter Factor*, *Comp Factor* and *Flow Temp*.

8. Check the checkbox in the *Measure status* to activate the record.
9. Choose Data >> Update to update record(s) to database.
10. Confirm Calculate Position displays WIO entitlement in the Balancing View and confirm that the Seller's Interest position displays in NG Scheduling.
11. Confirm that Create Nomination streams PRODUCTION position to NG Stream Detail Delivery Point.

Chapter 7: Production Positions

This part of the documentation allows you to review a summary of production positions and associated balancing details.

The Production Position view provides a summary of the quantities calculated after running the Balance Interest and Calculate Position processes. The view displays the same level of detail as the Balancing view, but also includes details for the production position representing Seller's Interest. Quantities in the view are updated as each daily process is completed.

If necessary, the Production Position view allows a production position to be deleted.

The Positions pane, Quantity Status column reflects the best available status of the production position in ngquantity (not propquantity):

- After Calculate Position process, the production position = FORECAST
- After Create Nomination process, the production position = NOM

Daily quantity changes displayed in the Positions pane of Production Positions view should match quantities displayed in the Scheduling view of Logistics because both views display quantities from the ngquantity table.

The following procedures are discussed:

- [Review Summary of PRODUCTION Positions and WIO Balancing](#)

Review Summary of PRODUCTION Positions and WIO Balancing

Use the following information to view a summary of production positions.

To view a summary of production positions:

Open the Production Positions view (Navigation sidebar >> Property >> Equity Production >> Production Positions).

1. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period >> Time Period.

CHAPTER 7: PRODUCTION POSITIONS

2. Filter the query request by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [*"Standard Selection Criteria"*](#) for more details.
3. Choose Pane >> Positions.
4. Choose Pane >> Balancing.
5. Choose Data >> Select to retrieve production positions.

Workflow Production Measurement Production Positions											
Balancing											
Operator	Property	Owner	Seller	Work Int	Balance Int	Market Int	Beg Imbalance Volume	Adjustment Volume			
Delta Petroleum	Abbeville 3-3	Matrix Oil	Delta Petroleum	0.45000000	0.00000000	0.45000000	0.00	0.00			
Abell 5-5											
Energy Corp	Abell 5-5	Edge Petroleum	Energy Corp	0.41250000	0.00000000	0.41250000	0.00	0.00			
Energy Corp	Abell 5-5	Energy Corp	Energy Corp	0.17500000	0.00000000	0.17500000	0.00	0.00			
Energy Corp	Abell 5-5	Newfield Exploration	Energy Corp	0.05000000	0.00000000	0.05000000	0.00	0.00			
Energy Corp	Abell 5-5	Range Energy	Energy Corp	0.36250000	0.00000000	0.36250000	0.00	0.00			
Abell 5-5											
Positions											
Position	Posdetail	Quantitytype	Begtime	Endtime	Path	Quantity	Status	Energy	Energy Unit	Mass	Volume
142632	101682	RECEIPT	1/1/2008 12:00 AM	2/1/2008 12:00 AM	FORECAST	9,550		mmbtu		9,493	mcf
											DAY
											Shaila Pat

Chapter 8: Nominations

This part of the documentation provides procedures for estimating and configuring nominations for submission to the pipeline.

The Nominations view is used to generate pipeline nomination adjustments for natural gas. This functionality is not applicable to crude oil. Prior to the month of production, the Nomination process is invoked from the Balancing view which sets each Seller's nomination quantity equal to the calculated right-to-market quantity.

The following procedures are discussed:

- [*Create and Adjust Nominations Due to Production Variances*](#)
- [*Review and Adjust Nominations Due to Production Variances*](#)

Create and Adjust Nominations Due to Production Variances

To create a nomination due to production variances:

1. Open the Nominations view (Navigation sidebar >> Property >> Equity Production >>Nominations).
2. Select Display Volume or Display Energy in the Parameters sidebar to add those columns to the table.
3. Choose a time dimension to filter the analysis (e.g., Time Range) from Parameters sidebar >> Time Period >> Time Column.
4. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period >> Time Period.
5. Select a Pipeline, Point, and Seller from the Standard Selection Criteria. You must select a pipeline to create a nomination.
6. Click the Create Nomination icon. The nomination will appear in the Prod nominations pane.

Workflow Nominations (ANR)											
Prodquantity											
Seller	Property	Market interest	Market rate	Market Energy	Product	Quantity status	Ba	Estimate date	Owner		
El Tanzanite 6-6											
Energy Search	El Tanzanite 6-6	0.16250000		0.00	NG	FORECAST	☐		Energy Search		
Energy Search	El Tanzanite 6-6	0.16250000		116,328.70	NG	FORECAST	☐		Energy Search		
Energy Search	El Tanzanite 6-6	0.16250000		119,298.90	NG	FORECAST	☐		Energy Search		
Energy Search	El Tanzanite 6-6	0.16250000		108,855.69	NG	FORECAST	☒		Energy Search		
Prod nominations											
Shipper	Beg time	End time	Quantity	Estimate	Nom estimate	Variance	Nom variance	Ad	Adj date	Adj quantity	Co
Energy Corp	12/1/2007 12:00	1/1/2008 12:00	87,235.00	2,704,285	2,704,285	0	0	☐			0
Energy Search	12/1/2007 12:00	1/1/2008 12:00	71,384.00	2,212,904	2,212,904	0	0	☐			0
Energyquest Resour	12/1/2007 12:00	1/1/2008 12:00	59,169.00	1,834,239	1,834,239	0	0	☐			0
Gulfport Energy	12/1/2007 12:00	1/1/2008 12:00	47,322.00	1,466,982	1,466,982	0	0	☐			0

The Prodquantity pane of the Nominations view displays the same level of detail as the Balancing view, but includes additional columns for market rate calculations. Market rate calculations represent the daily average rate of production projected to the end of the month.

The Prod Nominations pane of the Nominations view displays the calculations needed to determine if a Nomination Adjustment is recommended.

- When you click Create Nomination, records are automatically confirmed in the Nominations view. If the nomination is adjusted, then the record will need to be reconfirmed.
- Review the Market Rate, Quantity, and Estimate Date in ProdQuantity pane.
- Review the Variance and Nom Variance in the Nominations pane.
- Leave defaults or enter revised Nom Adjustment and Adjustment Date in the Prod nominations pane.
- Confirm Create Nomination invokes a Nomination Adjustment for the pipeline, point, and shipper.
- Confirm that the Nomination Adjustment displays in Scheduling effective on Nomination Adjustment Date.

Review and Adjust Nominations Due to Production Variances

During the production month as daily production measurement records are entered and the Create Nomination process is run, a production variance will likely result. The variance is the difference between the original nominated

quantity (based on the production forecast) and the daily production measurement quantity (based on estimated production) projected to the end of the month.

When the Nominations view displays a significant Nomination Variance, a nomination adjustment should be made. Allegro calculates the optimal daily adjustment needed to align pipeline nominations with estimated production. The adjustment may be upward or downward depending on projections. The Create Nomination icon is used to process daily nomination adjustments.

The reason for making a nomination adjustment is to avoid pipeline penalties that may be assessed when nomination quantities do not match production quantities. This is known as a pipeline imbalance. Pipelines typically provide a reasonable level of tolerance before assessing imbalance penalties.

To revise a nomination due to production variances:

1. Open the Nominations view (Navigation sidebar >> Property >> Equity Production >>Nominations).
2. Select Display Volume or Display Energy in the Parameters sidebar to add those columns to the table.
3. Choose a time dimension to filter the analysis (e.g., Time Range) from Parameters sidebar >> Time Period >> Time Column.
4. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period >> Time Period.
5. Select a Pipeline, Point, and Shipper from the Standard Selection Criteria. You must select a pipeline, point and shipper to revise a nomination.
6. Choose Data >> Select to retrieve current pipeline nominations.

Workflow Nominations (ANR)										
Prodquantity										
Seller	Property	Market interest	Market rate	Market Energy	Product	Quantity status	Ba	Estimate date	Owner	
El Tanzanite 6-6										
Energy Search	El Tanzanite 6-6	0.16250000		0.00	NG	FORECAST	☐		Energy Search	
Energy Search	El Tanzanite 6-6	0.16250000		116,328.70	NG	FORECAST	☐		Energy Search	
Energy Search	El Tanzanite 6-6	0.16250000		119,298.90	NG	FORECAST	☐		Energy Search	
Energy Search	El Tanzanite 6-6	0.16250000		108,655.69	NG	FORECAST	☒		Energy Search	
Prod nominations										
Shipper	Beg time	End time	Quantity	Estimate	Nom estimate	Variance	Nom variance	Adj	Adj date	Adj quantity
Energy Corp	12/1/2007 12:00	1/1/2008 12:00	87,235.00	2,704,285	2,704,285	0	0	☐		0
Energy Search	12/1/2007 12:00	1/1/2008 12:00	71,384.00	2,212,904	2,212,904	0	0	☐		0
Energyquest Resour	12/1/2007 12:00	1/1/2008 12:00	59,169.00	1,834,239	1,834,239	0	0	☐		0
Outport Energy	12/1/2007 12:00	1/1/2008 12:00	47,322.00	1,466,982	1,466,982	0	0	☐		0

7. Nomination adjustments are allowed only on the last row displayed for each Seller in the Prod Nomination pane.
8. To manually adjust status, enter a new Adjustment quantity and Adjustment date in the Prod Nominations pane.
9. To have Allegro automatically adjust status, check the Adjust status column. Allegro automatically defaults an Adjustment quantity and an Adjustment date.

The Adj date column defaults to 2 days after the Estimate Date and reflects the effective date of the new nomination. The Estimate Date column displays the latest meter measurement date processed for the property. The Adjustment Date can be updated to reflect a different nomination effective date.

The Adj quantity column will default Allegro's optimal calculated quantity necessary to align nominations with projected production. This quantity can be changed as needed.

10. Confirm Create Nomination invokes a Nomination Adjustment for the pipeline, point, and shipper.

A new production nomination row is created. The previous row will be end-dated and the Beg Time of the new row will be equal to the specified Adjustment Date.

11. Choose Data >> Select to refresh the view. After the Nominations view is refreshed, the Adjust Status, Adjustment Date and Adjustment Quantity columns display null values.
12. Confirm that the Nomination Adjustment displays in Scheduling effective on Nomination Adjustment Date.

Chapter 9: NG Operator Actualization

This part of the documentation explains how to default and allocate operator best available quantities.

The NG Operator Actuals view allows reconciliation and “true up” of natural gas quantities that were transported through a pipeline point. Each point Operator is responsible for tracking the quantity and sending a monthly statement to each Shipper who owns or controls gas flowing through the point.

The “true up” process is known as Actualization. Actualized quantity is considered the best available quantity used in Allegro allocations back to the property and interest owner.

Actualization allows the best available quantity to be used with Net Back prices for revenue and royalty disbursements.

The following procedure is discussed:

- [Calculate Shipper Allocation Based on Point Operator Statement](#)

Calculate Shipper Allocation Based on Point Operator Statement

Best available operator measurements are defaulted to a statement when the Default Operator icon is invoked in the Operator Actuals view. These measurements are defaulted based on the best available quantity of all underlying measurements associated with the natural gas operator for the given time period.

To calculate shipper allocation based on point operator statement:

1. Open the Operator Actuals View (Navigation sidebar >> Property >> Equity Production >> Operator Actuals).
2. Choose Pane >> Operator Actuals.
3. Choose Pane >> Operator Measure.

CHAPTER 9: NG OPERATOR ACTUALIZATION

4. Select a unit of measure to use when defaulting in the actual measurement from Parameters sidebar >> Unit.
5. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period >> Time Period.
6. Filter the query request by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [“Standard Selection Criteria”](#) for more details.
7. Choose Data >> Select to retrieve existing records.
8. Select Home >> Insert to add a new record.
9. Enter a statement record in the *Operator actuals* pane (see [Operator actuals pane](#) for detailed column descriptions).

Required information includes *Statement identifier* and *Pipeline*.

10. Choose Data >> Update to update record(s) to database.
11. Highlight an operator actual statement record in the *Operator Actuals* pane for which you want to generate default measurement records. Allegro will respond by retrieving all existing measurement records (in the *Operator Measure* tab) that correspond to that statement.
12. Click the *Default Operator Actuals* icon. The system will default best available measurement records.
13. Update the counterparty (Shipper) quantity to match the operator statement.
14. Choose Data >> Update to save the records to the database.

Workflow Operator Actuals										
Operator actuals										
Statement	Statement date	Pipeline	Beg time	End time	Frequency	Energy unit	Volume unit	Pressure	Alloc status	
ANR01012007	12/19/2007	ANR	1/1/2007 12:00 AM	1/1/2008 12:00 AM	MONTH	dth	mcf	14.730000	ALLOC	
Cocodrie01012007	12/19/2007	Cocodrie	1/1/2007 12:00 AM	1/1/2008 12:00 AM	MONTH	mmbtu	mcf	14.730000	UNALLOC	
COLUMBIA GAS01012007	12/19/2007	COLUMBIA GAS	1/1/2007 12:00 AM	1/1/2008 12:00 AM	MONTH	dth	mcf	14.730000	UNALLOC	
SOUTHWEST GAS C001012007	12/19/2007	SOUTHWEST GAS CO	1/1/2007 12:00 AM	1/1/2008 12:00 AM	MONTH	dth	mcf	14.730000	UNALLOC	
Operator measure										
Measure /	Pipeline	Point	Counterparty	Beg time	End time	Quantity	Alloc status	Unit	Time unit	Energy
100001	ANR	000502231 COLD SPRING 1	Energy Corp	12/1/2007 12:00 AM	12/15/2007 12:00 AM	5,000.000000	☒	dth	DAY	1.00
100002	ANR	000502231 COLD SPRING 1	Energy Corp	12/1/2007 12:00 AM	12/15/2007 12:00 AM	5,000.000000	☐	dth	DAY	1.00
100003	ANR	000502231 COLD SPRING 1	Energy Corp	12/1/2007 12:00 AM	12/15/2007 12:00 AM	5,000.000000	☐	dth	DAY	1.00

15. Highlight a measurement statement record in the *Operator actuals* pane for which you want to allocate measurement quantities to working interest owners.
16. To allocate all measurement records for the statement click the *Allocate Operator Actual* icon while selecting a statement record in the *Operator actuals* pane. The system will then attempt to allocate the quantities captured on the measurement records to all underlying working interest owners matching the record attributes. When a successful allocation occurs for a given measurement record, the *Alloc Status* check box is checked.
17. Review *Actual volume* and *Actual energy* columns in the Balancing view to see results from the actualization process.

Chapter 10: Production Variance

This part of the documentation explains how to use the Production Variance view to review forecasted versus estimated quantity variance by operator.


The following procedure is discussed:

- [Analyze Variance between Production Forecast and Daily Production Estimate](#)

Analyze Variance between Production Forecast and Daily Production Estimate

To view production variance:

1. Open the Production Variance View (Navigation sidebar >> Property >> Equity Production >> Production Variance).
2. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period >> Time Period.
3. Filter the query request by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See ["Standard Selection Criteria"](#) for more details.
4. Choose Data >> Select to retrieve existing records.



Operator	Product	Property	Meter	Forecast	Estimate	Forecast/Estimate Variance	Unit	Measure date	Beg time	End time
Century Petroleum	NG	Andrews South 2-4	101912	213,809	0	213,809	original	11/1/2007	12:00 AM	12/1/2007 12:00 AM
Century Petroleum	NG	Andrews South 2-4	101912	219,246	0	219,246	original	12/1/2007	12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Andrews South 4-10	103397	224,436	0	224,436	original	11/1/2007	12:00 AM	12/1/2007 12:00 AM
Century Petroleum	NG	Andrews South 4-10	103397	230,153	0	230,153	original	12/1/2007	12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Bagley North 6-3	101928	313,958	0	313,958	original	11/1/2007	12:00 AM	12/1/2007 12:00 AM
Century Petroleum	NG	Bagley North 6-3	101928	321,957	0	321,957	original	12/1/2007	12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Bagley North 6-4	102631	326,746	0	326,746	original	11/1/2007	12:00 AM	12/1/2007 12:00 AM
Century Petroleum	NG	Bagley North 6-4	102631	335,082	0	335,082	original	12/1/2007	12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Bayou Penchant 7-4	101945	227,102	0	227,102	original	11/1/2007	12:00 AM	12/1/2007 12:00 AM
Century Petroleum	NG	Bayou Penchant 7-4	101945	232,898	0	232,898	original	12/1/2007	12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Bayou Penchant 7-5	102642	237,288	0	237,288	original	11/1/2007	12:00 AM	12/1/2007 12:00 AM
Century Petroleum	NG	Bayou Penchant 7-5	102642	243,354	0	243,354	original	12/1/2007	12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Blue Buck Point 2-2	101962	241,475	0	241,475	original	11/1/2007	12:00 AM	12/1/2007 12:00 AM
Century Petroleum	NG	Blue Buck Point 2-2	101962	247,634	0	247,634	original	12/1/2007	12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Blue Buck Point 2-3	102651	253,771	0	253,771	original	11/1/2007	12:00 AM	12/1/2007 12:00 AM
Century Petroleum	NG	Blue Buck Point 2-3	102651	260,252	0	260,252	original	12/1/2007	12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Blue Buck Point 3-6	103233	266,125	0	266,125	original	11/1/2007	12:00 AM	12/1/2007 12:00 AM

The variance appears in the Forecast/Estimate Variance column.

5. Perform Operator Actuals Allocation (Refer to Calculate Shipper

Allocation Based on Point Operator Statement for instructions on performing allocation).

6. After performing allocation, return to the Production Variance View and analyze the variances before and after allocation.

Chapter 11: Pipeline Variance

This part of the documentation explains how to use the Pipeline Variance view to review estimated versus actual quantity variance by pipeline and point.


The following procedure is discussed:

- [Analyze Variance between Daily Production Estimates and Production Actuals](#)

Analyze Variance between Daily Production Estimates and Production Actuals

To analyze the pipeline variance:

1. Open the Pipeline Variance View (Navigation sidebar >> Property >> Equity Production >> Pipeline Variance View).
2. Choose a time period to filter the request (e.g., Next Month) from Parameters sidebar >> Time Period >> Time Period.
3. Filter the query request by drilling down and choosing from the standard selection criteria for this View (Index sidebar). See [“Standard Selection Criteria”](#) for more details.
4. Choose Data >> Select to retrieve existing records.



Group description	Product	Property	Meter	Estimate	Actual	Estimate/Actual Variance	Pipeline	Point	Unit	Beg time	End time
Bayou Chauvin				0	2,500	2,500		Bayou Chauvin	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Chauvin 3-2	101938	0	833	833		Bayou Chauvin	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Chauvin 3-3	102637	0	833	833		Bayou Chauvin	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Chauvin 4-6	103224	0	833	833		Bayou Chauvin	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
Bayou Copasaw				0	1,000	1,000		Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 11-3	101940	0	250	250		Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 11-4	102639	0	250	250		Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 11-5	102995	0	250	250		Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 12-7	103225	0	250	250		Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
Bayou Jean Lacroix				0	1,500	1,500		Bayou Jean Lacroix	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Jean Lacroix 13-4	101942	0	750	750		Bayou Jean Lacroix	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Jean Lacroix 13-6	102996	0	750	750		Bayou Jean Lacroix	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM

The variance appears in the ForecastActual Variance column.

5. Perform Operator Actuals Allocation (Refer to Calculate Shipper Allocation Based on Point Operator Statement for instructions on performing allocation).

6. After performing allocation, return to the Pipeline Variance View and analyze the variances before and after allocation.

PART 3: EQUITYPROD CLASS

Part 3: EquityProd Class

Allegro Views are organized into application classes. This part of the documentation provides information about the structure of each View associated with the *EquityProd* class of the *Equity Production* component, including View access procedure, a description of standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.

The following Views belong to this class:

- [Chapter 12, "Equity Production Parameters,"](#) is used to define various drop-down parameters used for characterizing the Equity Production component.

Parameters

The following parameters are associated with this class:

- None

Icons

The following icons are associated with this class:

- None

Chapter 12: Equity Production Parameters View


The Equity Production Parameters View is used to enter parameter set up information.

This part of the documentation provides information about the structure of the *Equity Production Parameters View*. The information is divided into the following sections:

- [*View access procedure*](#)
- [*Standard panes and columns*](#)
- [*Standard selection criteria*](#)
- [*View-specific time periods*](#)

View access procedure

To access the Equity Production Parameters View choose Navigation sidebar >> Property>>Parameters>>Equity Production Parameters.



The screenshot shows a software interface with a 'Workflow' tab and an 'Equity Production Parameters' pane. The 'Meters' section is active, displaying a table with the following columns: Meter, Description, Pipeline, Point, Meter type, Downstream meter, Line size, Plate diameter, Orifice factor, Meter constant, Spec grav, and Diff range. The table contains six rows of data for various meters.

Meter	Description	Pipeline	Point	Meter type	Downstream meter	Line size	Plate diameter	Orifice factor	Meter constant	Spec grav	Diff range
101902	Abbeville 3-3	Henry	Abbeville	Production							
101903	Abell 5-5	Santa Rosa	Abell	Production							
101908	Agua Dulce Stratton 4-3	Gulf Plains	Agua Dulce Stratton	Production							
101909	Anderson 10-6	Artesia	Anderson	Production							
101910	Andrews 13-2	Dollarhide	Andrews	Production							
101911	Andrews North 1-3	Fullerton	Andrews North	Production							

Standard panes and columns

The following standard panes and columns are associated with this View. The View label name is indicated in bold; the underlying data element name is enclosed in parenthesis.

There are three panes associated with this View:

- [*Meters pane*](#)
- [*Tanks pane*](#)
- [*Tank straps pane*](#)

Meters pane

The following columns appear in this pane:

Workflow Equity Production Parameters											
Meters											
Meter	Description	Pipeline	Point	Meter type	Downstream meter	Line size	Plate diameter	Orifice factor	Meter constant	Spec grav	Diff range
101902	Abbeville 3-3	Henry	Abbeville	Production							
101903	Abell 5-5	Santa Rosa	Abell	Production							
101908	Agua Dulce Stratton 4-3	Gulf Plains	Agua Dulce Stratton	Production							
101909	Anderson 10-6	Artesia	Anderson	Production							
101910	Andrews 13-2	Dollarhide	Andrews	Production							
101911	Andrews North 1-3	Fullerton	Andrews North	Production							

Meter (meter.meter) Indicates the user-defined identifier associated with the device used to measure and record the quantity associated with this ticket.

Description (meter.description) Optional description of the meter.

Pipeline (meter.pipeline) Indicates the short pipeline identifier associated with the indicated point. A pipeline can represent a gathering system, interstate/intrastate pipeline or distribution facility.

Point (meter.point) Indicates the short identifier associated with a physical (or conceptual) geographic location on the pipeline.

Meter type (meter.meter.type) Indicates how the meter is used. Choices are: PRODUCTION, USAGE, INJECTION, CHECK, or PIPELINE.

Downstream meter (meter.downstreammeter)) Indicates the next meter downstream of this meter. This field is used in conjunction with the Production component.

Line size (meter.linesize) Line size of meter flange.

Plate diameter (meter.platediameter) Diameter of orifice plate.

Orifice factor (meter.orificefactor) Not used.

Meter constant (meter.meterconstant) Not used.

Spec grav (meter.specgrav) Not used.

Diff range (meter.diffrange) Not used.

Pressure range (meter.pressurerange) Not used.

Pressure status (meter.pressurestatus) Not used.

Pressure base (meter.pressurebase) Not used.

Temp base (meter.tempbased) Not used.

Meter error (meter.metererror) Not used.

Min pressure (meter.minpressure) Not used.

Max pressure (meter.maxpressure) Not used.

Min deliv pressure (meter.mindelivpressure) Not used.

Max deliv pressure (meter.maxdelivpressure) Not used.

Calibration test (meter.calibrationtest) Not used.

Sampling test (meter.samplingtest) Not used.

Temp scale (meter.tempscale) Not used.

Estimate status (meter.estimatestatus) If checked, indicates that this meter is subject to estimates.

Property (meter.property) Indicates the property associated with this meter, if this meter is a production meter.

Test length (meter.testlength) Not used.

Status (meter.status) Indicates whether the meter is ACTIVE or INACTIVE.

MDN (meter.MDN) Used in the Allegro Retail Component to indicate the Maximum Daily Nomination associated with this customer meter.

Tanks pane

The following columns appear in this pane:

Workflow Equity Production Parameters												
Tank s												
Tank	Description	Location	Region	District	Capacity	Field	Product type	Height	Base volume	Tank incr	Height unit	Volume unit
1001	Bangchak Refinery		SE Asia		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1002	Botlek ExxonMobil		NW Europe		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1003	Europoort Nereco (BP/Chevron)		NW Europe		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1004	Pasadena ConocoPhillips		US Gulf		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1005	Pasadena ExxonMobil		US Gulf		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1006	Pennis Shell		NW Europe		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl
1007	Q8 Refinery Kuwait		NW Europe		20,000.00000000			170.00000000	0.00000000	0.12500000	INCH	bbl

Tank (tank.tank) User-defined identifier associated with this tank.

Description (tank.description) An optional further description of the tank.

Location (tank.location) Geographic location where the tank is located.

Region (tank.region) Indicates the region associated with this tank.

District (tank.district) Indicates district where this tank is located.

Capacity (tank.capacity) Indicates the capacity of this tank in the unit of measure defined in the *Volume Unit* column.

Field (tank.field) Used to indicate the producing field associated with this tank. Used by Exploration and Production users.

Product type (tank.producttype) Indicates that this tank can store products associated with this product type.

Height (tank.height) Height of the tank in the unit of measure defined in the *Height Unit* column.

Base volume (tank.basevolume) Volume of conical tank base below zero height expressed in the unit of measure defined in the *Volume Unit* column.

Tank incr (tank.tankincr) Tank strapping increment (e.g., in the US generally a quarter or eighth of an inch) expressed in the unit of measure defined in the *Height Unit* column.

Height unit (tank.heightunit) Unit of measure used to express height. Choices are: INCH, FOOT, YARD, MM, CM, or METER.

Volume unit (tank.volumeunit) Unit of measure used to express volumetric quantity.

Measurement date (tank.measurementdate) Date of last calibration of the strapping.

Encrustation factor (tank.encrustationfactor) Tank encrustation

factor. Generally used to reduce yield of tank (i.e., 0.95 indicates 95% available capacity and 5% unusable).

Floating roof factor (tank.floatingrooffactor) Floating roof factor. Generally used to reduce yield of tank (i.e., 0.95 indicates 95% available capacity and 5% unusable).

Property (tank.property) Identification of producing property attached to this tank. Used in the Allegro *Production* component.

Tank straps pane

The following columns are associated with this pane:

Workflow		Equity Production Parameters	
Tank straps			
	Tank	Height	Quantity
▶	1001	36.00000000	14.83688890
	1001	72.00000000	14.83688497
	1001	108.00000000	14.83688366
	1001	144.00000000	14.83688245
	1001	170.00000000	14.57488235
	1002	36.00000000	14.83688890
	1002	72.00000000	14.83688497
	1002	108.00000000	14.83688366

Tank (tankstrap.tank) User-defined identifier associated with this tank.

Height (tankstrap.height) Height of this strapping level in the unit of measure defined by the *Height Unit* column associated with the tank record.

Quantity (tankstrap.quantity) Quantity of product represented between the height recorded on this record and the next lower height record. This quantity represents the quantity of product per increment (as defined by the Tank Incr and Height Unit columns associated with the tank record) between these two height records

Standard selection criteria

The following standard selection criteria are associated with this View:

- Connection
- District
- Field
- Location

- Operator
- Product Type
- Region
- Volume Unit

View-specific time periods

The following standard time criteria are associated with this View:

- None.

PART 4: EQUITY PRODFORECAST CLASS

Part 4: EquityProdForecast Class

Allegro Views are organized into application classes. This part of the documentation provides information about the structure of each View associated with the *EquityProdForecast* class of the *Equity Production* component, including View access procedure, a description of standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.

The following Views belong to this class:

- [Chapter 13, "Production Positions View,"](#) allows you to view production position details by property, owner and seller.

Parameters

The following parameters are associated with this class:

- None

Icons

The following icons are associated with this class:

- None.

Chapter 13: Production Positions View


The Production Positions View is used to display production position details by property, owner and seller.

This part of the documentation provides information about the structure of the *Production Positions* View. The information is divided into the following sections:

- [View access procedure](#)
- [Standard panes and columns](#)
- [Standard selection criteria](#)
- [View-specific time periods](#)

View access procedure

To access the Production Positions View choose Navigation sidebar >> Property>>Equity Production>>Production Positions.



The screenshot shows the 'Production Positions' view in a software application. The interface includes a 'Workflow' tab and a 'Production Positions' tab. Below the tabs is a 'Balancing' section with a table. The table has columns for Operator, Property, Owner, Seller, Work Int, Balance Int, Market Int, Beg Imbalance Volume, Adjustment Volume, and Entitled. The data is grouped by property names: Abell 5-6, Abell 5-7, and Agua Dulce Stratton 4-3. Each group contains multiple rows of data for different operators and owners.

Operator	Property	Owner	Seller	Work Int	Balance Int	Market Int	Beg Imbalance Volume	Adjustment Volume	Entitled
Abell 5-6									
Energy Corp	Abell 5-5	Edge Petroleum	Energy Corp	0.41250000	0.00000000	0.41250000	0.00	0.00	
Energy Corp	Abell 5-5	Energy Corp	Energy Corp	0.17500000	0.00000000	0.17500000	0.00	0.00	
Energy Corp	Abell 5-5	Newfield Exploration	Energy Corp	0.05000000	0.00000000	0.05000000	0.00	0.00	
Energy Corp	Abell 5-5	Range Energy	Energy Corp	0.36250000	0.00000000	0.36250000	0.00	0.00	
Abell 5-7									
Energy Corp	Abell 5-7	Edge Petroleum	Energy Corp	0.41250000	0.00000000	0.41250000	0.00	0.00	
Energy Corp	Abell 5-7	Energy Corp	Energy Corp	0.17500000	0.00000000	0.17500000	0.00	0.00	
Energy Corp	Abell 5-7	Newfield Exploration	Energy Corp	0.05000000	0.00000000	0.05000000	0.00	0.00	
Energy Corp	Abell 5-7	Range Energy	Energy Corp	0.36250000	0.00000000	0.36250000	0.00	0.00	
Agua Dulce Stratton 4-3									
Energy Corp	Agua Dulce Stratton 4-3	Energy Corp	Energy Corp	0.31250000	0.00000000	0.31250000	0.00	0.00	
Energy Corp	Agua Dulce Stratton 4-3	Gasco Energy	Energy Corp	0.20000000	0.00000000	0.20000000	0.00	0.00	
Energy Corp	Agua Dulce Stratton 4-3	Gulfport Energy	Energy Corp	0.17500000	0.00000000	0.17500000	0.00	0.00	
Energy Corp	Agua Dulce Stratton 4-3	Penn Virginia Oil & Gas	Energy Corp	0.22500000	0.00000000	0.22500000	0.00	0.00	
Energy Corp	Agua Dulce Stratton 4-3	Terax Energy	Energy Corp	0.08750000	0.00000000	0.08750000	0.00	0.00	

Standard panes and columns

The following standard panes and columns are associated with this View. The View label name is indicated in bold; the underlying data element name is enclosed in parenthesis.

There are two panes associated with this View:

- [Balancing pane](#)
- [Positions pane](#)

Balancing Pane

The following columns are associated with this pane:

Workflow		Production Positions								
Balancing										
Operator	Property	Owner	Seller	Work Int	Balance Int	Market Int	Beg Imbalance Volume	Adjustment Volume	Entitled	
Abell 5-5										
Energy Corp	Abell 5-5	Edge Petroleum	Energy Corp	0.41250000	0.00000000	0.41250000	0.00	0.00		
Energy Corp	Abell 5-5	Energy Corp	Energy Corp	0.17500000	0.00000000	0.17500000	0.00	0.00		
Energy Corp	Abell 5-5	Newfield Exploration	Energy Corp	0.05000000	0.00000000	0.05000000	0.00	0.00		
Energy Corp	Abell 5-5	Range Energy	Energy Corp	0.36250000	0.00000000	0.36250000	0.00	0.00		
Abell 5-7										
Energy Corp	Abell 5-7	Edge Petroleum	Energy Corp	0.41250000	0.00000000	0.41250000	0.00	0.00		
Energy Corp	Abell 5-7	Energy Corp	Energy Corp	0.17500000	0.00000000	0.17500000	0.00	0.00		
Energy Corp	Abell 5-7	Newfield Exploration	Energy Corp	0.05000000	0.00000000	0.05000000	0.00	0.00		
Energy Corp	Abell 5-7	Range Energy	Energy Corp	0.36250000	0.00000000	0.36250000	0.00	0.00		
Agua Dulce Stratton 4-3										
Energy Corp	Agua Dulce Stratton 4-3	Energy Corp	Energy Corp	0.31250000	0.00000000	0.31250000	0.00	0.00		
Energy Corp	Agua Dulce Stratton 4-3	Gasco Energy	Energy Corp	0.20000000	0.00000000	0.20000000	0.00	0.00		
Energy Corp	Agua Dulce Stratton 4-3	Gulfport Energy	Energy Corp	0.17500000	0.00000000	0.17500000	0.00	0.00		
Energy Corp	Agua Dulce Stratton 4-3	Penn Virginia Oil & Gas	Energy Corp	0.22500000	0.00000000	0.22500000	0.00	0.00		
Energy Corp	Agua Dulce Stratton 4-3	Terax Energy	Energy Corp	0.08750000	0.00000000	0.08750000	0.00	0.00		

Operator (propoperator.operator) Indicates the party responsible for the management and day-to-day operation of the property. The operator of a producing property is generally a working-interest owner or a company under contract to the working-interest owner(s).

Property (propquantity.property) Indicates the property associated with this production forecast balance.

Owner (propquantity.owner) Short name identifier of the interest owner (i.e., company or entity) in the marketing arrangement balance.

Seller (propquantity.seller) Indicates the party responsible for marketing the production for the indicated owner in this marketing arrangement.

Work interest (propquantity.workinterest) Indicates the entitled decimal percentage interest that this owner has in this marketing arrangement. 100% is represented as 1.0. This column is not editable.

Balance interest (propquantity.balanceint) Indicates the decimal percentage adjustment, up to operator thresholds, required to bring this owner's interest in the marketing arrangement back into balance given prior period over or under deliveries.

Market interest (propquantity.marketint) Indicates the right to market decimal interest for this owner in this marketing arrangement. The right to market interest takes into consideration balancing adjustments, up to operator thresholds, to bring the owner back into entitled balance assuming

prior period over or under deliveries. *Market Interest* is calculated as follows:

Market Interest = Working Interest + Balancing Interest

Max Balance Int (propoperator.maxbalanceint) Indicates the maximum amount of interest that can be applied when balancing this property.

Override MaxBalance Int (propoperator.overridebalanceint) If this field is populated, this value will be used in place of the Max Balance Int value when calculating balance interest.

Beg Imbalance (propquantity.imbalance) Opening cumulative imbalance for this owner on this marketing arrangement.

Adjustment (propquantity.adjustment) allows the user to adjust the system generated cumulative imbalance for each working interest owner and maintain balanced adjustments. This occurs in a financially settled imbalance where there is no prior period volumetric adjustment, but the need to capture an adjustment to the cumulative imbalance due to an agreed upon cash settlement. A manual adjustment to a long imbalance will trigger a recalculation of the short imbalances in order to keep the total net adjustments balanced at zero.

Entitlement (propquantity.entitlement) Indicates the entitled share of the quantity for this marketing arrangement for the given time range (i.e., *Beg/End Time*) per *Time Unit* for this owner based on the owner's interest described by the *Work Interest* column.

Market (propquantity.market) Indicates the calculated right to market share of the quantity for this marketing arrangement for the given time range (i.e., *Beg/End Time*) per *Time Unit* for this owner based on the owners interest described by the *Market Interest* column.

Actual (propquantity.actual) Indicates the best available actual delivered quantity for this marketing arrangement for the given time range (i.e., *Beg/End Time*) per *Time Unit* for this owner.

When the balancing record is initially created by invoking the *Calculate Position* icon from the Production Forecast view, the *Actual* column is initially set to the value in the *Market* column.

As the underlying property quantities are posted with estimated and/or actual values from the *Gathering System Measurement*, *Gathering System Actuals*, *Production Measurement*, *Operator Actuals* or *Physical Operator Actuals* views, the *Actual* column changes to reflect the best available quantity.

End imbalance (propquantity.endimbalance) The ending imbalance for the owner of this marketing arrangement.

Beg time (propquantity.begtime) Indicates the beginning date that this balance is in effect for this owner.

End time (propquantity.endtime) Indicates the ending date that this balance is in effect for this owner.

Unit (propquantity.unit) Unit of measure in which the *Imbalance, Market, Work and Actual* columns are expressed.

Time unit (propquantity.timeunit) Frequency interval of the *Imbalance, Market, Entitlement and Actual* columns to describe the context of the indicated quantity (e.g., per DAY, MONTH or TOTAL).

Balance status (propquantity.balancestatus) If TRUE, indicates the marketing status has been balanced.

Quantity status (propquantity.quantitystatus) Indicates the underlying quantity status (e.g., FORECAST, ESTIMATE or ACTUAL) of transactions that are associated with this marketing arrangement balance. Quantity status associated with a property is stored in the propquantity table.

Total Market(.totalmarket) Indicates the total market share of the quantity for this marketing arrangement

Total Entitlement (.totalentitlement) Indicates the total entitled share of the quantity for this marketing arrangement

Gross Quantity (.grossquantity) Displays the gross quantity, this field is calculated by:

$$\text{Gross Quantity} = \text{Total entitlement} / \text{Work interest}$$

Estimate date (propquantity.estimatedate) Indicates the last date on which daily meter estimates are recorded for quantities associated with this marketing arrangement.

Product (propquantity.product) Indicates the product marketed.

Pipeline (propquantity.pipeline) Indicates the gathering or transmission system (i.e., pipeline *Category* = GATHERING or TRANSMISSION) that is connected to the property associated with this marketing arrangement. This column is only associated with *Products* with *Product Groups* of GAS.

Point (propquantity.point) Indicates the point on the pipeline that is directly connected to the property associated with this marketing arrangement. Generally this is the initial gathering point. This column is only associated with *Products* with *Product Groups* of GAS.

Location (propquantity.location) Indicates the geographic location that is connected to the property associated with this marketing arrangement. This column is only associated with *Products* with *Product Groups* of LIQUID.

Positions pane

The following columns are associated with this pane:

The screenshot shows the 'Production Positions' window with two panes. The top pane is titled 'Balancing' and contains a table with columns: Operator, Property, Owner, Seller, Work Int, Balance Int, Market Int, Beg Imbalance Volume, and Adjustmer. The bottom pane is titled 'Positions' and contains a table with columns: Position, Quantitytype, Begtime, Endtime, Path, Quantity Status, Energy, Energy Unit, and Mass.

Operator	Property	Owner	Seller	Work Int	Balance Int	Market Int	Beg Imbalance Volume	Adjustmer
Energy Corp	Func Property	Energy Corp	Energy Corp	1.00000000	0.00000000	1.00000000	0.00	
Energy Corp	Func Property	Energy Corp	Energy Corp	0.25000000	0.00000000	0.25000000	0.00	
Energy Corp	Func Property	ExxonMobil	Energy Corp	0.75000000	0.00000000	0.75000000	0.00	
				2.00000000	0.00000000	2.00000000	0.00	
				2.00000000	0.00000000	2.00000000	0.00	

Position	Quantitytype	Begtime	Endtime	Path	Quantity Status	Energy	Energy Unit	Mass
1100724	RECEIPT	8/1/2006 12:00 A	9/1/2006 12:00 A		FORECAST	65	DTH	
1100724	RECEIPT	5/1/2006 12:00 A	6/1/2006 12:00 A		FORECAST	0	DTH	

Position (ngquantity.position) Indicates the unit of measure associated with the quantity-related columns for this position.

Quantitytype (ngquantity.quantitytype) Indicates whether the position is a RECEIPT, DELIVERY or LOSS. *Quantity type* corresponds to the *Position Type* column associated with the position. For example, *Position Type*=BUY or supply positions created at the destination point of an inventory movement, correspond to *Quantity Type*=RECEIPT. *Position Type*=SELL or short positions created at the origin point of an inventory movement, correspond to *Quantity Type*=DELIVERY.

For *Position Type*=Exchange, two transaction sequences are involved, one with a *Quantity Type*=RECEIPT and the other with DELIVERY.

Quantity Type of LOSS is generated during the nomination process and represents any losses resulting from the movement.

Beg time (ngquantity.begtime) Beginning time of the effective delivery period for this position row.

End time (ngquantity.endtime) Ending time of the effective delivery period for this position row.

Path (ngquantity.path) Indicates the unique system-generated number

assigned to the position row when the position was nominated in the *Natural Gas Scheduling* view (i.e., *Create Path*, *Create Contract Paths*, *Create Title Transfers* or *Repeat Path* icon invoked).

Quantity Status (ngquantity.quantitystatus) System-generated indicator of the state of the quantity associated with the indicated position. Possible values in order of least to best settlement quality are: FORECAST, SCHEDULE, NOM, ESTIMATE or ACTUAL.

Energy (ngquantity.energy) Indicates the measured energy quantity for the indicated position for the indicated *Beg/End Time*. This column is displayed when the *Display Energy* parameter is checked (i.e., Parameters sidebar >> Display Energy).

Energy Unit (ngquantity.energyunit) Indicates the unit of measurement in which energy quantities are expressed. This column is based on the energy unit of the pipeline and is intended for display only.

Mass (physicalquantity.mass) The quantity of the commodity expressed in the unit of measure represented by the *Mass Unit*.

Volume (ngquantity.volume) Indicates the measured volumetric quantity for the indicated position for the indicated *Beg/End Time*. This column is displayed when the *Display Volume* parameter is checked (i.e., Parameters sidebar >> Display Volume).

Mass Unit (physicalquantity.massunit) Indicates the unit of measurement in which the *Mass* is expressed.

Volume Unit (ngquantity.volumeunit) Indicates the unit of measurement in which volumetric quantities are expressed. This column is based on the volume unit of the pipeline and is intended for display only.

Time Unit (ngquantity.timeunit) Indicates the time interval of measurement quantities associated with this measurement allocation. This column is influenced by the Frequency column on the Actuals pane. Options are: MONTH, DAY or HOUR.

Pipeline (ngquantity.pipeline) Indicates the short pipeline identifier that describes a continuous pipe conduit, complete with such equipment as valves, compressor stations, communications systems, and meters, for transporting natural gas from one point to another, usually from a point in or beyond the producing field to another pipeline or to points of use.

A pipeline can represent a gathering system, interstate/intrastate pipeline or distribution facility.

Point (ngquantity.point) Indicates the short identifier of the geographic location on the pipeline associated with this measurement record.

Standard selection criteria

The following standard selection criteria are associated with this View:

- Location
- Mass unit
- Operator
- Path
- Pipeline
- Point
- Positions
- Quantity type
- Seller
- Volume unit

View-specific time periods

The following standard time criteria are associated with this View:

- Beg time
- Creation Date
- Estimate date
- Revision date
- Time Range

PART 5: EQUITY PRODBALANCE CLASS

Part 5: EquityProdBalance Class


Allegro Views are organized into application classes. This part of the documentation provides information about the structure of each View associated with the *EquityProdBalance* class of the *Equity Production* component, including View access procedure, a description of standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.

The following Views belong to this class:

- [Chapter 14, "Balancing view"](#), provides procedures for balancing owner-level positions.
- [Chapter 15, "Nominations view"](#), provides procedures for configuring and submitting nominations to the pipeline.

Parameters

The following parameter is associated with this class:



- **Display Energy** If checked, indicates that energy quantities in the *Prodquantity* pane of the *Nominations* view and the *Balancing* pane of the *Balancing* view will display in the unit of measure described by the *Energy Unit* column of the *Pipelines* pane of the *Natural Gas Pipeline* view.
- **Display Volume** If checked, indicates that volumetric quantities in the *Prodquantity* pane of the *Nominations* view and the *Balancing* pane of the *Balancing* view will display in the unit of measure described by the *Volume Unit* column of the *Pipelines* pane of the *Natural Gas Pipeline* view.

Icons

The following icons are associated with this class:



- **Balance Interests** Click to calculate right to market adjustments so that the cumulative imbalance will return back to zero for each owner. If an owner is in a short position, then the calculated right to market adjustment will be positive. If the owner is in a long position, the adjustment will be negative. The final right to market (RTM) quantity is equal to the right to market percentage times the total monthly production. Right to market percentage is equal to the entitlement percentage plus the right to market adjustment.
- **Confirm All** If you are satisfied that all positions that have been retrieved are subject to nomination, you can confirm all the positions in mass by choosing the Confirm All icon. When invoked, the Confirm All icon automatically checks the Confirm checkbox column in all rows on the Prod nominations pane.
- **Create Nomination** Click to trigger a nomination to the pipeline.

Chapter 14: Balancing View

The Balancing View is used to display the best available right to market, actual and imbalance quantities by property, owner and seller for a given time period. This information can help you actively manage the balancing and nomination process for properties.

This part of the documentation provides information about the structure of the *Balancing View*. The information is divided into the following sections:

- [View access procedure](#)
- [Standard panes and columns](#)
- [Standard selection criteria](#)
- [View-specific time periods](#)

View access procedure

To access the Balancing View choose Navigation sidebar >> Property>>Equity Production>>Balancing.

Workflow		Balancing				
Balancing						
 Operator	Property	 Owner	 Seller	Work Int	Balance Int	Market Int
Elm Grove 4-2	Elm Grove 4-2	Aspen Drilling	Aspen Group Resour	1.00000000	1.11000000	1.11200000
Freshwater Bayou 10-5	Freshwater Bayou 10-	Century Petroleum	Abraxas Petroleum	1.11000000	1.21000000	1.14000000
	Freshwater Bayou 10-	Century Petroleum	Abraxas Petroleum	1.11000000	1.21000000	1.14000000
Hayes 7-3	Hayes 7-3	Forest Oil	West Shore Pipe Lin	1.10000000	1.41000000	1.23000000
	Hayes 7-3	Forest Oil	West Shore Pipe Lin	1.10000000	1.41000000	1.23000000
Wildcat Bayou 11-5	Wildcat Bayou 11-5	Questar Exploration	Maclaren Energy	0.10600000	0.11000000	1.25000000
	Wildcat Bayou 11-5	Questar Exploration	Maclaren Energy	0.10600000	0.11000000	1.25000000

Standard panes and columns

The following standard panes and columns are associated with this View. The View label name is indicated in bold; the underlying data element name is enclosed in parenthesis.

There is one pane associated with this View:

- [Balancing pane](#)

Balancing Pane

The following columns are associated with this pane:

Workflow Balancing						
Balancing						
Operator	Property	Owner	Seller	Work Int	Balance Int	Market Int
Elm Grove 4-2	Elm Grove 4-2	Aspen Drilling	Aspen Group Resour	1.00000000	1.11000000	1.11200000
Freshwater Bayou 10-5						
	Freshwater Bayou 10-	Century Petroleum	AbraXas Petroleum	1.11000000	1.21000000	1.14000000
	Freshwater Bayou 10-	Century Petroleum	AbraXas Petroleum	1.11000000	1.21000000	1.14000000
Hayes 7-3						
	Hayes 7-3	Forest Oil	West Shore Pipe Lin	1.10000000	1.41000000	1.23000000
	Hayes 7-3	Forest Oil	West Shore Pipe Lin	1.10000000	1.41000000	1.23000000
Wildcat Bayou 11-5						
	Wildcat Bayou 11-5	Questar Exploration	Maclaren Energy	0.10600000	0.11000000	1.25000000
	Wildcat Bayou 11-5	Questar Exploration	Maclaren Energy	0.10600000	0.11000000	1.25000000

Operator (propoperator.operator) Indicates the party responsible for the management and day-to-day operation of the property. The operator of a producing property is generally a working-interest owner or a company under contract to the working-interest owner(s).

Property (propquantity.property) Indicates the property associated with this production forecast balance.

Owner (propquantity.owner) Short name identifier of the interest owner (i.e., company or entity) in the marketing arrangement balance.

Seller (propquantity.seller) Indicates the party responsible for marketing the production for the indicated owner in this marketing arrangement.

Work interest (propquantity.workinterest) Indicates the entitled decimal percentage interest that this owner has in this marketing arrangement. 100% is represented as 1.0. This column is not editable.

Balance interest (propquantity.balanceint) Indicates the decimal percentage adjustment, up to operator thresholds, required to bring this owner's interest in the marketing arrangement back into balance given prior period over or under deliveries.

Market interest (propquantity.marketint) Indicates the right to market decimal interest for this owner in this marketing arrangement. The right to market interest takes into consideration balancing adjustments, up to operator thresholds, to bring the owner back into entitled balance assuming prior period over or under deliveries. *Market Interest* is calculated as follows:

$$\text{Market Interest} = \text{Working Interest} + \text{Balancing Interest}$$

Max Balance Int (propoperator.maxbalanceint) Indicates the maximum amount of interest that can be applied when balancing this property.

Override MaxBalance Int (propoperator.overridebalanceint) If this

field is populated, this value will be used in place of the Max Balance Int value when calculating balance interest.

Beg Imbalance (propquantity.imbalance) Opening cumulative imbalance for this owner on this marketing arrangement.

Adjustment (propquantity.adjustment) allows the user to adjust the system generated cumulative imbalance for each working interest owner and maintain balanced adjustments. This occurs in a financially settled imbalance where there is no prior period volumetric adjustment, but the need to capture an adjustment to the cumulative imbalance due to an agreed upon cash settlement. A manual adjustment to a long imbalance will trigger a recalculation of the short imbalances in order to keep the total net adjustments balanced at zero.

Entitlement (propquantity.entitlement) Indicates the entitled share of the quantity for this marketing arrangement for the given time range (i.e., *Beg/End Time*) per *Time Unit* for this owner based on the owner's interest described by the *Work Interest* column.

Market (propquantity.market) Indicates the calculated right to market share of the quantity for this marketing arrangement for the given time range (i.e., *Beg/End Time*) per *Time Unit* for this owner based on the owners interest described by the *Market Interest* column.

Actual (propquantity.actual) Indicates the best available actual delivered quantity for this marketing arrangement for the given time range (i.e., *Beg/End Time*) per *Time Unit* for this owner.

When the balancing record is initially created by invoking the *Calculate Position* icon from the Production Forecast view, the *Actual* column is initially set to the value in the *Market* column.

As the underlying property quantities are posted with estimated and/or actual values from the *Gathering System Measurement*, *Gathering System Actuals*, *Production Measurement*, *Operator Actuals* or *Physical Operator Actuals* views, the *Actual* column changes to reflect the best available quantity.

End imbalance (propquantity.endimbalance) The ending imbalance for the owner of this marketing arrangement. This is calculated as:

Beginning Imbalance + Adjustment + sum of entitlements- sum of actual

Beg time (propquantity.begtime) Indicates the beginning date that this balance is in effect for this owner.

End time (propquantity.endtime) Indicates the ending date that this balance is in effect for this owner.

Unit (propquantity.unit) Unit of measure in which the *Imbalance, Market, Work and Actual* columns are expressed.

Time unit (propquantity.timeunit) Frequency interval of the *Imbalance, Market, Entitlement and Actual* columns to describe the context of the indicated quantity (e.g., per DAY, MONTH or TOTAL).

Balance status checkbox (propquantity.balancestatus)
Check this checkbox to indicate that the marketing arrangement has been balanced. The system will automatically check this checkbox when you click the *Balance Interests* icon in Navigation sidebar>>Property>>Equity Production>>Balancing.

Quantity status (propquantity.quantitystatus) Indicates the underlying quantity status (e.g., FORECAST, ESTIMATE or ACTUAL) of transactions that are associated with this marketing arrangement balance. Quantity status associated with a property is stored in the propquantity table.

Total Market (.totalmarket) Indicates the total market share of the quantity for this marketing arrangement

Total Entitlement (.totalentitlement) Indicates the total entitled share of the quantity for this marketing arrangement

Gross Quantity (.grossquantity) Displays the gross quantity, this field is calculated by:

Gross Quantity = Total entitlement/Work interest

Estimate date (propquantity.estimatedate) Indicates the last date on which daily meter estimates are recorded for quantities associated with this marketing arrangement.

Product (propquantity.product) Indicates the product marketed.

Pipeline (propquantity.pipeline) Indicates the gathering or transmission system (i.e., pipeline *Category* = GATHERING or TRANSMISSION) that is connected to the property associated with this marketing arrangement. This column is only associated with *Products* with *Product Groups* of GAS.

Point (propquantity.point) Indicates the point on the pipeline that is directly connected to the property associated with this marketing

arrangement. Generally this is the initial gathering point. This column is only associated with *Products* with *Product Groups* of GAS.

Location (propquantity.location) Indicates the geographic location that is connected to the property associated with this marketing arrangement. This column is only associated with *Products* with *Product Groups* of LIQUID.

Standard selection criteria

The following standard selection criteria are associated with this View:

- Field
- Forecast status
- Location
- Operator
- Owner
- Pipeline
- Point
- Product
- Property
- Region
- Seller
- Volume unit

View-specific time periods

The following standard time criteria are associated with this View:

- Beg time
- Creation Date
- End time
- Estimate date
- Revision date
- Time Range

Chapter 15: Nominations View

The Nominations View is used to create Pipeline nominations for properties. This view creates SCHEDULE and NOM records in ngquantity at the Point in the Pipeline that connects with the Property.

This part of the documentation provides information about the structure of the *Nominations View*. The information is divided into the following sections:

- [View access procedure](#)
- [Standard panes and columns](#)
- [Standard selection criteria](#)
- [View-specific time periods](#)

View access procedure

To access the Nominations View choose Navigation sidebar >> Property >> Equity Production>>Nominations.

Seller	Property	Market interest	Market rate	Market Energy	Product	Quantity status	Ba	Estimate date	Owner
Energy Search	El Tanzanite 6-6	0.16250000		0.00	NG	FORECAST	☐		Energy Search
Energy Search	El Tanzanite 6-6	0.16250000		116,328.70	NG	FORECAST	☐		Energy Search
Energy Search	El Tanzanite 6-6	0.16250000		119,298.90	NG	FORECAST	☐		Energy Search
Energy Search	El Tanzanite 6-6	0.16250000		108,655.69	NG	FORECAST	☒		Energy Search

Shipper	Beg time	End time	Quantity	Estimate	Nom estimate	Variance	Nom variance	Ad	Adj date	Adj quantity	Co
Energy Corp	12/1/2007 12:00	1/1/2008 12:00	87,235.00	2,704,285	2,704,285	0	0	☐			0
Energy Search	12/1/2007 12:00	1/1/2008 12:00	71,384.00	2,212,904	2,212,904	0	0	☐			0
Energyquest Resour	12/1/2007 12:00	1/1/2008 12:00	59,169.00	1,834,239	1,834,239	0	0	☐			0
Gulfport Energy	12/1/2007 12:00	1/1/2008 12:00	47,322.00	1,466,982	1,466,982	0	0	☐			0

Standard panes and columns

The following standard panes and columns are associated with this View. The View label name is indicated in bold; the underlying data element name is enclosed in parenthesis.

There are two panes associated with this View:

- [Prodquantity pane](#)
- [Production Nominations pane](#)

Prodquantity pane

The following columns are associated with this pane:

PART 5: EQUITYPRODBALANCE CLASS

Seller	Property	Market interest	Market rate	Market Energy	Product	Quantity status	Ba	Estimate date	Owner
Energy Search	El Tanzanite 6-6	0.16250000		0.00	NG	FORECAST	☐		Energy Search
Energy Search	El Tanzanite 6-6	0.16250000		116,326.70	NG	FORECAST	☐		Energy Search
Energy Search	El Tanzanite 6-6	0.16250000		119,298.90	NG	FORECAST	☐		Energy Search
Energy Search	El Tanzanite 6-6	0.16250000		108,655.69	NG	FORECAST	☒		Energy Search

Shipper	Beg time	End time	Quantity	Estimate	Nom estimate	Variance	Nom variance	Ad	Adj date	Adj quantity	Co
Energy Corp	12/1/2007 12:00	1/1/2008 12:00	87,235.00	2,704,285	2,704,285	0	0	☐		0	☐
Energy Search	12/1/2007 12:00	1/1/2008 12:00	71,384.00	2,212,904	2,212,904	0	0	☐		0	☐
Energyquest Resour	12/1/2007 12:00	1/1/2008 12:00	59,169.00	1,834,239	1,834,239	0	0	☐		0	☐
Gulfport Energy	12/1/2007 12:00	1/1/2008 12:00	47,322.00	1,466,982	1,466,982	0	0	☐		0	☐

Seller (propquantity.seller) Indicates the party responsible for marketing the production for the indicated owner in this marketing arrangement.

Property (propquantity.property) Indicates the property associated with this marketing arrangement balance.

Market interest (propquantity.marketint) Indicates the right to market decimal interest for this owner in this marketing arrangement. The right to market interest takes into consideration balancing adjustments, up to operator thresholds, to bring the owner back into entitled balance assuming prior period over or under deliveries. Market Interest is calculated as follows:

$$\text{Market Interest} = \text{Working Interest} + \text{Balancing Interest}$$

Market rate (.marktrate) Displays the current market rate calculated as follows:

$$\text{Market rate} = \text{Market} / \text{days in period}$$

Market (propquantity.market) Indicates the calculated right to market share of the quantity for this marketing arrangement for the given time range (i.e., Beg/End Time) per Time Unit for this owner based on the owners interest described by the Market Interest column.

Unit (propquantity.unit) Unit of measure in which the *Imbalance*, *Market*, *Work* and *Actual* columns are expressed.

Product (propquantity.product) Indicates the product marketed.

Quantity status (propquantity.quantitystatus) Indicates the underlying quantity status (e.g., FORECAST, ESTIMATE or ACTUAL) of transactions that are associated with this marketing arrangement balance.

Balance status checkbox (propquantity.balancestatus) If this checkbox is checked, it indicates that the marketing arrangement has been balanced. The system

will automatically check this checkbox when you click the Balance Interests icon in Navigation sidebar>>Property.>>Equity Production.>>Balancing.

Estimate date (propquantity.estimatedate) If populated, indicates the last date on which daily meter estimates are recorded for quantities associated with this marketing arrangement.

The estimate date is used to calculate nom estimates.

If this column is null, measurements are coming from the forecast volume.

Owner (propquantity.owner) Short name identifier of the interest owner (i.e., company or entity) in the marketing arrangement balance.

Pipeline (propquantity.pipeline) Indicates the gathering or transmission system (i.e., pipeline Category = GATHERING or TRANSMISSION) that is connected to the property associated with this marketing arrangement. This column is only associated with Products with Product Groups of GAS.

Point (propquantity.point) Indicates the point on the pipeline that is directly connected to the property associated with this marketing arrangement. Generally this is the initial gathering point. This column is only associated with Products with Product Groups of GAS.

Time Unit (prodforecast.timeunit) Unit of time measurement for the forecast.

Beg Time (prodforecast.begtime) The start date of the forecast.

End Time (prodforecast.endtime) The end date of the forecast.

Energy Factor (.energyfactor) Indicates the factor used in deriving an energy quantity from a volumetric quantity, and vice versa.

Prod nominations Pane

The following columns are associated with this pane:

Workflow Nominations (ANR)										
Prodquantity										
	Seller	Property	Market interest	Market rate	Market Energy	Product	Quantity status	Ba	Estimate date	Owner
El Tanzanite 6-6										
	Energy Search	El Tanzanite 6-6	0.16250000		0.00	NG	FORECAST	☐		Energy Search
	Energy Search	El Tanzanite 6-6	0.16250000		116,328.70	NG	FORECAST	☐		Energy Search
	Energy Search	El Tanzanite 6-6	0.16250000		119,298.90	NG	FORECAST	☐		Energy Search
	Energy Search	El Tanzanite 6-6	0.16250000		108,655.69	NG	FORECAST	☒		Energy Search
Prod nominations										
	Shipper	Beg time	End time	Quantity	Estimate	Nom estimate	Variance	Nom variance	Adj date	Adj quantity
	Energy Corp	12/1/2007 12:00	1/1/2008 12:00	87,235.00	2,704,285	2,704,285	0	0	☐	0
	Energy Search	12/1/2007 12:00	1/1/2008 12:00	71,384.00	2,212,904	2,212,904	0	0	☐	0
	Energyquest Resour	12/1/2007 12:00	1/1/2008 12:00	59,169.00	1,834,239	1,834,239	0	0	☐	0
	Gulfport Energy	12/1/2007 12:00	1/1/2008 12:00	47,322.00	1,466,982	1,466,982	0	0	☐	0

Seller (prodnomination.shipper) Indicates the Seller responsible for marketing the production for the indicated owner in this marketing arrangement.

Beg time (prodnomination.begtime) Indicates the beginning date that this nomination is in effect for this property.

End time (prodnomination.endtime) Indicates the ending date that this nomination is in effect for this property.

Nom Quantity (prodnomination.quantity) The quantity nominated and displayed in the Scheduling view; it is equal to the daily production forecast quantity only until the first nomination adjustment.

Prod Estimate (.estimate) Equal to the Market Energy from Prod Quantity pane; it is the projected production quantity

Nom estimate (.nomestimate) Indicates the estimated nominated quantity based on the following calculation:

EstimateDays = days from beg time (prodquantity.begtime) to most recent estimate date (prodquantity.estimatedate) from meter measurements

ReminingDays = days from most recent estimate date (prodquantity.estimatedate) to end time (prodquantity.endtime).

If the *Confirm status checkbox* is checked, *Nom estimate = (MarketRate * EstimateDays) + (ConfirmQuantity * RemainingDays)*

If *Confirm status checkbox* is not checked, *Nom estimate = (MarketRate * EstimateDays) + (NomQuantity * RemainingDays)*

Variance (.variance) Indicates the variance or the difference between Prod Estimate and the Nom Estimate.

Nom Variance (.nomvariance) Indicates the nominated variance calculated as Variance / # of days associated with this nomination record

Adj status checkbox (.adjstatus) If checked, indicates an adjustment is ready to be made to original nomination record. See Adj quantity column description.

Adj date Indicates the date the adjustment; defaults in, but can be overwritten

Adj quantity When a nomination quantity on the *Production Nominations pane* is

adjusted and the *Adjustment* column is checked, upon saving the record the system will automatically generate a new nomination record with the quantity equal to the difference between the original nomination and the updated quantity. Adjust quantity defaults in, but can be overwritten .

Confirm status checkbox (prodnomination.confirmstatus) If the Confirm status checkbox is checked, Nom estimate = (MarketRate * EstimateDays) + (ConfirmQuantity * RemainingDays)

If Confirm status checkbox is not checked, Nom estimate = (MarketRate * EstimateDays) + (NomQuantity * RemainingDays)

Confirm quantity (prodnomination.quantity) Used to calculate the Nom estimate when status is confirmed.

Point (prodnomination.point) Indicates the point on the pipeline that is directly connected to the property associated with this nomination. Generally this is the initial gathering point. This column is only associated with *Products* with *Product Groups* of GAS.

Product (prodnomination.product) Indicates the type of product associated with the nomination.

Unit (prodnomination.unit) Indicates the unit of measurement in which quantities are expressed for this nomination.

Time Unit (prodnomination.timeunit) Indicates the time interval of measurement quantities associated with this measurement allocation. Options are: TOTAL, QUARTER, MONTH, SEMIMONTH, DAY, HOUR, HALFHOUR, and QTRHOUR

Standard selection criteria

The following standard selection criteria are associated with this View:

- Energy unit
- Forecast status
- Location
- Operator
- Owner
- Pipeline
- Point
- Product
- Property
- Quantity status
- Seller

- Shipper
- Unit
- Volume unit

View-specific time periods

The following standard time criteria are associated with this View:

- Beg time
- Creation date
- End time
- Estimate date
- Revision date
- Time range

PART 6: EQUITY PRODN NOTIFICATIONS CLASS

Part 6: EquityProdNotifications Class

Allegro Views are organized into application classes. This part of the documentation provides information about the structure of each View associated with the EquityProdNotifications class of the *Equity Production* component, including View access procedure, a description of standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.

The following Views belong to this class:


- [Chapter 16, "Shipper Notification view"](#), provides procedures for generating and sending notifications in mass.

Parameters

The following parameters are associated with this class:

- None.

Icons



- **Create Notification** Click to automatically generate shipper notification documents.
- **Send Notification** Click to automatically send shipper notification documents.

Chapter 16: Shipper Notification View


The *Shipper Notification* View is used to generate and send notifications in mass.

This part of the documentation provides information about the structure of the *Shipper Notification* View. The information is divided into the following sections:

- [View access procedure](#)
- [Standard panes and columns](#)
- [Standard selection criteria](#)
- [View-specific time periods](#)

View access procedure

To access the Shipper Notification View choose Navigation sidebar >> Property>>Equity Production>>Shipper Notification.



The screenshot shows a software interface with three tabs: 'Shipper Notification' (selected), 'Workflow', and 'Shipper Performance'. Below the tabs is a table titled 'Nominations'. The table has columns: TIK Owner, Beg time, End time, Quantity, Point Desc, Point, Product, Unit, and Time un. The first row is expanded, showing 'Energy Corp' as the TIK Owner, with a start time of '10/1/2007 12:00 AM' and an end time of '11/1/2007 12:00 AM'. The quantity is '9318.00'. The point description is 'Branch', and the point is '040002308 GREEN CANYON B'. The product is 'NG', the unit is 'mmbtu', and the time unit is 'DAY'.

TIK Owner	Beg time	End time	Quantity	Point Desc	Point	Product	Unit	Time un
Energy Corp	10/1/2007 12:00 AM	11/1/2007 12:00 AM	9318.00	Branch	040002308 GREEN CANYON B	NG	mmbtu	DAY

Standard panes and columns


The following standard panes and columns are associated with this View. The View label name is indicated in bold; the underlying data element name is enclosed in parenthesis.

There are three panes associated with this View:

- [Nominations pane](#)
- [ShipperNotification pane](#)
- [Production pane](#)

Nominations Pane

The following columns are associated with this pane:



The screenshot shows a software interface with three tabs: 'Shipper Notification' (selected), 'Workflow', and 'Shipper Performance'. Below the tabs is a table titled 'Nominations'. The table has columns: TIK Owner, Beg time, End time, Quantity, Point Desc, Point, Product, Unit, and Time un. The first row is expanded, showing 'Energy Corp' as the TIK Owner, with a start time of '10/1/2007 12:00 AM' and an end time of '11/1/2007 12:00 AM'. The quantity is '9318.00'. The point description is 'Branch', and the point is '040002308 GREEN CANYON B'. The product is 'NG', the unit is 'mmbtu', and the time unit is 'DAY'.

TIK Owner	Beg time	End time	Quantity	Point Desc	Point	Product	Unit	Time un
Energy Corp	10/1/2007 12:00 AM	11/1/2007 12:00 AM	9318.00	Branch	040002308 GREEN CANYON B	NG	mmbtu	DAY

TIK Owner (prodnomination.shipper) Indicates the take-in-kind owner

responsible for marketing the production for the indicated owner in this marketing arrangement.

Beg time (prodnomination.begtime) Indicates the beginning date that this nomination is in effect for this property.

End time (prodnomination.endtime) Indicates the ending date that this nomination is in effect for this property.

Quantity (prodnomination.quantity) Indicates the quantity being nominated.

Point Desc (ngpoint.desc) Indicates the full name of the point that can be used on external statements.

Notification date (prodnomination.notificationdate) Indicates the notification date associated with this nomination

Point (prodnomination.point) Indicates the point on the pipeline that is directly connected to the property associated with this nomination. Generally this is the initial gathering point. This column is only associated with *Products* with *Product Groups* of GAS.

Product (prodnomination.product) Indicates the type of product associated with the nomination.

Unit (prodnomination.unit) Indicates the unit of measurement in which quantities are expressed for this nomination.

Time Unit (prodnomination.timeunit) Indicates the time interval of measurement quantities associated with this measurement allocation. Options are: TOTAL, QUARTER, MONTH, SEMIMONTH, DAY, HOUR, HALFHOUR, and QTRHOUR

Pipeline (prodnomination.pipeline) Indicates the gathering or transmission system (i.e., pipeline *Category* = GATHERING or TRANSMISSION) that is connected to the property associated with this marketing arrangement. This column is only associated with *Products* with *Product Groups* of GAS.

Production pane

The following columns are associated with this pane:

Workflow Shipper Notification										
Nominations ShipperNotification										
TK Owner	Beg time	End time	Quantity	Point Desc	Notification Date	Point	Product	Unit	Time unit	Pipeline
Energy Corp	8/1/2006 12:00 AM	8/1/2006 12:00 AM	65.00	Beaver Creek/Kenova		BEAVER CREEK	NG	DTH	DAY	TCO
Production										
Owner	Propert Desc	TK Owner	Meter	Meter Desc	Market Int	Daily Energy	Daily Volume	Market Energy	Energy Unit	B
Energy Corp	Functionality Test	Energy Corp	Func Meter 1	Functionality Test	1.00000000	.00	.00	0.00	DTH	5/
Energy Corp	Functionality Test	Energy Corp	Func Meter 1	Functionality Test	0.25000000	16.13	16.13	500.00	DTH	8/
ExxonMobil	Functionality Test	Energy Corp	Func Meter 1	Functionality Test	0.75000000	48.39	48.39	1,500.00	DTH	8/
					2.00000000			2,000.00		

Owner (propquantity.owner) Short name identifier of the interest owner (i.e., company or entity) in the marketing arrangement balance.

Propert desc (property.description) Description of the property

Tik Owner (propquantity.seller) Indicates the party responsible for marketing the production for the indicated owner in this marketing arrangement.

Meter (meter.meter) Indicates the user-defined identifier associated with the device used to measure and record the quantity associated with this ticket.

Meter desc (meter.meterdesc) Description of the meter

Market int (propquantity.marketint) Indicates the right to market decimal interest for this owner in this marketing arrangement. The right to market interest takes into consideration balancing adjustments, up to operator thresholds, to bring the owner back into entitled balance assuming prior period over or under deliveries. *Market Interest* is calculated as follows:

Market Interest = Working Interest + Balancing Interest

Daily Energy Indicates the averaged measured energy quantity per day.

Daily Volume Indicates the averaged measured volume quantity per day.

Market Energy (propquantity.marketenergy) Represents the total energy quantity delivered to the receiver of power or wheeling entity for the Beg/End Time range expressed in the unit of measure described by the Energy Unit column as defined by the following formula:

Market energy = {value of Duration column} x {value of the Market Rate column}

Energy unit (propquantity.energyunit) Indicates the unit of measurement in which energy quantities are expressed. This column is based on the energy unit of the pipeline and is intended for display only.

Beg time (propquantity.begtime) Indicates the beginning date that this balance is in effect for this owner.

End time (propquantity.endtime) Indicates the ending date that this balance is in effect for this owner.

Time unit (propquantity.timeunit) Frequency interval of the *Imbalance, Market, Entitlement and Actual* columns to describe the context of the indicated quantity (e.g., per DAY, MONTH or TOTAL).

Quantity status (propquantity.quantitystatus) Indicates the underlying quantity status (e.g., FORECAST, ESTIMATE or ACTUAL) of transactions that are associated with this marketing arrangement balance. Quantity status associated with a property is stored in the propquantity table.

Estimate date (propquantity.estimatedate) Indicates the last date on which daily meter estimates are recorded for quantities associated with this marketing arrangement.

Product (propquantity.product) Indicates the product marketed.

Pipeline (propquantity.pipeline) Indicates the gathering or transmission system (i.e., pipeline *Category* = GATHERING or TRANSMISSION) that is connected to the property associated with this marketing arrangement. This column is only associated with *Products* with *Product Groups* of GAS.

Point (propquantity.point) Indicates the point on the pipeline that is directly connected to the property associated with this marketing arrangement. Generally this is the initial gathering point. This column is only associated with *Products* with *Product Groups* of GAS.

Shipper Notification pane

The following columns are associated with this pane:

Shipper Notification		
Workflow		
Shipper Performance		
ShipperNotification		
Shipper	Notification	Contact
▶ Energy Corp	EMAIL	Destri Weir

Shipper (shippernotification.shipper) Indicates the company, which has contracted to transport gas through the pipeline, in order for the supplier to provide gas to the customer.

Notification (shippernotification.notification) Indicates the preferred notification method for this counterparty (e.g., MAIL, FAX, EMAIL, TELEX or VERBAL).

Contact (shippernotification.contact) Indicates the specific individual to notify.

Standard selection criteria

The following standard selection criteria are associated with this View:

- Energy unit
- Pipeline
- Point
- Shipper
- TIK owner
- Volume unit

View-specific time periods

The following standard time criteria are associated with this View:

- Beg time
- Creation date
- End time
- Estimate date
- Notification date
- Revision date
- Time Range

PART 6: EQUITY OF PACTUAL CLASS

Part 7: EquityOpActual Class


Allegro Views are organized into application classes. This part of the documentation provides information about the structure of each View associated with the EquityOpActual class of the *Equity Production* component, including View access procedure, a description of standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.

The following Views belong to this class:

- [Chapter 17, “Operator Actuals View,”](#) is used to default and adjust the best available quantity of all underlying measurements associated with the natural gas operator for the given time period.

Parameters


The following parameters are associated with this class:



- **Unit** Used to indicate the unit of measure to use in valuing the selected transactions. Use the ORIGINAL setting when you want to value using the underlying transaction’s measurement unit without restatement.

Icons

The following icons are associated with this class:



- **Default Operator Actual** When clicked in the *Operator Actuals* or *Physical Operator Actuals* view, the system defaults in the best available measurement quantities.
- **Allocate Operator Actual** When clicked, the system will attempt

to allocate the quantities captured on the measurement records to all underlying positions matching the measurement record attributes. When a successful allocation occurs for a given measurement record, the *Measure Status* column associated with that measurement record is automatically set to 'ALLOC'.

Chapter 17: Operator Actuals View


The Operator Actuals view is used to default and adjust the best available quantity of all underlying measurements associated with the natural gas operator for the given time period.

This part of the documentation provides information about the structure of the *Operator Actuals* View. The information is divided into the following sections:

- [View access procedure](#)
- [Standard panes and columns](#)
- [Standard selection criteria](#)
- [View-specific time periods](#)

View access procedure

To access the Operator Actuals view choose Navigation sidebar >> Property>> Equity Production>> Operator Actuals.



The screenshot shows two panes from a software application. The top pane is titled 'Operator actuals' and contains a table with columns: Statement, Statement date, Pipeline, Beg time, End time, Frequency, Energy unit, Volume unit, Pressure, and Alloc status. It lists four entries: ALLIANCE01011, Gulf Plains01011, Pegasus0101196, and PAUTE0101196. The bottom pane is titled 'Operator measure' and contains a table with columns: Measure, Pipeline, Point, Counterparty, Beg time, End time, Quantity, Alloc status, Unit, Time unit, Energy factor, and Carrier. It lists one entry: 111, PAUTE, 15 DELIVERY LOCATION 8/E.

Statement	Statement date	Pipeline	Beg time	End time	Frequency	Energy unit	Volume unit	Pressure	Alloc status
ALLIANCE01011	9/5/2007	ALLIANCE	1/1/1960 12:00	1/1/2040 12:00	MONTH	dth	mcf	14.730000	UNALLOC
Gulf Plains01011	9/5/2007	Gulf Plains	1/1/1960 12:00	1/1/2040 12:00	MONTH	mmbtu	mcf	14.730000	UNALLOC
Pegasus0101196	9/5/2007	Pegasus	1/1/1960 12:00	1/1/2040 12:00	MONTH	mmbtu	mcf	14.730000	UNALLOC
PAUTE0101196	9/5/2007	PAUTE	1/1/1960 12:00	1/1/2040 12:00	MONTH	dth	mcf	14.730000	UNALLOC

Measure	Pipeline	Point	Counterparty	Beg time	End time	Quantity	Alloc status	Unit	Time unit	Energy factor	Carrier
111	PAUTE	15 DELIVERY LOCATION 8/E		1/1/2007 12:00 AM	12/31/2007 12:00 AM	500.000000	☒	original	DAY	1.00000000	Ameri

Standard panes and columns


The following standard panes and columns are associated with this View. The View label name is indicated in bold; the underlying data element name is enclosed in parenthesis.

There are two panes associated with this View:

- [Operator Actuals pane](#)
- [Operator Measure pane](#)

Operator Actuals pane

The following columns are associated with this pane:



The screenshot shows the 'Operator actuals' pane with a table containing columns: Statement, Statement date, Pipeline, Beg time, End time, Frequency, Energy unit, Volume unit, Pressure, and Alloc status. The data rows are: ALLIANCE01011, Gulf Plains01011, Pegasus0101196, and PAUTE0101196.

Statement	Statement date	Pipeline	Beg time	End time	Frequency	Energy unit	Volume unit	Pressure	Alloc status
ALLIANCE01011	9/5/2007	ALLIANCE	1/1/1960 12:00	1/1/2040 12:00	MONTH	dth	mcf	14.730000	UNALLOC
Gulf Plains01011	9/5/2007	Gulf Plains	1/1/1960 12:00	1/1/2040 12:00	MONTH	mmbtu	mcf	14.730000	UNALLOC
Pegasus0101196	9/5/2007	Pegasus	1/1/1960 12:00	1/1/2040 12:00	MONTH	mmbtu	mcf	14.730000	UNALLOC
PAUTE0101196	9/5/2007	PAUTE	1/1/1960 12:00	1/1/2040 12:00	MONTH	dth	mcf	14.730000	UNALLOC

Statement (operatoractual.statement) Indicates the user-defined measurement statement number that uniquely identifies this set of operator actual measurements. If you don't enter a statement identifier, the system will assign one.

Statement date (operatoractual.statementsdate) An informational date that can be used to record when the measurement statement was recorded. The system defaults today's date upon entry.

Pipeline (operatoractual.pipeline) Indicates the gathering system (i.e., pipeline *Category* = GATHERING) that is connected to the property associated with this marketing arrangement. This column is only associated with *Products* with *Product Groups* of GAS.

Beg time (operatoractual.begtime) Indicates the beginning date and time of delivery that this operator actual statement is in effect.

End time (operatoractual.endtime) Indicates the ending date and time of delivery that this operator actual statement is in effect.

Frequency (operatoractual.frequency) Indicates the desired time interval of measurement quantities associated with this measurement statement. Choices are:

- **MONTH** Indicates that measurement quantities will be captured and allocated to positions on a monthly basis for the selected statement *Beg/End Time*.
- **DAY** Indicates that measurement quantities will be captured and allocated to positions on a daily basis for the selected statement *Beg/End Time*.
- **HOURLY** Indicates that measurement quantities will be captured and allocated to positions on an hourly basis for the selected statement *Beg/End Time*.

Energy Unit (operatoractual.energyunit) Indicates the unit of measurement in which energy quantities are expressed. This column is based on the energy unit of the pipeline and is intended for display only.

Volume Unit (operatoractual.volumeunit) Indicates the unit of measurement in which volumetric quantities are expressed. This column is based on the volume unit of the pipeline and is intended for display only.

Pressure (operatoractual.pressure) The ambient pressure expressed in pounds per square inch (psi) associated with this property.

Alloc status (operatoractual.allocstatus) Indicates the status of allocation of measurement records to underlying positions. Choices are:

- **ALLOC** Indicates that all measurements (i.e., records in *Measurement* pane) have been allocated to underlying positions (i.e., records in the *Allocation* pane).
- **UNALLOC** Indicates that all measurements (i.e., records in *Measurement* pane) have not been allocated to underlying positions (i.e., records in the *Allocation* pane).
- Only verified measurement records can be allocated. The entire statement is considered unallocated until all measurement records have been allocated to underlying positions.

Approval status (operatoractual.approvalstatus) If checked, this checkbox indicates that the operator actual measurement has been approved.

Approval date (operatoractual.approvaldate) The date the operator actual was approved.

Approval name (operatoractual.approvalname) The name of the user who approved the operator actual.

Carrier (operatoractual.carrier) Operator of physical transport services.

Operator Measure pane



Access to the Operator Measure pane requires that a statement in the Operator Actuals pane be selected first.

The following columns are associated with this pane:

Operator Actuals										
Statement	Statement date	Pipeline	Beg time	End time	Frequency	Energy unit	Volume unit	Pressure	Alloc status	
ALLIANCE01011	9/5/2007	ALLIANCE	1/1/1960 12:00	1/1/2040 12:00	MONTH	dth	mcf	14.730000	UNALLOC	
Gulf Plains01011	9/5/2007	Gulf Plains	1/1/1960 12:00	1/1/2040 12:00	MONTH	mmbtu	mcf	14.730000	UNALLOC	
Pegasus0101196	9/5/2007	Pegasus	1/1/1960 12:00	1/1/2040 12:00	MONTH	mmbtu	mcf	14.730000	UNALLOC	
PAUTE0101196	9/5/2007	PAUTE	1/1/1960 12:00	1/1/2040 12:00	MONTH	dth	mcf	14.730000	UNALLOC	

Operator measure										
Measure	Pipeline	Point	Counterparty	Beg time	End time	Quantity	Alloc status	Unit	Time unit	Energy factor
111	PAUTE	15 DELIVERY LOCATION 8/E		1/1/2007 12:00 AM	12/31/2007 12:00 AM	500.000000	☒	original	DAY	1.000000000

Measure (operatormeasure.measure) Indicates the system-generated measurement identifier associated with actual quantities.

Pipeline (operatormeasure.pipeline) Indicates the gathering or transmission system (i.e., pipeline Category = GATHERING or TRANSMISSION) that is connected to the property associated with this marketing arrangement. This column is only associated with Products with Product Groups of GAS.

Point (operatormeasure.point) Indicates the point on the pipeline that is directly connected to the property associated with this marketing arrangement. Generally this is the initial gathering point. This column is only associated with Products with Product Groups of GAS.

Counterparty (operatormeasure.counterparty) Short name identifier of the interest owner (i.e., company or entity).

Beg time (operatormeasure.begtime) Indicates the beginning date and time of delivery that this measurement is in effect.

End time (operatormeasure.endtime) Indicates the ending date and time of delivery that this measurement is in effect.

Quantity (operatormeasure.quantity) Indicates the quantity obtained when

the meter measurement was taken

Alloc status (operatormeasure.allocstatus) Indicates the status of allocation of measurement records to underlying positions. Choices are:

- **ALLOC** Indicates that all measurements (i.e., records in *Measurement* pane) have been allocated to underlying positions (i.e., records in the *Allocation* pane).
- **UNALLOC** Indicates that all measurements (i.e., records in *Measurement* pane) have not been allocated to underlying positions (i.e., records in the *Allocation* pane).
- Only verified measurement records can be allocated. The entire statement is considered unallocated until all measurement records have been allocated to underlying positions.

Unit (operatormeasure.unit) Indicates the unit of measurement in which quantities are expressed for this operator measurement.

Time unit (operatormeasure.timeunit) Indicates the time interval of measurement quantities associated with this measurement allocation. Options are: DAY, HOUR, MONTH, TOTAL, and YEAR.

Energy factor (operatormeasure.energyfactor) Indicates the factor used in deriving an energy quantity from a volumetric quantity, and vice versa.

Carrier (operatormeasure.carrier) Operator of physical transport services.

Validation (operatormeasure.validation) If a point was adjusted, a validation message appears in this column indicating that a volumn change was made. Re-default Operator Actuals to delete existing measurement records and create new records based on PPA quantity.

Standard selection criteria

The following standard selection criteria are associated with this View:

- Carrier
- Counterparty
- Location
- Pipeline

View-specific time periods

The following standard time criteria are associated with this View:

- Beg time
- End time
- Creation date
- Statement date
- Revision date
- Time range

PART 6: EQUITY PRODUCTION MEASUREMENT CLASS

Part 8: EquityProdMeasurement Class


Allegro Views are organized into application classes. This part of the documentation provides information about the structure of each View associated with the EquityProdMeasurement class of the *Equity Production* component, including View access procedure, a description of standard panes, columns, and selection criteria; as well as a description of class-specific parameters and icons.

The following Views belong to this class:

- [Chapter 18, "Gathering System Measurement"](#), is used to enter the estimated measurements obtained during meter readings.
- [Chapter 19, "Production Measurement"](#), is used to enter the estimated measurements obtained during meter readings.
- [Chapter 20, "Gathering System Actuals"](#), is used to enter and view the actual measurements.
- [Chapter 21, "Pipeline Variance"](#), is used to view the pipeline variance.
- [Chapter 22, "Production Variance"](#), is used to view the production variance.

Parameters


The following parameter is associated with this class:



- **Unit** Used to indicate the unit of measure to use in valuing the selected transactions. Use the ORIGINAL setting when you want to value using the underlying transaction's measurement unit without restatement.

Icons

The following icons are associated with this class:



- **Calculate Position** Click after entering meter measurements to

update quantities.

Chapter 18: Gathering System Measurement View


The Gathering System Measurement View is used to enter the estimated measurements obtained during meter readings.

The information is divided into the following sections:

- [View access procedure](#)
- [Standard panes and columns](#)
- [Standard selection criteria](#)
- [View-specific time periods](#)

View access procedure

To access the Gathering System Measurement View choose Navigation sidebar >> Property >> Equity Production >> Gathering System Measurement.



Meter	Beg time	End time	Meas	Quantity	Unit	Time unit	Source	Product	Measure date	Measure
103542	9/1/2007 12:00 A	9/30/2007 12:00	✓	500.000000	bbl	DAY		Mixed Sour	9/5/2007 12:00	measu
102288	9/1/2007 12:00 A	9/30/2007 12:00	✓	440.000000	bbl	DAY		OK Sweet	9/5/2007 12:00	001
101902	9/1/2007 12:00 A	9/30/2007 12:00	✓	320.000000	bbl	DAY		Mxd Sour Hardisty	9/5/2007 12:00	002
102297	9/1/2007 12:00 A	9/30/2007 12:00	✓	128.000000	bbl	DAY		Siberian Light	9/5/2007 12:0	003

Standard panes and columns


The following standard panes and columns are associated with this View. The View label name is indicated in bold; the underlying data element name is enclosed in parenthesis.

There is one pane associated with this View:

- [Metermeasure_pipeline pane](#)

Metermeasure_pipeline pane

The following columns are associated with this pane:



Meter	Beg time	End time	Meas	Quantity	Unit	Time unit	Source	Product	Measure date	Measure
103542	9/1/2007 12:00 A	9/30/2007 12:00	✓	500.000000	bbl	DAY		Mixed Sour	9/5/2007 12:00	measu
102288	9/1/2007 12:00 A	9/30/2007 12:00	✓	440.000000	bbl	DAY		OK Sweet	9/5/2007 12:00	001
101902	9/1/2007 12:00 A	9/30/2007 12:00	✓	320.000000	bbl	DAY		Mxd Sour Hardisty	9/5/2007 12:00	002
102297	9/1/2007 12:00 A	9/30/2007 12:00	✓	128.000000	bbl	DAY		Siberian Light	9/5/2007 12:0	003

Meter (metermeasure.meter) User-defined identifier associated with this

meter. Alphanumeric meter identifiers can be used.

Beg time (metermeasure.begtime) Indicates the beginning date that this measurement is in effect for this gathering system.

End time (metermeasure.endtime) Indicates the ending date that this measurement is in effect for this gathering system.

Measure status(metermeasure.measurestatus) When checked, activates the measurement record.

Quantity (metermeasure.quantity) Indicates the quantity obtained when the meter measurement was taken.

Unit (metermeasure.unit) Indicates the unit of measurement in which quantities are expressed for this meter measurement.

Time unit (metermeasure.timeunit) Indicates the time interval of measurement quantities associated with this measurement allocation. Options are: DAY, HOUR, MONTH, TOTAL, and YEAR.

Source (metermeasure.source) User defined, can be used to indicate the source of the measurement quantity.

Product (metermeasure.product) Indicates the type of product associated with the measurement

Measure date (metermeasure.measuredate) Indicates the date the measurement was entered.

Measure (metermeasure.measure) Indicates the system-generated measurement identifier that uniquely identifies this pipeline measurement record. Allegro assigns this measurement identifier when the measurement record is entered.

Disposition (metermeasure.disposition) Indicates the type of measurement performed. Disposition types are configured in the *Production Parameters* view of the Production component.

Beg meter (metermeasure.begmeter) Indicates the beginning meter reading used to determine measurement quantity.

End meter (metermeasure.endmeter) Indicates the ending beginning meter reading used to determine measurement quantity.

Meter factor (metermeasure.meterfactor) Indicates an adjustment factor used to achieve proper recorded measurements for known meter inaccuracies (i.e., 1.0 is normal).

$$\text{Net Volume} = \text{Gross Volume} \times \text{Meter Factor} \times \text{Comp Factor} * (1 - \text{BSW})$$

After saving a measurement, if you change the *Meter Factor*, the system will recalculate the *Net Volume*.

Meter factor is used when the operator knows a meter is reading improperly. By using this factor, the system can compensate for the inaccuracy.

Comp factor (metermeasure.compfactor) Indicates a compression adjustment factor used to achieve accurate recorded measurements (i.e., 1.0 is normal).

$$\text{Net Volume} = \text{Gross Volume} \times \text{Meter Factor} \times \text{Comp Factor} * (1 - \text{BSW})$$

After saving a measurement, if you change the *Comp Factor*, the system will recalculate the *Net Volume*.

Flow temp (metermeasure.flowtemp) Not used.

Flow diff (metermeasure.flowdiff) Not used.

Pressure (metermeasure.pressure) The ambient pressure expressed in pounds per square inch (psi) associated with this property.

When updating equity production positions, if the property is in a different pressure, pressureunit or saturated status than the pipeline of the point where the production volume is targeted, then Allegro converts the quantity to the pipeline's pressure and saturated status.

Pipeline (metermeasure.pipeline) Indicates the gathering system or transmission pipeline (i.e., pipeline Category = GATHERING or TRANSMISSION) that is connected to the property associated with this marketing arrangement. This column is only associated with Products with Product Groups of GAS.

Point (metermeasure.point) Indicates the point on the pipeline that is directly connected to the property associated with this marketing arrangement. Generally this is the initial gathering point. This column is only associated with *Products* with *Product Groups* of GAS.

Standard selection criteria

The following standard selection criteria are associated with this View:

- Disposition
- Meter
- Pipeline
- Product
- Time unit
- Unit

View-specific time periods

The following standard time criteria are associated with this View:

- Beg time
- End time
- Creation date
- Measure date
- Revision date
- Time range

Chapter 19: Production Measurement View

The Production Measurement view is used to enter the estimated measurements obtained during meter readings.

This part of the documentation provides information about the structure of the Production Measurement view. The information is divided into the following sections:

- [View access procedure](#)
- [Standard panes and columns](#)
- [Standard selection criteria](#)
- [View-specific time periods](#)

View access procedure

To access the Production Measurement view, choose Navigation sidebar >> Property >> Equity Production >> Production Measurement view.

Workflow Gathering System Measurement Production Measurement										
Meter measurement										
Meter	Beg time	End time	Me	Quantity	Unit	Time unit	Source	Product	Measure date	Measure
101902	1/1/2007 12:00	12/31/2007 12:0	☒	440.000000	original	DAY		AL Sour	9/5/2007 12:00	100001
102496	1/1/2007 12:00	12/31/2007 12:0	☒	320.000000	original	DAY		Arab Extra Light	9/5/2007 12:00	100002
102214	1/1/2007 12:00	12/31/2007 12:0	☒	175.000000	original	DAY		KS Sweet	9/5/2007 12:00	100003
103033	1/1/2007 12:00	12/31/2007 12:0	☒	860.000000	original	DAY		Mixed Sour	9/5/2007 12:00	100004
103543	1/1/2007 12:00	12/31/2007 12:0	☒	3,400.000000	original	DAY		Basrah Heavy	9/5/2007 12:0	100005

Standard panes and columns

The following standard panes and columns are associated with this View. The View label name is indicated in bold; the underlying data element name is enclosed in parenthesis.

There is one pane associated with this View:

- [Meter measurement](#)

Meter measurement pane



All columns on this pane are displayed only and cannot be edited.

The following columns are associated with this pane:

Workflow Gathering System Measurement Production Measurement										
Meter measurement										
Meter	Beg time	End time	Me	Quantity	Unit	Time unit	Source	Product	Measure date	Measure
101902	1/1/2007 12:00	12/31/2007 12:0	☒	440.000000	original	DAY		AL Sour	9/5/2007 12:00	100001
102496	1/1/2007 12:00	12/31/2007 12:0	☒	320.000000	original	DAY		Arab Extra Light	9/5/2007 12:00	100002
102214	1/1/2007 12:00	12/31/2007 12:0	☒	175.000000	original	DAY		KS Sweet	9/5/2007 12:00	100003
103033	1/1/2007 12:00	12/31/2007 12:0	☒	860.000000	original	DAY		Mixed Sour	9/5/2007 12:00	100004
103543	1/1/2007 12:00	12/31/2007 12:0	☒	3,400.000000	original	DAY		Basrah Heavy	9/5/2007 12:0	100005

Meter (metermeasure.meter) User-defined identifier associated with this meter. Alphanumeric meter identifiers can be used.

Beg time (metermeasure.begtime) Indicates the beginning date that this is in effect for this transmission system.

End time (metermeasure.endtime) Indicates the ending date that this measurement is in effect for this transmission system.

Measure (metermeasure.measurestatus) When checked, activates the measurement record and indicates that this measurement will be used in position calculations.

Quantity (metermeasure.quantity) Indicates the quantity obtained when the meter measurement was taken.

Unit (metermeasure.unit) Indicates the unit of measurement in which quantities are expressed for this meter measurement.

Time unit (metermeasure.timeunit) Indicates the time interval of measurement quantities associated with this measurement allocation. Options are: DAY, HOUR, MONTH, TOTAL, and YEAR.

Source (metermeasure.source) Indicates the source used to determine measurement quantity

Product (metermeasure.product) Indicates the type of product associated with the measurement

Measure date (metermeasure.measuredate) Indicates the date the measurement took place

Measure (metermeasure.measure) Indicates the system-generated measurement identifier that uniquely identifies this pipeline measurement record. Allegro assigns this measurement identifier when the measurement record is entered.

Disposition (metermeasure.disposition) Indicates the type of measurement performed. Disposition types are configured in the *Production Parameters* view of the Production component.

Beg meter (metermeasure.begmeter) Indicates the beginning meter reading used to determine measurement quantity.

End meter (metermeasure.endmeter) Indicates the ending meter reading used to determine measurement quantity.

Meter factor (metermeasure.meterfactor) Indicates an adjustment factor used to achieve proper recorded measurements for known meter inaccuracies (i.e., 1.0 is normal).

$$\text{Net Volume} = \text{Gross Volume} \times \text{Meter Factor} \times \text{Comp Factor} * (1 - \text{BSW})$$

After saving a measurement, if you change the *Meter Factor*, the system will recalculate the *Net Volume*.

Meter factor is used when the operator knows a meter is reading improperly. By using this factor, the system can compensate for the inaccuracy.

Comp factor (metermeasure.compfactor) Indicates a compression adjustment factor used to achieve accurate recorded measurements (i.e., 1.0 is normal).

$$\text{Net Volume} = \text{Gross Volume} \times \text{Meter Factor} \times \text{Comp Factor} * (1 - \text{BSW})$$

After saving a measurement, if you change the *Comp Factor*, the system will recalculate the *Net Volume*.

Flow temp (metermeasure.flowtemp) Not used.

Flow diff (metermeasure.flowdiff) Not used.

Pressure (metermeasure.pressure) The ambient pressure expressed in pounds per square inch (psi) associated with this property.

When updating equity production positions, if the property is in a different pressure, pressureunit or saturated status than the pipeline of the point where the production volume is targeted, then Allegro converts the quantity to the pipeline's pressure and saturated status.

Property (metermeasure.property) User-defined identifier that describes the boundary dividing tracts on which mineral rights, royalty or leases are separately owned. (Defined in Navigation sidebar>>Logistics>>Natural Gas>>Natural Gas Pipelines>>Property tab).

Pipeline Indicates the short pipeline identifier associated with this production forecast. A pipeline can represent a gathering system, interstate/intrastate pipeline or distribution facility.

Standard selection criteria

The following standard selection criteria are associated with this View:

- None

View-specific time periods

The following standard time criteria are associated with this View:

- Beg time
- End time
- Creation date
- Measure date
- Revision date
- Time range

Chapter 20: Gathering System Actuals View

The Gathering System Actuals view is used to enter and view the actual measurements.

This part of the documentation provides information about the structure of the *Gathering System Actuals* view. The information is divided into the following sections:

- [View access procedure](#)
- [Standard panes and columns](#)
- [Standard selection criteria](#)
- [View-specific time periods](#)

View access procedure

To access the Gathering System Actuals view choose Navigation sidebar >> Property >> Equity Production>> Gathering System Actuals view.

Gathering System Actuals Workflow											
Actuals											
Statement	Pipeline	Statement date	Beg time	End time	Actual status	Alloc status	Frequency	Volume unit	Energy unit	Pressure	
Big Lake	Big Lake	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	14.730000	
NTS	NTS	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	14.730000	
Pegasus	Pegasus	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	14.730000	
▶ Walton	Walton	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	▼ 14.730000	

Standard panes and columns

The following standard panes and columns are associated with this View. The View label name is indicated in bold; the underlying data element name is enclosed in parenthesis.

There are two panes associated with this view:

- [Actuals pane](#)
- [Measurement pane](#)

Actuals pane

The following columns are associated with this pane:

Gathering System Actuals		Workflow									
Actuals											
Statement	Pipeline	Statement date	Beg time	End time	Actual status	Alloc status	Frequency	Volume unit	Energy unit	Pressure	
Big Lake	Big Lake	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	14.730000	
NTS	NTS	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	14.730000	
Pegasus	Pegasus	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	14.730000	
▶ Walton	Walton	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	14.730000	

Statement (ngactual.statement) Indicates the user-defined measurement statement number that uniquely identifies this set of operator actual measurements. If you don't enter a statement identifier, the system will assign one.

Pipeline (ngactual.pipeline) Indicates the gathering system (i.e., pipeline *Category* = GATHERING) that is connected to the property associated with this marketing arrangement. This column is only associated with *Products* with *Product Groups* of GAS.

Statement date (ngactual.statementdate) An informational date that can be used to record when the measurement statement was recorded. The system defaults today's date upon entry.

Beg time (ngactual.begtime) Indicates the beginning date and time of delivery that this gathering system actual statement is in effect.

End time (ngactual.endtime) Indicates the ending date and time of delivery that this gathering system actual statement is in effect.

Actual status (ngactual.actualstatus) Indicates the desired quantity status to be assigned to positions associated with this measurement statement. Choices are:

- **ESTIMATE** Indicates that positions that have measurement quantities allocated to them are assigned a Quantity Status of ESTIMATE. This can be used to optionally assign a more reliable quantity to positions prior to final actual measurements. It is generally used to support the financial accrual process.
- **ACTUAL** Indicates that positions that have measurement quantities allocated to them are assigned a *Quantity Status* of ACTUAL and that they represent final actual measurements. It is generally used to support the settlement process.

Alloc status (ngactual.allocstatus) Indicates the status of allocation of measurement records to underlying positions. Choices are:

- **ALLOC** Indicates that all measurements (i.e., records in *Measurement* pane) have been allocated to underlying positions (i.e., records in the *Allocation* pane).
- **UNALLOC** Indicates that all measurements (i.e., records in *Measurement* pane) have not been allocated to underlying positions (i.e., records in the *Allocation* pane).

- Only verified measurement records can be allocated. The entire statement is considered unallocated until all measurement records have been allocated to underlying positions.

Frequency (ngactual.frequency) Indicates the desired time interval of measurement quantities associated with this measurement statement. Choices are:

- MONTH Indicates that measurement quantities will be captured and allocated to positions on a monthly basis for the selected statement *Beg/End Time*.
- DAY Indicates that measurement quantities will be captured and allocated to positions on a daily basis for the selected statement *Beg/End Time*.
- HOUR Indicates that measurement quantities will be captured and allocated to positions on an hourly basis for the selected statement *Beg/End Time*.

Energy unit (ngactual.energyunit) Indicates the unit of measurement in which energy quantities are expressed. This column is based on the energy unit of the pipeline and is intended for display only.

Volume Unit (ngactual.volumeunit) Indicates the unit of measurement in which volumetric quantities are expressed. This column is based on the volume unit of the pipeline and is intended for display only.

Pressure (ngactual.pressure) The ambient pressure expressed in pounds per square inch (psi) associated with this property.



Measurement Pane

Access to the Measurements pane requires that a statement in the Actuals pane be selected first.

The following columns are associated with this pane:

Gathering System Actuals Workflow												
Actuals												
Statement	Pipeline	Statement date	Beg time	End time	Actual status	Alloc status	Frequency	Volume unit	Energy unit	Pressure	Creation name	Creation i
Big Lake	Big Lake	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	14.730000	Destri Weir	9/4/2007
NTS	NTS	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	14.730000	Destri Weir	9/5/2007
Pegasus	Pegasus	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	14.730000	Destri Weir	9/5/2007
Walton	Walton	9/4/2007	1/1/1960 12:00 AM	1/1/2040 12:00 AM	ACTUAL	UNALLOC	DAY	mcf	mmbtu	14.730000	Destri Weir	9/5/2007

Measurement										
Measure	Beg time	End time	Pipeline	Point	Measure type	Measure status	Rec energy	Loss energy	Del energy	Imbal
00001	1/1/2007 12:00	12/31/2007 12:0	NTS	NBP	ADJUSTMENT	NEW	500.0000	2.0000	498.0000	

Measure (ngmeasure.measure) Indicates the system-generated measurement identifier that uniquely identifies this pipeline measurement record. Allegro assigns this measurement identifier when the measurement record is entered.

Separate measurement identifiers and rows are generated for common groupings of *Pipeline*, *Point*, *Beg/End Time* (driven by *Frequency* of HOUR, DAY or MONTH), *Measure Type*, *Service*, *Pipeline Contract*, *Shipper Account* and *Stream Contract*.

Beg time (ngmeasure.begtime) Beginning date and time of the effective delivery period for quantities associated with this measurement record.

End time (ngmeasure.endtime) Ending date and time of the effective delivery period for quantities associated with this measurement record.

Pipeline (ngmeasure.pipeline) Indicates the short pipeline identifier associated with this measurement reading. A pipeline can represent a gathering system, interstate/intrastate pipeline. The Allegro Retail component is used to apply actual quantities to distribution facilities.

Point (ngmeasure.point) Indicates the short identifier of the geographic location on the pipeline associated with this measurement record.

Measure type (ngmeasure.measuretype) Indicates the type of positions associated with this measurement record. Options are:

- **RECEIPT** Indicates that the measurement record is associated with long positions (e.g., purchase trades).
- **DELIVERY** Indicates that the measurement record is associated with short positions (e.g., sales trades).
- **IMBALANCE** Indicates that this measurement record is associated with an imbalance position. Imbalance measurement records are generated when the *Calculate Imbalance* icon is invoked. They are generated based on the imbalance policy records established in the *Imbalance Contracts* pane of the

Natural Gas Service view.

- **ADJUSTMENT** Used in conjunction with the *Acct Date* parameter (i.e., Parameters sidebar >> Acct Date) and the *Adjustment* checkbox, to automatically generate measurement adjustments records.

When a measurement quantity on the *Measurement* pane is adjusted and the *Adjustment* column is checked, upon saving the record the system will automatically generate a new measurement record with the quantity equal to the difference between the original measurement and the updated quantity. In addition, the new measurement record will have a *Beg/End Time* set to the date range indicated by the *Acct Date* parameter. The *Flow Beg/End* columns will also be set to the *Beg/End Time* of the original measure record. The original measure record will not be affected. The adjustment record can be displayed in the time period associated with the measure *Beg/End Time* columns which will correlate to the *Acct Date* parameter. The new adjustment measure acts similar to other measure records except that when allocating actual quantities, the system will allocate positions that are associated with the *Flow Beg/End* columns instead of the *Beg/End Time* columns.

Measure status (ngmeasure.measurestatus) A system-assigned identifier that indicates the approval status of this measurement record. Options are:

- **NEW** Assigned to the measurement record upon default when invoking the Default Actual Quantities icon.
- **REVISED** This status indicates that the measurement has been adjusted and is ready to be verified. It is assigned to the measurement record when Rec/Loss/Del Energy/Volume quantities are overridden.
- **VERIF** This status indicates that the measurement has been approved and ready to be allocated to underlying positions. It is assigned to the measurement record when the Verify All icon is invoked or the Verify Status column is checked. The Verify All icon is used to automatically check each Verify Status column on the selected statement.
- **APPROV** Not used.
- **ALLOC** This status indicates that the measurement has been allocated to underlying positions. It is assigned to the measurement record when invoking the *Allocate Actual Quantities* process.

Rec energy (ngmeasure.recenergy) Indicates the measured energy quantity for all receipts associated with the associated underlying positions (i.e., long positions).

Loss energy (ngmeasure.lossenergy) Indicates the measured energy quantity of losses incurred when moving receipt energy quantities to delivery.

Del energy (ngmeasure.delenergy) Indicates the measured energy quantity for all

deliveries associated with the associated underlying positions (i.e., short positions).

Imbalance energy (.imbalanceenergy) A calculated energy quantity which represents the difference between the receipts and deliveries (considering losses) associated with this measurement. Imbalance energy is calculated as follows:

$$\text{Imbalance Energy} = \text{Rec Energy} - \text{Loss Energy} - \text{Del Energy}$$

Rec volume (ngmeasure.recvolume) Indicates the measured volumetric quantity for all receipts associated with the associated underlying positions (i.e., long positions).

Loss volume (ngmeasure.lossvolume) Indicates the measured volumetric quantity of losses incurred when moving receipt volumetric quantities to delivery.

Del volume (ngmeasure.delvolume) Indicates the measured volumetric quantity for all deliveries associated with the associated underlying positions (i.e., short positions).

Imbalance volume (.imbalancevolume) A calculated volumetric quantity which represents the difference between the receipts and deliveries (considering losses) associated with this measurement. Imbalance volume is calculated as follows:

$$\text{Imbalance Volume} = \text{Rec Volume} - \text{Loss Volume} - \text{Del Volume}$$

Energy factor (ngmeasure.energyfactor) Indicates the default factor used in deriving an energy quantity from a volumetric quantity for this measurement, and vice versa. It can be overridden to the actual energy factor of the measured quantities.

The result of dividing an energy factor into an energy quantity results in the volume quantity. The product of a volume quantity and an energy factor represents the energy quantity.

Contract (ngmeasure.contract) Indicates the contract in effect governing the settlement terms and conditions associated with underlying positions associated with this measurement.

Shipper account (ngmeasure.shipperaccount) Indicates the specific account that the selected pipeline has with the shipper for nonpathed pipeline nominations associated with this measurement.

Service (ngmeasure.service) Indicates the transportation service used to nominate gas related to underlying positions associated with this measurement.

Pipeline contract (ngmeasure.pipelinecontract) Indicates the pipeline contract used for transportation service in nominating gas related to underlying positions associated with this measurement.

Adjustment checkbox (.adjustment) Used in conjunction with the *Acct Date* parameter (i.e., Parameters sidebar >> Acct Date) to automatically generate measurement adjustments records (i.e., *Measure Type* of ADJUSTMENT records).

When a measurement quantity on the *Measurement* pane is adjusted and the *Adjustment* column is checked, upon saving the record the system will automatically generate a new measurement record with the quantity equal to the difference between the original measurement and the updated quantity. In addition, the new measurement record will have a *Beg/End Time* set to the date range indicated by the *Acct Date* parameter. The *Flow Beg/End Time* columns will also be set to the *Beg/End Time* of the original measure record. The original measure record will not be affected. The adjustment record can be displayed in the time period associated with the measure *Beg/End Time* columns which will correlate to the *Acct Date* parameter. The new adjustment measure acts similar to other measure records except that when using the *Allocate Actual Quantities* process, the system will allocate positions that are associated with the *Flow Beg/End* columns instead of the *Beg/End Time* columns.

Flow beg time (ngmeasure.flowbegtime) Indicates the beginning time of the delivery period associated with a measurement adjustment record. The *Flow Beg Time* column is used in conjunction with the *Acct Date* parameter (i.e., Parameters sidebar >> Acct Date) and the *Adjustment* column to automatically generate measurement adjustments records (i.e., *Measure Type* of ADJUSTMENT records).

When a measurement quantity on the *Measurement* pane is adjusted and the *Adjustment* column is checked, upon saving the record the system will automatically generate a new measurement record with the quantity equal to the difference between the original measurement and the updated quantity. In addition, the new measurement record will have its *Beg/End Time* set to the date range indicated by the *Acct Date* parameter. The *Flow Beg Time* column will also be set to the *Beg Time* column of the original measure record. The new adjustment measure acts similar to other measure records except that when using the *Allocate Actual Quantities* process, the system will allocate positions that are associated with the *Flow Beg/End Time* columns instead of the *Beg/End Time* columns.

Flow end time (ngmeasure.flowendtime) Indicates the ending time of the delivery period associated with a measurement adjustment record. The *Flow End Time* column is used in conjunction with the *Acct Date* parameter (i.e., Parameters sidebar >> Acct Date) and the *Adjustment* column to automatically generate measurement adjustments records (i.e., *Measure Type* of ADJUSTMENT records).

When a measurement quantity on the *Measurement* pane is adjusted and the *Adjustment* column is checked, upon saving the record the system will automatically generate a new measurement record with the quantity equal to the difference between the original measurement and the updated quantity. In addition, the new

measurement record will have its *Beg/End Time* set to the date range indicated by the *Acct Date* parameter. The *Flow End Time* column will also be set to the *End Time* column of the original measure record. The new adjustment measure acts similar to other measure records except that when using the allocating actual quantities, the system will allocate positions that are associated with the *Flow Beg/End Time* columns instead of the *Beg/End Time* columns.

Counterparty (ngmeasure.counterparty) The company which holds the opposite side of positions associated with this measurement.

Verif status checkbox (ngmeasure.verifstatus) If checked, indicates that the measurement record has been approved and is ready to be allocated to underlying positions.

The *Verify All* icon can be used to automatically check each *Verify Status* column on the selected statement.

Verif name (ngmeasure.verifname) Used in conjunction with the *Verif Status* column to indicate the user name of the individual that approved the measurement record. When the *Verify Status* column is checked, the system assigned the user's name to this column.

Verif date (ngmeasure.verifdate) Used in conjunction with the *Verif Status* column to indicate the date that the measurement record was approved. When the *Verify Status* column is checked, the system assigns today's date to this column.

Volume unit (ngmeasure.volumeunit) Indicates the unit of measurement in which volumetric quantities are expressed. This column is based on the volume unit of the pipeline and is intended for display only.

Energy unit (ngmeasure.energyunit) Indicates the unit of measurement in which energy quantities are expressed. This column is based on the energy unit of the pipeline and is intended for display only.

Stream contract (ngmeasure.streamcontract) Indicates the up or down stream transportation contract associated with this measurement record. The up or down stream contract is obtained from the physical natural gas trade (i.e., *Stream Contract* column from the *Natural Gas* pane of the *Trades* view).

Stream package (ngmeasure.streampackage) Not used.

Stream rank (ngmeasure.streamrank) Not used.

Activity (ngmeasure.activity) Not used.

Package (ngmeasure.package) Not used.

Imbalance energy diff (.imbalanceenergydiff) Works in conjunction with

measurement records with *Measure Type* of IMBALANCE to represent the difference between the system calculated imbalance energy quantity and any imbalance energy quantity updates entered manually into the *Rec Energy* or *Del Energy* columns on the imbalance row. For example, if the imbalance is calculated at 10 and a user updates the imbalance to 9, then the imbalance difference is 1.

The system calculated imbalance quantity is based on imbalance rules expressed in the *Imbalance Contracts* pane of the *Natural Gas Service* view

Imbalance volume diff (.imbalancevolumediff) Works in conjunction with measurement records with *Measure Type* of IMBALANCE to represent the difference between the system calculated imbalance volumetric quantity and any imbalance volumetric quantity updates entered manually into the *Rec Volume* or *Del Volume* columns on the imbalance row. For example, if the imbalance is calculated at 10 and a user updates the imbalance to 9, then the imbalance difference is 1.

The system calculated imbalance quantity is based on imbalance rules expressed in the *Imbalance Contracts* pane of the *Natural Gas Service* view

Stream code (ngmeasure.streamcode) Not used.

Standard selection criteria

The following standard selection criteria are associated with this View:

- Counterparty
- Loss type
- Pipeline
- Pipeline contract
- Point
- Price index
- Service
- Trade book
- Trade status
- Zone

View-specific time periods



When processing actual transactions using the *Default Gathering Actuals, Calculate Imbalance Volumes* or *Create Imbalance Trades* icon, be sure to only use the *Time Range* option below. Most of the time criteria listed below are used for searching records and are not intended for use with record creation.

The following standard time criteria are associated with this View:

- Beg time
- Creation date
- End time
- Flow beg time
- Flow end time
- Revision date
- Statement date
- Time range
- Verif date

Chapter 21: Pipeline Variance View

The Pipeline Variance view is used to the pipeline variance.

This part of the documentation provides information about the structure of the *Pipeline Variance* view. The information is divided into the following sections:

- [View access procedure](#)
- [Standard panes and columns](#)
- [Standard selection criteria](#)
- [View-specific time periods](#)

View access procedure

To access the Pipeline Variance view choose Navigation sidebar >>Property >> Equity Production>>Pipeline Variance.

Workflow Production Variance Pipeline Variance													
Pipeline_variance													
Group description	Product	Property	Meter	Estimate	Actual	Estimate/Actual	Variance	Pipeline	Point	Unit	Beg time	End time	
Bayou Chauvin				0	2,500		2,500			Bayou Chauvin	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Chauvin 3-2	101938	0	833		833			Bayou Chauvin	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Chauvin 3-3	102637	0	833		833			Bayou Chauvin	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Chauvin 4-6	103224	0	833		833			Bayou Chauvin	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
Bayou Copasaw				0	1,000		1,000			Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 11-3	101940	0	250		250			Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 11-4	102639	0	250		250			Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 11-5	102995	0	250		250			Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 12-7	103225	0	250		250			Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
Bayou Jean Lacroix				0	1,500		1,500			Bayou Jean Lacroix	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Jean Lacroix 13-4	101942	0	750		750			Bayou Jean Lacroix	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Jean Lacroix 13-6	102996	0	750		750			Bayou Jean Lacroix	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM

Standard panes and columns

The following standard panes and columns are associated with this View. The View label name is indicated in bold; the underlying data element name is enclosed in parenthesis.

There is one pane associated with this View:

- [Pipeline_variance pane](#)

Pipeline_variance pane



All columns on this pane are displayed only and cannot be edited.

The following columns are associated with this pane:

Workflow Production Variance Pipeline Variance												
Pipeline_variance												
Group description	Product	Property	Meter	Estimate	Actual	Estimate/Actual	Variance	Pipeline	Point	Unit	Beg time	End time
Bayou Chauvin		Bayou Chauvin 3-2	101938	0	2,500		2,500		Bayou Chauvin	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Chauvin 3-3	102637	0	833		833		Bayou Chauvin	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Chauvin 4-6	103224	0	833		833		Bayou Chauvin	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
Bayou Copasaw				0	1,000		1,000		Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 11-3	101940	0	250		250		Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 11-4	102639	0	250		250		Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 11-5	102995	0	250		250		Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Copasaw 12-7	103225	0	250		250		Bayou Copasaw	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
Bayou Jean Lacroix				0	1,500		1,500		Bayou Jean Lacroix	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Jean Lacroix 13-4	101942	0	750		750		Bayou Jean Lacroix	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM
		Bayou Jean Lacroix 13-6	102996	0	750		750		Bayou Jean Lacroix	dth	12/1/2007 12:00 AM	12/15/2007 12:00 AM

Group description (.groupdesc) The identifier associated with the drill down hierarchy. The context of this column depends on the hierarchical level that is being evaluated.

Product (.product) Indicates the type of product associated with the measurement.

Property (.property) User-defined identifier that describes the boundary dividing tracts on which mineral rights, royalty or leases are separately owned. (Defined in Navigation sidebar>>Logistics>>Natural Gas>>Natural Gas Pipelines>>Property tab)

Meter (.meter) User-defined identifier associated with this meter. Alphanumeric meter identifiers can be used.

Estimate (.estimate) Indicates the estimated actual quantity

Actual (.actual) Indicates the best available quantity

Estimate/Actual Variance (.variance) Indicates the difference between the estimated quantity and the actual quantity

Pipeline (.pipeline) Indicates the gathering system or transmission (i.e., pipeline Category = GATHERING or TRANSMISSION) that is connected to the property associated with this marketing arrangement. This column is only associated with *Products* with *Product Groups* of GAS.

Point (.point) Indicates the point on the pipeline that is directly connected to the property associated with this marketing arrangement. Generally this is the initial gathering point. This column is only associated with *Products* with *Product Groups* of GAS.

Unit (.unit) Indicates the unit of measurement in which quantities are expressed.

Begtime (.begtime) Indicates the beginning date the variance is in effect.

Endtime (.endtime) Indicates the ending date the variance is in effect.

Standard selection criteria

The following standard selection criteria are associated with this View:

- Pipeline

View-specific time periods

The following standard time criteria are associated with this View:

- Time range

Chapter 22: Production Variance View

The Production Variance view is used to view the production variance.

This part of the documentation provides information about the structure of the *Production Variance* view. The information is divided into the following sections:

- [View access procedure](#)
- [Standard panes and columns](#)
- [Standard selection criteria](#)
- [View-specific time periods](#)

View access procedure

To access the Production Variance view choose Navigation sidebar >> Property >> Equity Production>> Production Variance.

Workflow Production Variance											
Production_variance											
Operator	Product	Property	Meter	Forecast	Estimate	Forecast/Estimate	Variance	Unit	Measure date	Beg time	End time
Century Petroleum	NG	Andrews South 2-4	101912	219,246	0		219,246	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Andrews South 4-10	103397	230,153	0		230,153	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Bagley North 6-3	101928	321,957	0		321,957	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Bagley North 6-4	102631	335,082	0		335,082	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Bayou Penchant 7-4	101945	232,898	0		232,898	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Bayou Penchant 7-5	102642	243,354	0		243,354	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Blue Buck Pont 2-2	101962	247,634	0		247,634	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Blue Buck Pont 2-3	102651	260,252	0		260,252	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Blue Buck Pont 3-6	103233	272,930	0		272,930	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Bunchs Creek 13-5	101970	233,025	0		233,025	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Caprock East 4-4	101976	128,514	0		128,514	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Caprock East 4-5	102658	138,709	0		138,709	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM
Century Petroleum	NG	Caprock East 5-8	103237	149,006	0		149,006	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM

Standard panes and columns

The following standard panes and columns are associated with this View. The View label name is indicated in bold; the underlying data element name is enclosed in parenthesis.

There is one pane associated with this View:

- [Production variance](#)

Production_variance pane



All columns on this pane are displayed only and cannot be edited.

The following columns are associated with this pane:

Production Variance											
Production_variance											
Operator	Product	Property	Meter	Forecast	Estimate	Forecast/Estimate	Variance	Unit	Measure date	Beg time	End time
Century Petroleum	NG	Andrews South 2-4	101912	219,246	0	219,246	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Andrews South 4-10	103397	230,153	0	230,153	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Bagley North 6-3	101928	321,957	0	321,957	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Bagley North 6-4	102631	335,082	0	335,082	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Bayou Penchant 7-4	101945	232,898	0	232,898	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Bayou Penchant 7-5	102642	243,354	0	243,354	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Blue Buck Pont 2-2	101962	247,634	0	247,634	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Blue Buck Pont 2-3	102651	260,252	0	260,252	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Blue Buck Pont 3-6	103233	272,930	0	272,930	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Bunchs Creek 13-5	101970	233,025	0	233,025	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Caprock East 4-4	101976	128,514	0	128,514	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Caprock East 4-5	102658	138,709	0	138,709	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	
Century Petroleum	NG	Caprock East 5-8	103237	149,006	0	149,006	original		12/1/2007 12:00 AM	1/1/2008 12:00 AM	

Operator (property.operator) Indicates the operator of the property.

Product (.product) Indicates the type of product associated with the measurement

Property (property.property) User-defined identifier that describes the boundary dividing tracts on which mineral rights, royalty or leases are separately owned.

Meter (.meter) User-defined identifier associated with this property. Alphanumeric meter identifiers can be used.

Forecast (.forecast) Indicates the forecast quantity.

Estimate (.estimate) Indicates the estimated measurement quantity

Forecast/Estimate Variance (.variance) Indicates the difference between the forecast and the estimated quantity.

Unit (.unit) Indicates the unit of measurement in which quantities are expressed

Measure date (.measuredate) Indicates the date the measurement took place

Beg time (.begtime) Indicates the beginning date that this variance is in effect.

End time (.endtime) Indicates the ending date that this variance is in effect.

Standard selection criteria

The following standard selection criteria are associated with this View:

- Operator

View-specific time periods

The following standard time criteria are associated with this View:

- Time range

Glossary

BBL (abbreviation for barrel) A unit of measurement commonly used in quoting liquid hydrocarbon volumes. 1 barrel = 42 US gallons = 35 imperial gallons (approx) = 159 liters (approx).

Carrier The company that transports goods from one point to another. May be a vessel, airline, trucking company, or railroad.

Control Area For physical power transactions refers to the electric system or systems, bounded by interconnection metering and telemetry, capable of controlling generation to maintain its interchange schedule with other Control Areas and contributing to frequency regulation of the Interconnection, where the commodity was bought, sold or exchanged and involved in any quantity scheduling or measurement activity regarding this transaction.

Counterparty The opposite party in a bilateral agreement, contract, or transaction.

Current price The price that is quoted for settlement (payment and delivery) of the transaction immediately.

Drill down hierarchy Refers to the ability to move from summary information to detailed data by focusing in on something. To drill down through a series of levels, for example, on a desktop means to go through the hierarchy of folders to find a specific file or to click through drop-down menus in a GUI. To drill down through a database is to access information by starting with a general category and moving through the hierarchy to a specific record.

Forward curve In a forward market, the pattern of forward prices over various time horizons.

Forward price The price at which a commodity may be transacted (bought/sold) now but with settlement to occur at a given future date.

HTML Hypertext Markup Language is the coded format language used for creating hypertext documents on the World Wide Web and controlling how Web pages appear.

Icon A control that appears on the screen as a small graphic image. When the user clicks an icon, the application performs the action described by the icon's title. Icon actions are usually performed instantaneously.

Pane A portion of a View used to present information.

PDF Acronym for Portable Document Format, the PDF file format created by Adobe Systems, Inc. uses the PostScript printer description language and is highly portable across computer platforms. PDF documents are created with Adobe Acrobat or other programs and can be viewed with Adobe Acrobat Reader and other PDF reader programs.

Physical logistics Physical logistics covers all activities relating to the transport (e.g., truck, rail, pipeline, vessel, etc.) and storage of commodities.

Price index An index that tracks price records over time for a publicly traded commodity or company-specific purpose.

Sourcing The process of obtaining supply in order to deliver final product to our markets.

System Administrator The person that is charged with the overall administration, and operation of a computer system. The System Administrator is generally an employee or a member of the company that uses the system.

Table A set of data elements that has a horizontal dimension (rows) and a vertical dimension (columns) in a relational database system. A table has a specified number of columns but can have any number of rows. A table is often called a relation. Rows stored in a table are structurally equivalent to records from flat files in that they must not contain repeating columns.

Transmission The movement or transfer of electric energy over an interconnected group of lines and associated equipment between points of supply and points at which it is transformed for delivery to consumers, or is delivered to other electric systems. Transmission is considered to end when the energy is transformed for distribution to the consumer.

View An area on the screen organized to enter and display information. The user can open or close a view; move it around on the desktop; and sometimes change its size, scroll through it, edit its contents, print it, and download the contents of it.

Web service A web service is a self-describing, self-contained, modular unit of application logic that provides business functionality to an application using standard Internet protocols. Applications access web services via ubiquitous web protocols and data formats, such as HTTP and XML, with no need to worry about how each web service is implemented. Web services can be mixed and matched with other web services to execute a larger workflow or business transaction.

XML Extensible Markup Language is a flexible way to create common information formats and share both the format and the data on the World Wide Web, intranets, and elsewhere. XML is similar to the language of today's Web pages, the Hypertext Markup Language (HTML). Both XML and HTML contain markup symbols to describe the contents of a page or file.

Documentation Comment Form

Allegro Equity Production Component User's Guide

July 2011

We welcome your comments and suggestions regarding the quality and usefulness of this manual. Your comments help us improve the documentation to better meet your needs.

- Did you find any errors?
- Is the information clearly presented?
- Are the examples correct? Do you need more examples?
- What features do you like most (and least) about the manual?

If you find errors or have specific suggestions, please note the topic, chapter and page number.

Send your comments using any of the following methods:

E-mail	doc@allegrodev.com
Fax	214-237-8000. (On the cover sheet, specify that the fax should be routed to the doc@allegrodev.com e-mail address.)
Conventional mail	Documentation Manager Allegro Development 1445 Ross Ave, Suite 2200, Dallas, TX 75202

Thank you for taking the time to help us improve our documentation.