


DEPLOYMENTS TO STANDALONE MULE RUNTIME

* Download mule standalone


* Download Java 11 or 17


Set env variable in computer (java)

>> go to search and type env variable




>> Click on top new. And bottom as well. (user and system variables)







Click on path > new



Paste java bin path



>> To start mule, go to mule standloane folder > bin > click on last mule



>> it will open command prompt.

```
+++++
+ Mule is up and kicking (every 5000ms) +
+++++

*****
*          - - + DOMAIN + - -          * - - + STATUS + - - *
*****
* default                                * DEPLOYED *
*****
```

To run any project in this mule standalone.

Go to mule studio and export project as jar file and copy this file and go to mule standalone folder > apps > paste the jar file.

>> it will automatically will be seen in command prompt and it will extract it and run.

>> it will create anchor file in apps folder

```
+++++
+ New app 'firstapp' +
+++++

+++++
+ Initializing app 'firstapp' +
+++++

+++++
+ Starting app 'firstapp' +
+++++

*****
* Started app 'firstapp' *
* Application plugins: *
* - Sockets : 1.2.3 *
* - HTTP : 1.8.0 *
*****
```

Undeploy the application:

Delete the anchor file. It will delete

```
*****
* Started app 'firstapp' *
* Application plugins: *
* - Sockets : 1.2.3 *
* - HTTP : 1.8.0 *
*****

+++++
+ Disposing application 'firstapp' +
+++++

+++++
+ Undeployed artifact 'firstapp' +
+++++
```

To run as a windows service:

Go to bin folder > type cmd on path

This PC > Downloads > softwares > mule distribution-standalone-4.9.4 > mule-enterprise-standalone-4.9.4 > bin

Name	Date modified	Type	Size
amc_debug	4/3/2025 10:02 PM	File	6 KB
amc_setup	4/3/2025 10:24 PM	File	4 KB
amc_setup	4/3/2025 10:24 PM	Windows Batch File	2 KB
launcher	4/30/2025 8:12 PM	File	1 KB
launcher	4/30/2025 8:12 PM	Windows Batch File	4 KB
mule	4/30/2025 8:12 PM	File	120 KB
mule	4/30/2025 8:12 PM	Windows Batch File	6 KB

```
C:\Windows\System32\cmd.exe
Microsoft Windows [Version 10.0.19045.5796]
(c) Microsoft Corporation. All rights reserved.

C:\Users\krazy\Downloads\softwares\mule distribution-standalone-4.9.4\mule-enterprise-standalone-4.9.4\bin>
```

>> Type mule install. It will install mule enterprise edition

```
C:\Users\krazy\Downloads\softwares\mule distribution-standalone-4.9.4\mule-enterprise-standalone-4.9.4\bin>mule install
MULE_HOME is set to C:\Users\krazy\Downloads\softwares\mule distribution-standalone-4.9.4\mule-enterprise-standalone-4.9.4
MULE_BASE is set to C:\Users\krazy\Downloads\softwares\mule distribution-standalone-4.9.4\mule-enterprise-standalone-4.9.4
Found JAVA_HOME = C:\Program Files\Java\jdk-17
Mule Enterprise Edition service installed.

C:\Users\krazy\Downloads\softwares\mule distribution-standalone-4.9.4\mule-enterprise-standalone-4.9.4\bin>
```

>> Type mule start

```
C:\Users\krazy\Downloads\softwares\mule distribution-standalone-4.9.4\mule-enterprise-standalone-4.9.4\bin>mule start
MULE_HOME is set to C:\Users\krazy\Downloads\softwares\mule distribution-standalone-4.9.4\mule-enterprise-standalone-4.9.4
MULE_BASE is set to C:\Users\krazy\Downloads\softwares\mule distribution-standalone-4.9.4\mule-enterprise-standalone-4.9.4
Found JAVA_HOME = C:\Program Files\Java\jdk-17
Starting the Mule Enterprise Edition service...
Waiting to start...
Waiting to start...
Waiting to start...
Mule Enterprise Edition service started.

C:\Users\krazy\Downloads\softwares\mule distribution-standalone-4.9.4\mule-enterprise-standalone-4.9.4\bin>
```

>> To stop the service, type mule stop

To delete mule service, type mule remove