

Admin Onboarding — Stand Up a New Facility

RinkReports · Version 5-6 · for `super_admin` / `org_admin` / `facility_manager`

This is the guided first-day path for getting a brand-new rink live in RinkReports. Work top to bottom: each step builds on the one before it, and the early steps unlock the later screens. Links jump into the full module chapters where the detail lives.

Role note (⚠ VERIFY — permission-driven, not title-driven). RinkReports has no `org_admin` tier in the live app — treat any `org_admin` step as **super_admin**. Most setup below is a **facility_manager** (`admin`) task, but a few steps are **super_admin-only** and are flagged ⚠ **super_admin only**. Access is resolved per module/action, so confirm any "who can do this" claim against your configured facility. See **How RinkReports is organized**.

Everything you configure applies to your facility only — this is automatic. See the **Admin Control Center** chapter for the full back-office reference.

Phase 1 — Create the facility and its core configuration

- ☐ ⚠ **super_admin only — Create the facility.** In **Admin Center** → **Facility**, click **New Facility** and fill in Name, Slug (unique), Timezone, and address/contact. A regular admin sees this screen read-only. (See **Admin Control Center §5 — Facility**.)
- ☐ **Seed the canonical roles.** From the **Admin Dashboard** setup checklist ("Canonical roles seeded"), open the Roles screen and **Seed default roles** to create Super Admin / Administrator / Manager / Staff. (Roles has no sidebar link — reach it from the dashboard checklist. ⚠ VERIFY navigation. See **Admin Control Center §5 — Roles**.)
- ☐ **Review role permission defaults.** On the Roles screen, set each role's default View / Submit / Edit / Admin per module so new employees inherit sensible access. Add any custom per-facility roles (e.g. `driver`) now.
- ☐ **Turn on the modules you'll use.** In **Admin Center** → **Modules**, flip the on/off switch for each module (Daily Reports, Ice Depth, Ice Operations, Refrigeration, Air Quality, Incidents, Accidents, Scheduling, Communications, Facility Paperwork). This controls **staff navigation visibility only** — it doesn't grant permissions. (See **Admin Control Center §5 — Modules**.)
- ☐ **Set up shared lists.** Create **Departments** (for scheduling/routing) and **Facility Spaces** (the location list used by Incident, Accident, and Air Quality — use **Seed defaults** for a standard set). (See **Admin Control Center §5 — Departments / Facility Spaces**.)

Phase 2 — Add people and assign roles

- ☐ **Add your employees.** In **Admin Center** → **People**, use **Add employee** (or **Bulk add** for up to 100 at once). Set name, **Role**, and decide **Create a login & apply these permissions** (on for people who sign in; off for schedule-only staff such as minors). (See [Admin Control Center §5 — People / Employees](#) and the *employee field reference* in §7.)
- ☐ **Assign roles and job areas.** Choose each person's role in the same form (you can only assign roles at or below your own rank), and pick up to 4 **job areas** (one Primary) for scheduling. Set **Max weekly hours** if you want an overtime warning threshold.
- ☐ **Send invites.** For login users, the invite goes out when you create them (or via the **Invite** row action / the bulk "send invites" toggle). Seed permissions are applied automatically.
- ☐ **△ super_admin only — Cross-facility placement & Admin access.** Only a super_admin can place someone in a *different* facility and grant the **Admin module's Admin action** (Admin Center access). A regular admin cannot hand out Admin Center access. (See [Admin Control Center §5 — Permissions](#).)

Phase 3 — Configure each module's settings

Open each enabled module's admin area (Admin Center → Module Admin) and complete its **Setup & configuration** section. Most modules offer a **Seed defaults** button to get a working starting point.

- ☐ **Daily Reports** — create **Areas** (up to 30 active; △ VERIFY exact cap), build **Templates** and **Checklist Items**, and grant **Area Access** per employee. (See [Daily Reports §4](#).)
- ☐ **Refrigeration Logs** — **Seed defaults** or build **Sections / Equipment / Fields**, set **Thresholds** (normal ranges), and configure **Settings** (out-of-range alerts, readings-per-shift cap). (See [Refrigeration §4](#).)
- ☐ **Air Quality** — add **Reading types** and **Equipment**, choose a **Compliance** profile and **tighten thresholds** if needed (you can only tighten, never loosen — △ VERIFY), and set **Settings** (alerts, testing-frequency text). (See [Air Quality §4](#).)
- ☐ **Ice Operations** — set up **Rinks**, **Equipment**, **Fuel types**, **Circle-check items/templates**, then choose **Visible operations** and alerts in **Settings**. (See [Ice Operations §4](#).)
- ☐ **Ice Depth** — create **Rinks** and **Diagrams** (place measurement points), and set **Settings** (unit — inches/mm △ VERIFY, thresholds, colors, alerts). (See [Ice Depth §4](#).)
- ☐ **Incident / Accident Reporting** — configure **Severity Levels** (at least one is required), **Activities**, and **Types**; the location list comes from Facility Spaces. (See [Incident Reporting §4](#).)
- ☐ **Employee Scheduling** — set up **Job areas** (with required certifications), **Settings** (week start, approval rules, warning behavior), and **Templates / Compliance** rules. (See [Employee Scheduling §4](#).)

Phase 4 — Permissions, retention, exports

- ☐ **Fine-tune permissions.** In **Admin Center** → **Permissions**, override any individual's module × action access (View / Submit / Edit / Admin). Presets (Full Access / Submitter Only / Viewer Only / No Access)

write a whole row at once. Remember the **Admin-module Admin** cell is super_admin-only to grant. (See [Admin Control Center §5 — Permissions](#).)

- ☐ **Set data retention.** In **Admin Center** → **Data Retention**, set keep-days per module (0 = forever, or ≥ 30) and decide on nightly auto-purge. Heed the warning for incident/accident/workers'-comp records. (See [Admin Control Center §5 — Data Retention](#).)
- ☐ **Configure exports.** In **Admin Center** → **PDF/Export Settings**, set branding (logo, header/footer), layout (paper size, date format, CSV delimiter), and per-module column visibility. Run a test export. (See [Admin Control Center §5 — PDF/Export Settings](#).)
- ☐ **Check the Setup checklist & audit log.** Return to the **Admin Dashboard** — the setup checklist should read "Ready." Spot-check the **Audit Log** to confirm your changes are recorded. (See [Admin Control Center §5 — Dashboard / Audit Log](#).)

Quick reference — what's super_admin-only

These steps cannot be done by a facility_manager (`admin`) and must go to a super_admin:

- Create / edit / activate / deactivate a **facility**.
- Place an employee in a **different facility**.
- Grant the **Admin module's Admin action** (Admin Center access).
- **Hard-delete** an employee (others use Deactivate).
- Anything in the **Super Admin console** (`/admin/super-admin`).

(All confirmed in [Admin Control Center §2 and §9](#). $\triangle$ *VERIFY* — *org_admin* has no live equivalent; treat as *super_admin*.)