Hand Gesture Control - Cheat Sheet

Control your mouse and keyboard with your hand through the webcam. 100% local, nothing is recorded.

Starts **PAUSED** - hold an open palm to begin

MOUSE

☝️ **Point**
Index finger up, others down. Fingertip moves the cursor.
Move cursor

👌 **Pinch (tap)**
Quickly touch thumb + index tips, then open.
Left click

👌👌 **Pinch twice**
Two quick pinches in a row.
Double click

👌⏳ **Pinch & hold**
Hold thumb + index > 0.4 s, move, open to drop.
Drag & drop

👌 **Middle pinch**
Touch thumb + **middle** fingertip.
Right click

✌️ **V sign**
Index + middle up. Move hand up/down.
Scroll

🖖 **Three fingers**
Index + middle + ring up. Move hand up/down.
Zoom in / out

🤚 **Four fingers**
All fingers up, thumb folded. Move hand around.
Rotate 3D view

🙌 **Two-hand zoom**
Pinch with **both** hands, pull apart / push.
Zoom in / out

🤙 **Call-me sign**
Thumb + pinky out. Move hand up/down.
Volume up / down

✊ **Fist**
Close your whole hand and hold.
Pause control hold 1 s

🖐️ **Open palm**
All 5 fingers spread, hold still.
Resume control hold 1 s

KEYS, MEDIA & SHORTCUTS

👍 **Thumbs up**
Fist with thumb pointing up.
Enter hold 0.7 s

🤘 **Rock sign**
Index + pinky up, thumb folded.
Play / Pause hold 0.6 s

👎 **Thumbs down**
Fist, thumb pointing down.
On-screen keys hold 0.8 s

🤙 **Pinky only**
Only the little finger up, thumb folded.
Screenshot hold 0.8 s

SWIPES - OPEN PALM, QUICK FLICK (A STILL PALM NEVER SWIPES)

🖐️⬅️ **Swipe left**
Switch app

🖐️➡️ **Swipe right**
Switch app

🖐️⬆️ **Swipe up**
Task view

🖐️⬇️ **Swipe down**
Show desktop

Apps, hotkeys & tips

Some gestures change automatically depending on the app in front (shown as "App profile" in the preview).

PER-APP PROFILES

App	What changes
Chrome, Edge, Firefox, Brave, Opera	Swipe ← = **Back**, swipe → = **Forward**
PowerPoint	Swipe ← = **previous slide**, swipe → = **next slide**
Google Earth Pro	3 fingers & two-hand pinch = **zoom** (mouse wheel) 4 fingers = **tilt / rotate** view · Swipe ← → = move the view · Pinch & hold = drag the globe
Blender	3 fingers & two-hand pinch = **zoom** · 4 fingers = **orbit**
Everything else	Default gestures from page 1 (3 fingers = Ctrl+wheel zoom)

START & STOP

What	How
Start (real control)	Double-click **start.bat** - starts PAUSED, hold an open palm 🖐
Test only (no clicks)	Double-click **start-dry-run.bat**
Fit to your hand	Double-click **calibrate.bat** and follow the 4 steps
Quit instantly	`Ctrl` + `Alt` + `Q` or `Esc` in the preview
Pause / resume	`Ctrl` + `Alt` + `P` or fist ✊ / open palm 🖐
Gesture list	`H` in the preview window
Emergency stop	Push the **real mouse** into any screen corner

TIPS FOR BEST RESULTS

- Sit **50-80 cm** from the camera, palm facing it.
- Keep your hand inside the **yellow rectangle** - it covers the whole screen, no need to reach the edges.
- Good, even **light** on your hand; avoid a bright window behind you.
- A plain background helps tracking.
- **Right hand** is in control; your **left hand** takes over when the right one is out of view. The hand in control is drawn **blue**, an ignored hand **grey**.
- Finger names on screen turn **green** when that finger counts as "up".
- Make gestures clearly and hold them still for a moment - each gesture needs a few steady frames.

READING THE PREVIEW WINDOW

- **ACTIVE / PAUSED / DRY RUN** - top left
- **Gesture:** what it sees now · **FPS** top right (25+ is good)
- **Yellow text** - the action just done (e.g. LEFT CLICK)
- **Progress bar** - a hold gesture charging up
- **Bottom lines** - fingers up, pinch distance, which hand

SOMETHING FEELS OFF?

Clicks become drags → pinch quicker, or raise `timing.drag_hold_s`.
Gestures trigger too easily / too hard → run **calibrate.bat**.
Cursor shaky / slow → tune `smoothing` in config.json.
Turn a gesture off → set it to `null` in `gesture_actions`.