


Installation notes for „Logo Slider in Footer“

A) Upload the module from Back office:

- Go to Modules, choose „Upload a module“




Select module ZIP archive from your hard drive. The module will be installed automatically.
(If the file upload doesn't work, check with your hosting provider that the „php_fileinfo extension“ is enabled).

B) Manually via FTP (recommended)

If the A) doesn't work for you, you can install the module manually via FTP.

modules > wpfooterslider >			
Název	Datum změny	Typ	Velikost
translations	03.08.2017 16:35	Složka souborů	
views	03.08.2017 16:35	Složka souborů	
ajax_wpfooterslider	03.08.2017 16:43	Soubor PHP	2 kB
index	30.03.2017 18:25	Soubor PHP	2 kB
logo	02.05.2017 12:18	Soubor PNG	2 kB
WpFooterSlide	03.08.2017 17:23	Soubor PHP	5 kB
wpfooterslider	03.08.2017 17:23	Soubor PHP	51 kB

- Unzip and copy content of archive wpfooterslider.zip into your modules/directory on FTP:
 - Go to Back Office – Modules, type „wpfooterslider“ into the search window.
- You should see the „Logo Slider in footer“ module card. Click on „Install“.



Module setup

Go to Back Office > Modules, find „Logo slider in footer“ module and click „Configure“. The module provides following options:

SETTINGS

Visible items
The number of visible items (for desktop mode)

Scroll items
The number of items to scroll (desktop mode)

Speed
Determines the duration of the transition in milliseconds between slides. Default is 400.

Mouseover pause ☒ YES ☐ NO
Determines whether the timeout between transitions should be paused on mouse hover, when autoplay is enabled

Loop ☒ YES ☐ NO
Infinity loop

Autoplay ☒ YES ☐ NO
Determines whether the slider should scroll automatically or not

Save

Visible items - The number of visible images.

Scroll items - The number of images to scroll when you click on left / right arrow.

Speed - Determines the duration of the transition in milliseconds between slides. Default 400.

Autoplay - Determines whether the slider should scroll automatically or not

Mouseover pause - Determines whether the timeout between transitions should be paused on mouse hover, when autoplay is enabled.

Loop – infinity loop

SLIDES LIST

Click here to add new image

#1 - Sample 1 ☒ Enabled Edit Delete

#2 - Sample 2 ☒ Enabled Edit Delete

#3 - Sample 3 ☒ Enabled Edit Delete

TIPS

- In **Design – Positions**, you can **change position of module in footer** by sorting the module in hook displayFooterBefore
- You will get best result, if you **upload all images in same size**.
- Except footer, you can display the module anywhere else in your theme, using this code:
`{widget name="wpfooterslider" hook="displayFooterBefore"}`
- If you have less then 6 logo images (default number of visible items) and want to center them, make sure to resetup „Visible items“ and „Scroll items“ to the number of logos you have.