
Untitled Model 1
K2 STORAGE 2;
K4 STORAGE 3;
K5 STORAGE 4;
GENERATE 7,5;
TRANSFER BOTH,METK1,METK2;
METK1 SEIZE PRU1;
ADVANCE 25,6;
RELEASE PRU1;
TRANSFER ,STK;
METK2 ENTER K2;
ADVANCE 15,6;
LEAVE K2;
STK TRANSFER BOTH,METK3,METK4;
METK3 SEIZE PRU2;
ADVANCE 15,6;
RELEASE PRU2;
TRANSFER ,STK2;
METK4 ENTER K4;
ADVANCE 15,6;
LEAVE K4;
STK2 GATE SNF K5,OUT;
ENTER K5;
ADVANCE 10,3;
LEAVE K5;
OUT TERMINATE 1;
START 100;
Untitled Model 1.4.1 - REPORT
GPSS World Simulation Report - Untitled Model 1.4.1
Tuesday, March 21, 2023 18:28:56
START TIME END TIME BLOCKS FACILITIES STORAGES
0.000 782.333 22 2 3
NAME VALUE
K2 10000.000
K4 10001.000
K5 10002.000
METK1 3.000
METK2 7.000
METK3 11.000
METK4 15.000
OUT 22.000
PRU1 10003.000
PRU2 10004.000
STK 10.000
STK2 18.000
LABEL LOC BLOCK TYPE ENTRY COUNT CURRENT COUNT RETRY
1 GENERATE 106 0 0
2 TRANSFER 106 0 0
METK1 3 SEIZE 27 0 0
4 ADVANCE 27 1 0
5 RELEASE 26 0 0
6 TRANSFER 26 0 0
METK2 7 ENTER 79 0 0
8 ADVANCE 79 1 0
9 LEAVE 78 0 0
STK 10 TRANSFER 104 0 0
METK3 11 SEIZE 37 0 0
12 ADVANCE 37 1 0
13 RELEASE 36 0 0
14 TRANSFER 36 0 0
METK4 15 ENTER 67 0 0
16 ADVANCE 67 1 0
17 LEAVE 66 0 0
STK2 18 GATE 102 0 0
19 ENTER 102 0 0
20 ADVANCE 102 2 0
For Help, press F1
Report is Complete.
Clock
пуск
GPSS
GPSS World - Untitled...
Новая папка
PR2.txt - Блокнот
EN
18:34

Untitled Model 1

```
K2 STORAGE 2;
K4 STORAGE 3;
K5 STORAGE 4;

GENERATE 7,5;
TRANSFER BOTH,METK1,METK2;

METK1 SEIZE PRU1;
ADVANCE 25,6;
RELEASE PRU1;

TRANSFER ,STK;

METK2 ENTER K2;
ADVANCE 15,6;
LEAVE K2;

STK TRANSFER BOTH,METK3,METK4;

METK3 SEIZE PRU2;
ADVANCE 15,6;
RELEASE PRU2;

TRANSFER ,STK2;

METK4 ENTER K4;
ADVANCE 15,6;
LEAVE K4;

STK2 GATE SNF K5,OUT;
ENTER K5;
ADVANCE 10,3;
LEAVE K5;

OUT TERMINATE 1;
START 100;
```

Untitled Model 1.4.1 - REPORT

LABEL	LOC	BLOCK TYPE	ENTRY COUNT	CURRENT COUNT	RETRY
	1	GENERATE	106	0	0
	2	TRANSFER	106	0	0
METK1	3	SEIZE	27	0	0
	4	ADVANCE	27	1	0
	5	RELEASE	26	0	0
	6	TRANSFER	26	0	0
METK2	7	ENTER	79	0	0
	8	ADVANCE	79	1	0
	9	LEAVE	78	0	0
STK	10	TRANSFER	104	0	0
METK3	11	SEIZE	37	0	0
	12	ADVANCE	37	1	0
	13	RELEASE	36	0	0
	14	TRANSFER	36	0	0
METK4	15	ENTER	67	0	0
	16	ADVANCE	67	1	0
	17	LEAVE	66	0	0
STK2	18	GATE	102	0	0
	19	ENTER	102	0	0
	20	ADVANCE	102	2	0
	21	LEAVE	100	0	0
OUT	22	TERMINATE	100	0	0

FACILITY	ENTRIES	UTIL.	AVE. TIME	AVAIL.	OWNER	PEND	INTER	RETRY	DELAY
PRU1	27	0.894	25.898	1	105	0	0	0	0
PRU2	37	0.665	14.061	1	104	0	0	0	0

STORAGE	CAP.	REM.	MIN.	MAX.	ENTRIES	AVL.	AVE.C.	UTIL.	RETRY	DELAY
K2	2	1	0	2	79	1	1.428	0.714	0	0
K4	3	2	0	3	67	1	1.315	0.438	0	0
K5	4	2	0	4	102	1	1.284	0.321	0	0

FEC XN	PRI	BDT	ASSEM	CURRENT	NEXT	PARAMETER	VALUE
107	0	783.291	107	0	1		
103	0	783.554	103	16	17		
102	0	785.271	102	20	21		
101	0	789.262	101	20	21		
104	0	790.082	104	12	13		
106	0	790.578	106	8	9		
105	0	801.500	105	4	5		

Untitle... Untitle...

or Help, press F1 Report is Complete. Clock

пуск GPSS GPSS World - Untitled... Новая папка PR2.txt - Блокнот EN 18:35

жер [stud - Файловый менедж... [VM VirtualBox OSE Менед... WinXP MS VS 2010 [Работа... Датчики Net 18:35