




Router R1

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#in se 0/0

Router(config-if)#clock rate?

rate

Router(config-if)#clock rate ?

Speed (bits per second

1200

2400

4800

9600

19200

38400

56000

64000

72000

125000

128000

148000

250000

500000

800000

1000000

1300000

2000000

4000000

<300-4000000> Choose clockrate from list above

Router(config-if)#clock rate 64000

Router(config-if)#ip address 10.0.0.1 255.0.0.0

Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0, changed state to down

Router(config-if)#

Router(config-if)#in in fa 0/0

^

% Invalid input detected at '^' marker.

Router(config-if)#in fa 0/0

Router(config-if)#ip address 192.168.1.1 255.255.255.0

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

%LINK-5-CHANGED: Interface Serial0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0, changed state to up

Router(config-if)#exit

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route

Gateway of last resort is not set

C 10.0.0.0/8 is directly connected, Serial0/0

C 192.168.1.0/24 is directly connected, FastEthernet0/0

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#router rip

Router(config-router)#network 10.0.0.0

Router(config-router)#network 192.168.1.0

Router(config-router)#exit

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router R2

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#in se 0/1

Router(config-if)#ip address 10.0.0.2 255.0.0.0

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface Serial0/1, changed state to up

Router(config-if)#

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1, changed state to up

Router(config-if)#in fa 0/1

Router(config-if)#ip address 192.168.2.1 255.255.255.0

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

Router(config-if)#exit

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

C 10.0.0.0/8 is directly connected, Serial0/1

C 192.168.2.0/24 is directly connected, FastEthernet0/1

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#router rip

Router(config-router)#network 10.0.0.0

Router(config-router)#network 192.168.2.0

Router(config-router)#exit

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#ping 10.0.0.1

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to 10.0.0.1, timeout is 2 seconds:

!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/4 ms