Name: Shidqi Aditya Falah
NIM : L202173001
Class : X

KEGIATAN 1



Tugas 11A:


Eagle
Physical
Config
CLI
Attributes
IOS Command Line Interface
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)
Press RETURN to get started!
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 172.21.20.0 255.255.255.0 172.21.1.2
Router(config)#ip route 172.21.30.0 255.255.255.0 172.21.2.3
Router(config)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top


Puma
Physical
Config
CLI
Attributes
IOS Command Line Interface
Press RETURN to get started!
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 172.21.10.10 255.255.255.0 172.21.1.1
%Inconsistent address and mask
Router(config)#ip route 172.21.10.0 255.255.255.0 172.21.1.1
Router(config)#ip route 172.21.30.0 255.255.255.0 172.21.3.3
Router(config)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top



Tugas 12A:

Iya mendapatkan tanggapan dari Puma. Hal ini dikarenakan telah dibuat peroutingan untuk data lewat melalui jalur yang mana.

Tugas 12B:

1. Lakukan konfigurasi untuk ip address pada router eagle



2. Lakukan konfigurasi ip pada pc leo dan ubah default gateway.



3. Lakukan peroutingan pada masing-masing router sesuai dengan blok ip pc




Puma
Physical
Config
CLI
Attributes
IOS Command Line Interface
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
Router>enable
Router#ping 172.21.3.3
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.21.3.3, timeout is 2 seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/1 ms
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 172.21.100.0 255.255.255.0 172.21.1.1
Router(config)#ip route 172.21.30.0 255.255.255.0 172.21.3.3
Router(config)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top


Tiger
Physical
Config
CLI
Attributes
IOS Command Line Interface
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 172.21.100.0 255.255.255.0 172.21.1.2.1
% Invalid input detected at '^' marker.
Router(config)#ip route 172.21.100.0 255.255.255.0 172.21.2.1
Router(config)#ip route 172.21.20.0 255.255.255.0 172.21.3.2
Router(config)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top

4. Lakukan pengecekan







KEGIATAN 2

Tugas 4A:



Tugas 4B:

Karena network 172.21.0.0 sudah mencakup semua alamat jariangan lain.

Tugas 5A:



Debug berfungsi melihat transaksi yang terjadi.

Tugas 6A dan 6B:



Setelah router Puma dilakukan routing rip maka pada router eagle secara otomatis mengupdate entries untuk routing rip.

Tugas 6C:

Tidak perlu. Hal tersebut karena network yang dipakai adalah 172.21.0.0 yang dimana masih dalam satu jaringan.

Tugas 8A:



Routing otomatis di downkan dan dimana melalui serial 3/0 yang terjadi di mana hops juga berubah.

Tugas 9A:





Dikarenakan hubungan di downkan maka hasil routing yang berawal dari dimulai menjadi berhenti dan menghasilkan RTO karena jaringan tidak terhubung.

KEGIATAN 3

Tugas 4A



Tugas 5A:



Terjadi suatu transaksi yang mengiri tanda ataupun sapa untuk router lain dan komputer melalui fa dan serial.

Tugas 7A:





Tugas 7B:

Setelah router puma dikonfigurasi maka di router eagle otomatis meng-update kemudia mengirim ack dan seterusnya hingga proses selesai.

Tugas 7C:

Tidak perlu. Kan tetap berada pada jaringan yang sama dan karena peroutingan sudah dinamis.

Tugas 9A:





Setelah hubungan antara router eagle dan puma di putuskan melalui router puma maka juga ada pemberitahuan dan upadate pada router eagle.

Tugas 10A:





Setelah router terputus waktu yang dibutuhkan untuk mengirim data menjadi berbeda. Juga terdapat perbedaan pada hops atau jalan yang dilalui.

TUGAS MODUL 5

STATIC

1. Desain jaringan



2. Melakukam konfigurasi ip router dengan pembagian

a. Lion
   - fa 0/0 = 172.21.10.10
   - fa 1/0 = 172.21.20.20
   - se 2/0 = 172.21.1.1
   - se 3/0 = 172.21.2.1

b. Puma
   - fa 0/0 = 172.21.30.10
   - fa 1/0 = 172.21.40.20
   - se 2/0 = 172.21.1.2
   - se 3/0 = 172.21.3.1

c. Tiger
   - fa 0/0 = 172.21.50.10
   - fa 1/0 = 172.21.60.20
   - se 2/0 = 172.21.4.1
   - se 3/0 = 172.21.3.2

d. Jaguar
   - fa 0/0 = 172.21.70.10
   - fa 1/0 = 172.21.80.20
   - fa 2/0 = 172.21.4.2
   - fa 3/0 = 172.21.2.2


Lion
Physical
Config
CLI
Attributes
IOS Command Line Interface
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)
Press RETURN to get started!
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa 0/0
Router(config-if)#ip address 172.21.10.10 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#int fa 1/0
Router(config-if)#ip address 172.21.20.20 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#int se 2/0
Router(config-if)#clock rate 2000000
Router(config-if)#ip address 172.21.1.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#int se 3/0
Router(config-if)#clock rate 2000000
Router(config-if)#ip address 172.21.2.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top


Puma
Physical
Config
CLI
Attributes
IOS Command Line Interface
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)
Press RETURN to get started!
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
Router>enable
Router#comf term
^
% Invalid input detected at '^' marker.
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa 0/0
Router(config-if)#ip address 172.21.30.30 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#int fa 1/0
Router(config-if)#ip address 172.21.40.40 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#int se 2/0
Router(config-if)#ip address 172.21.1.2 255.255.255.0
Router(config-if)#int se 3/0
Router(config-if)#clock rate 2000000
Router(config-if)#ip address 172.21.3.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top


Tiger
Physical
Config
CLI
Attributes
IOS Command Line Interface
X.25 software, Version 3.0.0.
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)
Press RETURN to get started!
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa 0/0
Router(config-if)#ip address 172.21.50.50 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#int fa 1/0
Router(config-if)#ip address 172.21.60.60 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#int se 2/0
Router(config-if)#clock rate 2000000
Router(config-if)#ip address 172.21.4.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#int se 3/0
Router(config-if)#ip address 172.21.3.2 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top


Jaguar
Physical
Config
CLI
Attributes
IOS Command Line Interface
Bridging software.
X.25 software, Version 3.0.0.
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)
Press RETURN to get started!
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa 0/0
Router(config-if)#ip address 172.21.70.70 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#int fa 1/0
Router(config-if)#ip address 172.21.80.80 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#int se 2/0
Router(config-if)#ip address 172.21.4.2 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#int se 3/0
Router(config-if)#ip address 172.21.2.2 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top

3. Konfigurasi pada pc






PC2
Physical
Config
Desktop
Programming
Attributes
IP Configuration
IP Configuration
DHCP
Static
IP Address
172.21.30.1
Subnet Mask
255.255.255.0
Default Gateway
172.21.30.30
DNS Server
0.0.0.0
IPv6 Configuration
DHCP
Auto Config
Static
IPv6 Address
Link Local Address
FE80::2D0:58FF:FED7:5136
IPv6 Gateway
IPv6 DNS Server
Top


PC3
Physical
Config
Desktop
Programming
Attributes
IP Configuration
IP Configuration
DHCP
Static
IP Address
172.21.40.1
Subnet Mask
255.255.255.0
Default Gateway
172.21.40.40
DNS Server
0.0.0.0
IPv6 Configuration
DHCP
Auto Config
Static
IPv6 Address
Link Local Address
FE80::290:CFF:FE69:5254
IPv6 Gateway
IPv6 DNS Server
Top


PC4
Physical
Config
Desktop
Programming
Attributes
IP Configuration
IP Configuration
DHCP
Static
IP Address
172.21.50.1
Subnet Mask
255.255.255.0
Default Gateway
172.21.50.50
DNS Server
0.0.0.0
IPv6 Configuration
DHCP
Auto Config
Static
IPv6 Address
Link Local Address
FE80::201:C9FF:FE7A:685A
IPv6 Gateway
IPv6 DNS Server
Top


PC5
Physical
Config
Desktop
Programming
Attributes
IP Configuration
IP Configuration
DHCP
Static
IP Address
172.21.60.1
Subnet Mask
255.255.255.0
Default Gateway
172.21.60.60
DNS Server
0.0.0.0
IPv6 Configuration
DHCP
Auto Config
Static
IPv6 Address
Link Local Address
FE80::2E0:B0FF:FE11:822A
IPv6 Gateway
IPv6 DNS Server
Top


PC6
Physical
Config
Desktop
Programming
Attributes
IP Configuration
IP Configuration
DHCP
Static
IP Address
172.21.70.1
Subnet Mask
255.255.255.0
Default Gateway
172.21.70.70
DNS Server
0.0.0.0
IPv6 Configuration
DHCP
Auto Config
Static
IPv6 Address
Link Local Address
FE80::201:43FF:FEED:4DBE
IPv6 Gateway
IPv6 DNS Server
Top


PC7
Physical
Config
Desktop
Programming
Attributes
IP Configuration
IP Configuration
DHCP
Static
IP Address
172.21.80.1
Subnet Mask
255.255.255.0
Default Gateway
172.21.80.80
DNS Server
0.0.0.0
IPv6 Configuration
DHCP
Auto Config
Static
IPv6 Address
Link Local Address
FE80::201:96FF:FE02:E108
IPv6 Gateway
IPv6 DNS Server
Top

4. Melakukan cek koneksi

Dari pc 1 ke router lion



Dari router lion ke router puma



5. Melakukan routing






Tiger
Physical
Config
CLI
Attributes
IOS Command Line Interface
Router con0 is now available
Press RETURN to get started.
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 172.21.10.0 255.255.255.0 172.21.4.2
Router(config)#ip route 172.21.20.0 255.255.255.0 172.21.4.2
Router(config)#ip route 172.21.30.0 255.255.255.0 172.21.3.1
Router(config)#ip route 172.21.40.0 255.255.255.0 172.21.3.1
Router(config)#ip route 172.21.70.0 255.255.255.0 172.21.4.2
Router(config)#ip route 172.21.80.0 255.255.255.0 172.21.4.2
Router(config)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top


Jaguar
Physical
Config
CLI
Attributes
IOS Command Line Interface
Router con0 is now available
Press RETURN to get started.
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 172.21.10.0 255.255.255.0 172.21.2.1
Router(config)#ip route 172.21.20.0 255.255.255.0 172.21.2.1
Router(config)#ip route 172.21.30.0 255.255.255.0 172.21.2.1
Router(config)#ip route 172.21.40.0 255.255.255.0 172.21.2.1
Router(config)#ip route 172.21.50.0 255.255.255.0 172.21.4.1
Router(config)#ip route 172.21.60.0 255.255.255.0 172.21.4.1
Router(config)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top

6. Melakukan show ip route






Tiger
Physical
Config
CLI
Attributes
IOS Command Line Interface
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
172.21.0.0/24 is subnetted, 10 subnets
C 172.21.3.0 is directly connected, Serial3/0
C 172.21.4.0 is directly connected, Serial2/0
S 172.21.10.0 [1/0] via 172.21.4.2
S 172.21.20.0 [1/0] via 172.21.4.2
S 172.21.30.0 [1/0] via 172.21.3.1
S 172.21.40.0 [1/0] via 172.21.3.1
C 172.21.50.0 is directly connected, FastEthernet0/0
C 172.21.60.0 is directly connected, FastEthernet1/0
S 172.21.70.0 [1/0] via 172.21.4.2
[1/0] via 172.21.3.1
S 172.21.80.0 [1/0] via 172.21.4.2
Router>
Router>
Ctrl+F6 to exit CLI focus
Copy
Paste
Top


Jaguar
Physical
Config
CLI
Attributes
IOS Command Line Interface
Router>show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route
Gateway of last resort is not set
172.21.0.0/24 is subnetted, 10 subnets
C 172.21.2.0 is directly connected, Serial3/0
C 172.21.4.0 is directly connected, Serial2/0
S 172.21.10.0 [1/0] via 172.21.2.1
S 172.21.20.0 [1/0] via 172.21.2.1
S 172.21.30.0 [1/0] via 172.21.2.1
S 172.21.40.0 [1/0] via 172.21.2.1
S 172.21.50.0 [1/0] via 172.21.4.1
S 172.21.60.0 [1/0] via 172.21.4.1
C 172.21.70.0 is directly connected, FastEthernet0/0
C 172.21.80.0 is directly connected, FastEthernet1/0
Router>
Ctrl+F6 to exit CLI focus
Copy
Paste
Top

7. Melakukan ping dari pc 0 ke pc 4



RIP

1. Desain jaringan



2. Melakukan konfigurasi ip dan routing






Tiger
Physical
Config
CLI
Attributes
IOS Command Line Interface
Compiled Wed 27-Apr-04 19:01 by miwang
PT 1001 (PTSC2005) processor (revision 0x200) with 60416K/5120K bytes of memory
.
Processor board ID PT0123 (0123)
PT2005 processor: part number 0, mask 01
Bridging software.
X.25 software, Version 3.0.0.
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)
Press RETURN to get started!
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
Router>enable
Router#conf ter,
% Invalid input detected at '^' marker.
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#network 172.21.0.0
Router(config-router)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top


Jaguar
Physical
Config
CLI
Attributes
IOS Command Line Interface
63488K bytes of ATA CompactFlash (Read/Write)
Press RETURN to get started!
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#network 172.21.0.0
Router(config-router)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top

3. Melakukan ping dari pc 6 ke pc 2



IGRP

1. Desain jaringan



2. Melakukan konfigurasi ip dan routing secara otomatis






Tiger
Physical
Config
CLI
Attributes
IOS Command Line Interface
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router eigrp 100
Router(config-router)#network 172.21.0.0
Router(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 100: Neighbor 172.21.3.1 (Serial3/0) is up: new adjacency
Router(config-router)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top


Jaguar
Physical
Config
CLI
Attributes
IOS Command Line Interface
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router eigrp 100
Router(config-router)#network 172.21.0.0
Router(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 100: Neighbor 172.21.4.1 (Serial2/0) is up: new adjacency
%DUAL-5-NBRCHANGE: IP-EIGRP 100: Neighbor 172.21.2.1 (Serial3/0) is up: new adjacency
Router(config-router)#
Ctrl+F6 to exit CLI focus
Copy
Paste
Top

3. Melakukan ping dari pc 4 ke pc 0