

LEFT INFO PANEL
id: panel_left_info
x: 26
y: 22
w: 320
h: 700
purpose: Current selected phase information, building impact, material, logistics, user instruction.

TOP PHASE NAVIGATION
id: panel_top_phase_navigation
x: 407
y: 22
w: 900
h: 100
purpose: Phase selector / progress navigation for foundation, structure, roof, openings, finishing.

CENTER MAIN PLAN / SIMULATION AREA
id: panel_main_plan_simulation
x: 368
y: 162
w: 978
h: 560
purpose: Main plan view, active building zone, AR marker placement, simulation / spatial feedback.

RIGHT COMPARISON PANEL
id: panel_right_comparison
x: 1365
y: 22
w: 530
h: 438
purpose: purpose: Phase-based comparison table for masonry, 3D printed, and other phase-based methods. Prefab should use lifecycle card unless explicitly phase-mapped later.

STATE NOTE:
If selected method data_model = lifecycle_based, replace this panel with:

id: panel_prefab_lifecycle_card
x: 1365
y: 22
w: 530
h: 438

lifecycle stages:
A1-A3, A4, A5, B, C

sub_methods:
clt, modular_concrete

RIGHT COST / CHART PANEL
id: panel_right_cost_chart
x: 1365
y: 482
w: 530
h: 240
purpose: Total cost estimate, cost breakdown chart, material/labor/logistics/other percentages.

LEFT BOTTOM ASSEMBLY PANEL
id: panel_left_assembly_sequence
x: 26
y: 739
w: 460
h: 260
purpose: Assembly sequence preview, phase thumbnails, current assembly step.

BOTTOM METHOD SELECTION PANEL
id: panel_method_selection
x: 506
y: 739
w: 840
h: 260
purpose: Construction method selection area, RFID method objects, selection platform.

RIGHT PHASE PREVIEW PANEL
id: panel_right_phase_preview
x: 1365
y: 739
w: 530
h: 260
purpose: Phase preview, checklist, small model preview, progress slider.

STATE NOTE:
If selected method data_model = lifecycle_based, replace this panel with:
id: panel_prefab_lifecycle_card
same bounds:
x: 1365
y: 22
w: 530
h: 438

BOTTOM STATUS BAR
id: bar_bottom_status
x: 0 / y: 1030
w: 1920 / h: 50
purpose: Reset system, help message, audio status, global feedback.