tracetronic

tracetronic floating license

Documentation for tracetronic floating license mechanism

Set-up Floating license hosted on a tracetronic server

tracetronic GmbH
Stuttgarter Straße 3
01189 DRESDEN
GERMANY
www.tracetronic.de

Date: February 19, 2026


Please follow the instructions to activate the license. Please be aware that this is not the standard solution to set up the licensing. It is a special workaround for using the floating license hosted on a tracetronic server during the evaluation and not on a dedicated server within your company.

1 Set-Up Floating license

There are two simple ways to set up a floating license hosted on a tracetronic server:

1.1. During installation of ecu.test

- Please install ecu.test - during the installation the license server settings will be requested
- Please apply the "absolute file path" provided via e-mail ("@customer@password" is personalized for your specific license)




- If there is already an existing server, you can append the new server (with the "absolute file path") with a semicolon (";") at the end, e. g.:
  5063@licenseserver.com; 2060@license01.tracetronic.de@customer@password


- After you have completed the installation, you can start ecu.test; ecu.test should be able to get a license now

1.2. After installation of ecu.test

- Please search for "ecu.test License Manager" in the windows search dialog and open the "ecu.test License Manager":



- Please apply the “absolute file path” provided via e-mail (“@customer@password” is personalized for your specific license)



- If there is already an existing server, you can append the new server (with the “absolute file path”) with a semicolon (“;”) at the end, e. g.:
5063@licenseserver.com; 2060@license01.tracetronic.de@customer@password

- Now your available licenses should be displayed on the right side of the “ecu.test License Manager”, e. g.:

Available licenses

Product	Max. version	Count	Roaming count
ecu.test	2025.3	10	10
+ trace.check	2025.3	10	10
+ ecu.test diagnostics	2025.3	10	10

- Please close the "ecu.test License Manager" with "Exit" and start ecu.test; ecu.test should be able to get a license now.

2 If ecu.test can't find a license:

2.1 Troubleshooting under Windows


- If no license is available, please check that NO "RLM_LICENSE_PASSWORD" is set in your "environment variables" (from previous evaluations)

- If ecu.test still does not get a license, most likely the necessary ports are not open. The ports 2060 / 12060 are used by the tracetronic license server and need to be open for outgoing and incoming traffic.

    - To easily check this, please open windows powershell and type:

```
tnc license01.tracetronic.de -port 2060
tnc license01.tracetronic.de -port 12060
```

    - If TcpTestSucceeded is *True* it is fine:



- If the ports are not open, please contact your IT department to open the ports for the evaluation period.
- Please check the time zone in which the operating system is located. This must match the time zone of the license.

2.2 Troubleshooting under Linux

- If no license is available, please check that NO "RLM_LICENSE_PASSWORD" is set in your "environment variables" (from previous evaluations)
  - `echo $ RLM_LICENSE_PASSWORD`
    → no string should be printed

- If ecu.test still does not get a license, most likely the necessary ports are not open. The ports 2060 / 12060 are used by the tracetronic license server and need to be open for outgoing and incoming traffic.

  - To easily check if the license server can be reached from the machine executing ecu.test, please type in the command line:

    ```
    ping license01.tracetronic.de
    ```

  - To easily check the ports, please type in the command line:

    ```
    nc -zv license01.tracetronic.de 2060
    nc -zv license01.tracetronic.de 12060
    ```

  - You can also perform a deeper port scan using nmap:

    nmap -sV -p 2060 `license01.tracetronic.de`
    nmap -sV -p 12060 `license01.tracetronic.de`

- Please check the time zone in which the operating system is located. This must match the time zone of the license.

  - To easily check the time zone:

    ```
    bash> timedatectl
    ```

  - To easily change the time zone:

    ```
    bash> sudo timedatectl set-timezone Europe/Berlin
    ```