
# Создал сеть



# Команды:

## ?- список команд

· • • · · · · · · · · · · · · · · · · ·	
Switch>?	
Exec commands:	
connect	Open a terminal connection
disable	Turn off privileged commands
disconnect	Disconnect an existing network connection
enable	Turn on privileged commands
exit	Exit from the EXEC
logout	Exit from the EXEC
ping	Send echo messages
resume	Resume an active network connection
show	Show running system information
telnet	Open a telnet connection
terminal	Set terminal line parameters
traceroute	Trace route to destination

#### show-показать информацию о работающей системе(команды для show)

```
arp Arp table
cdp CDP information
clock Display the system clock
crypto Encryption module
dtp DTP information
etherchannel EtherChannel information
flash: display information about flash: file system
history Display the session command history
interfaces Interface status and configuration
ip IP information
lldp LLDP information
mac MAC configuration
mac-address-table MAC forwarding table
mls Show MultiLayer Switching information
privilege Show current privilege level
sessions Information about Telnet connections
ssh Status of SSH server connections
tcp Status of TCP connections
tcp Status of TCP connections
terminal Display terminal configuration parameters
users Display information about terminal lines
version System hardware and software status
vlan VTP VLAN status
--More--
```

### enabled-переход в привилегированный режим

### configure terminal

```
Switch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#
```

#### enable password\* - устанавливает пароль

```
Switch(config) #enable password govnanka
```

### enable secret\* - хранит пароль в зашифрованном виде

Switch(config) #enable secret govnanka28rus

#### write memory-сохраняет изменения в конфигурации

```
write memory
Building configuration...
[OK]
Switch#
```

reload – перезагрузка устройства

```
Loading "flash:/pt3000-i6q412-mz.121-22.EA4.bin"...
Restricted Rights Legend
Use, duplication, or disclosure by the Government is
subject to restrictions as set forth in subparagraph
(c) of the Commercial Computer Software - Restricted
Rights clause at FAR sec. 52.227-19 and subparagraph
(c) (l) (ii) of the Rights in Technical Data and Computer
Software clause at DFARS sec. 252.227-7013.
          cisco Systems, Inc.
          170 West Tasman Drive
          San Jose, California 95134-1706
Cisco Internetwork Operating System Software
IOS (tm) PT3000 Software (PT3000-I6Q4L2-M), Version 12.1(22)EA4, RELEASE SOFTWARE (fcl)
Copyright (c) 1986-2006 by cisco Systems, Inc.
Compiled Fri 12-May-06 17:19 by pt team
Cisco WS-CSwitch-PT (RC32300) processor (revision CO) with 21039K bytes of memory.
Processor board ID FHK0610Z0WC
Running Standard Image
6 FastEthernet/IEEE 802.3 interface(s)
63488K bytes of flash-simulated non-volatile configuration memory.
Base ethernet MAC Address: 0007.ECDD.4C55
Motherboard assembly number: 73-5781-09
Power supply part number: 34-0965-01
Motherboard serial number: FOC061004SZ
Power supply serial number: DAB0609127D
Model revision number: C0
Motherboard revision number: A0
Model number: WS-CSwitch-PT
System serial number: FHK0610Z0WC
Cisco Internetwork Operating System Software
IOS (tm) PT3000 Software (PT3000-I6Q4L2-M), Version 12.1(22)EA4, RELEASE SOFTWARE (fcl)
```

#### Тест команд

#### show users

Switch>show users

Line User Host(s) Idle Location

\* 0 con 0 idle 00:00:00

Interface User Mode Idle Peer Address

Switch>