



Rover Basic Masternode Setup Guide - Windows

2018.03.07



# Contents

1. Wind	ows wallet guide	. 3
	1.1 Download the latest Rover windows wallet	. 3
	1.2 How to make your own Rover address	. 3
	(Optional) How to reveal specific amount of coin for each address & Masternode tab	. 3
	1.3 How to send Rover	4
	1.4 Encrypting Windows wallet	. 4
2. Masternode setup guide		. 4
	2.1 Make new address for Masternode	. 5
	2.2 Send exactly '10000ROE' to address which is made in step 2.1	. 5
	2.3 Get privkey, TxHash and Output index	. 5
	2.4 Setup RPC details	. 6
	2.5 Setup the Masternode at windows wallet	. 7



# 1. Windows wallet guide

#### - 1.1 Download the latest Rover Windows wallet

https://github.com/RoverCoin/Rovercoin/files/1789416/Rover-QT-.Windows.zip

### - 1.2 How to make your own Rover address




Figure 1

### (Optional) How to reveal specific amount of coin for each address





Figure 3

3



## - 1.3 How to send Rover



## Figure 4

- a) Click 'Send' tab
- b) Type in Receiver's address in 'Pay To' (red box)
- c) Type in amount of HTK to send (green box)
- d) Click 'Send' (orange box)

## - 1.4 Encrypting Windows wallet




Figure 5

Go to Settings → Encrypt Wallet → Insert password twice

(Reminder: Never forget or lose your password!)



## 2. Masternode setup guide

- 2.1 Make new address for Masternode (Refer to step 1.2 for guidance)
- 2.2 Send exactly '10000ROE' to address which is made in step 2.1 (Refer to step 1.3 for guidance)
  - ▶ It will automatically include fee, so you just need to type 10000 at 'Amount'
- 2.3 Get privkey, TxHash and Output index




Figure 6

```
masternode outputs
```

Error: If you get a result like this, it means that there are no wallets containing 1000HTK

masternode outputs



### - 2.4 Setup RPC details




Figure 7




Figure 8

- a) Open 'Control Panel' (fig 7, red box)
- b) Click 'File Explorer Options' → 'View 'tab
  - ► Check 'Show hidden files, folders, and drivers' (fig 8, orange box)
- c) Go to 'Local disk (:C)' → 'Users' → 'YOURUSERNAME' → 'AppData' → 'Roaming' → 'Rover'
  - ▶ Open 'Rover.conf' and type the following and save (Open with notepad program)

```
rpcuser=RANDONWORD

rpcpassword=RANDONWORD(HAVE TO DIFFERENT WITH rpcuser's VALUE)

rpcallowip=127.0.0.1

rpcport=28217

port=28218

listen=1

server=1

daemon=1

bind=SERVERIP

masternode=1

externalip=SERVERIP:28218

masternodeprivkey=PRIVATE KEY(refer 2.3 (a), privkey)
```



#### - 2.5 Setup the Masternode at Windows wallet

a) Create Masternode




Figure 13

Figure 12

- a) Click 'Masternodes' tab (fig12, green box)
- b) Click 'Create' tab (fig 12, red box)
- ▶ Pop-up window(fig 13) will show up
- c) Type in the boxes and click 'OK' (red part should be changed to your own values)

Alias: YOUR\_MN\_NAME Address: YOUR\_IP:28218 PrivKey: PRIVATE KEY(refer 2.3 (a), privkey) TxHash: TxHash (refer 2.3 (b), TxHash) Output Index: 0 or 1 (refer 2.3 (b) Output Index) Reward Address: Masternode address (refer step 2.1) Reward %: 100

7



- e) Click your Masternode and click 'Start' button below (Unlock the wallet first, if it's encrypted)
  - ▶ Once you see the following pop-up window, Masternode setup is finished!

