EAD95802 - Exibir Bem-Vindo no COBOL

EAD95802 - COBOL

```
IDENTIFICATION DIVISION.
000100
            PROGRAM-ID.
000200
000300
                EAD95802.
000400
           AUTHOR.
000500
                LUCAS.
000600
           * EXIBIR BEM-VINDO NO COBOL
000700
00800
000810
000900
            ENVIRONMENT DIVISION.
001000
001100
           DATA DIVISION.
001110
           WORKING-STORAGE SECTION.
001120
            01 DATA-SIST.
                03 ANO-SIST PIC 9(2) VALUE ZEROS.
001130
001140
                03 MES-SIST PIC 9(2) VALUE ZEROS.
               03 DIA-SIST PIC 9(2) VALUE ZEROS.
001150
001160
           01 DATA-EXIBE.
                05 DIA-EXIBE PIC 9(2) VALUE ZEROS.
001170
001190
                05 FILLER PIC X
                                     VALUE '/'.
                05 MES-EXIBE PIC 9(2) VALUE ZEROS.
001191
                             PIC X(3) VALUE '/20'.
                05 FILLER
001192
                05 ANO-EXIBE PIC 9(2) VALUE ZEROS.
001193
001194
           01 HORA-SIST.
              05 HOR-SIST PIC 9(2) VALUE ZEROS.
001195
               05 MIN-SIST PIC 9(2) VALUE ZEROS.
001196
001197
               05 SEG-SIST
                             PIC 9(2) VALUE ZEROS.
              05 CEN-SIST PIC 9(2) VALUE ZEROS.
001198
001199
           01 HORA-EXIBE.
              05 HOR-EXIBE PIC 9(2) VALUE ZEROS.
001200
               05 FILLER
                             PIC X
001201
                                      VALUE ':'.
001202
               05 MIN-EXIBE PIC 9(2) VALUE ZEROS.
              05 FILLER PIC X VALUE ':'.
001203
                             PIC 9(2) VALUE ZEROS.
               05 SEG-EXIBE
001204
           77 NOME
001205
                             PIC A(10) VALUE SPACES.
001210
           PROCEDURE DIVISION.
001300
001400
           UNICA SECTION.
001500
            INICIO.
                ACCEPT NOME FROM SYSIN.
001600
                ACCEPT DATA-SIST FROM DATE.
001610
001620
                ACCEPT HORA-SIST FROM TIME.
001630
                MOVE DIA-SIST TO DIA-EXIBE.
                MOVE MES-SIST TO MES-EXIBE.
001640
001650
                MOVE ANO-SIST TO ANO-EXIBE.
001660
                MOVE HOR-SIST TO HOR-EXIBE.
001670
                MOVE MIN-SIST TO MIN-EXIBE.
                MOVE SEG-SIST TO SEG-EXIBE.
001680
001690
                DISPLAY 'OLA ' NOME
                       ', BEM-VINDO AO CURSO DE COBOL'.
001691
```

1

```
001692 DISPLAY 'A DATA EH: ' DATA-EXIBE.
001693 DISPLAY 'HORA: ' HORA-EXIBE.
001700 STOP RUN.
```

COMPILADOR

EXECUTAVÉL - EXECO2

SAÍDA