



Team Administrator and Supervisor User Guide

ACI® Proactive Risk Manager™

Version 9.3.0.0, May 2024

Table of Contents

About this publication	2
What's new in this publication	2
August 2023	2
May 2023	2
February 2023	3
December 2022	3
July 2022	3
May 2022	3
1. Getting started	5
1.1. Log in to PRM	5
1.2. Keyboard shortcuts	5
1.3. Standard grid functionality	6
1.3.1. Show or hide columns in a grid	6
1.3.2. Sort data in a grid	7
1.3.3. Filters	8
1.3.4. Reorder columns in a grid	10
1.3.5. Page through multipage grids	10
1.3.6. Modify page size (number of rows displayed)	11
1.3.7. Refresh data in a grid	11
1.3.8. Printing pages in the Web UI	11
1.3.9. Context menu and selection toolbar	12
1.3.10. Copy to clipboard	13
1.4. Log out of PRM	13
1.5. Change your password	14
1.6. Change your expired password	15
1.7. Main menu	16
1.8. Landing page	17
2. Dashboard	18
2.1. Dark mode	18
2.2. Widgets	18
2.2.1. Monitor KPIs	18
2.2.2. Add a widget	19
2.2.3. Edit a widget	27
2.2.4. Sort a widget	27
2.2.5. Refresh a widget	27
2.2.6. Remove a widget	27
2.2.7. Custom widgets	27
3. Search	28
4. Review	30
4.1. Pending alerts	30
4.1.1. Open a pending alert	31

4.1.2. Open a dimension ID	32
4.1.3. Delete one or more pending alerts	32
4.1.4. Copy pending alert data	33
4.1.5. Export pending alert data	33
4.2. Forwards & Reminders	33
4.2.1. Reminders	34
4.2.2. Forwards sent by me	34
4.2.3. Forwards sent to me	34
4.2.4. My team	35
4.2.5. Edit a reminder	35
4.2.6. Edit a forward	36
5. Configurations	37
5.1. Teams & users	37
5.1.1. View users assigned to a team	38
5.1.2. Add a user	39
5.1.3. Edit a user	41
5.1.4. Delete a user	43
6. Risk strategy & control	45
6.1. Team Administrator	45
6.2. Supervisor	46
7. Skip rule, queue, or computed variable execution	47
7.1. Rule manager	48
7.1.1. Open the Rule Manager window	48
7.1.2. Add a rule	49
7.1.3. Edit a rule	52
7.1.4. Delete a rule	54
7.1.5. Clone a rule	54
7.1.6. Assign rules to portfolios	55
7.1.7. Export rules	57
7.1.8. Import rules and computed variables	59
7.1.9. Deploy a rule	60
7.1.10. Skip-Bad-Rule functionality	68
7.2. Dataset generator	69
7.2.1. Generate a dataset using the current NRT database	70
7.2.2. Generate a dataset using a replica of the NRT database	71
7.3. Test a rule	74
7.4. Queues	77
7.4.1. Roles and permissions	78
7.4.2. Queue manager	78
7.4.3. Queue assignment	81
7.5. Computed variables	83
7.5.1. Add computed variables	85
7.5.2. Edit, delete, or clone a computed variable	86

7.5.3. Export computed variables	87
7.6. List management	87
7.6.1. View a list	88
7.6.2. Add a list	89
7.6.3. Edit a list	91
7.6.4. Clone a list	91
7.6.5. Delete lists	92
7.7. External messaging	92
7.7.1. State and nonstate actions	93
7.7.2. Statuses	93
7.7.3. Managing external messages	94
7.8. Communication templates	95
7.8.1. Templates	95
7.8.2. Tags	96
7.8.3. Images	96
7.8.4. Add templates	96
7.8.5. Edit templates	97
7.8.6. Add tags	98
7.8.7. Edit tags	99
7.8.8. Add image	100

Notices

ACI Worldwide

Offices in principal cities throughout the world.

www.aciworldwide.com

Americas +1 402 390 7600

Asia Pacific +65 6334 4843

Europe, Middle East, Africa +44 (0) 1923 816393

© Copyright ACI Worldwide, Inc. 2024

All information contained in this documentation, as well as the software described in it, is confidential and proprietary to ACI Worldwide, Inc., or one of its subsidiaries, is subject to a license agreement, and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this documentation may be reproduced, stored in a retrieval system, or transmitted in any form or by electronic, mechanical, recording, or any other means, without the prior written permission of ACI Worldwide, Inc., or one of its subsidiaries.

ACI, ACI Worldwide, ACI Payments, Inc., ACI Pay, Speedpay and all ACI product/solution names are trademarks or registered trademarks of ACI Worldwide, Inc., or one of its subsidiaries, in the United States, other countries or both. Other parties' trademarks referenced are the property of their respective owners.

About this publication

This publication describes and provides instructions for the tasks performed by Fraud Analysts.

What's new in this publication

Here's what's new in this publication.

August 2023

Following are the topics and the changes made for PRM 9.2.4.0:

- [Widgets](#)

Adds information about the RT Rule KPIs and Rule KPIs widgets and how to configure and generate them.

- [Computed variables](#)

Modifies the note in the "Edit, Delete, or Clone a computed variable" section to state that users cannot delete a computed variable if it is referenced in any real-time rules, near real-time rules, batch queues, or smart queues, regardless of whether those rules or queues are deployed. The computed variable cannot be deleted until each rule and/or queue in which it is referenced is undeployed and deleted.

- [Deploy a rule](#), [Dual control disabled](#), [Dual control without override](#), and [Dual control with override](#)

Adds information about how to configure the order in which real-time rules are executed and why it matters.

- [External Messaging](#)

Updates the list of statuses to include In Progress and Not Processed. Adds information to Managing External Messages to include Enable Batch functionality.

- [Test a rule](#)

Updates the topic to include the new fields in the TEST RESULTS and PREVIOUS TEST RESULTS sections of the Rule Tester window and an explanation of the progress bar.

- [Generate test data](#)

Updates the topic to include the configuration and steps to follow to use a database replica.

May 2023

Following are the topics and the changes made for PRM 9.2.3.1:

- [Page through multipage grids](#)

Updates the description of the information that is displayed on each page to indicate the number of rows displayed.

Adds a description of the new IgnoreTotalCount configuration parameter.

Adds a description of the Previous page and Next page buttons.

February 2023

Following are the topics and the changes made for PRM 9.2.3.0:

- [Queues](#)

Added the "Queues" topic. It describes the different types of queues and includes a section on the roles and permissions associated with the Queue Manager window functions and the Queue Assignment window functions.

- [Queue manager](#)

Revised the topic and moved some information to the new "Queues" topic.

December 2022

Following are the topics and the changes made for PRM 9.2.2.0:

- [List management](#)

Added information about partitions.

July 2022

The following are the topics and the changes made for PRM 9.2.1.0:

- [Dashboard widgets](#)

The Queue Type dropdown field has been added to the Analyst Performance widget so that users can select one or more queues to include in the widget.

Administrators who have the *Manage Widgets for Team Members* permission can assign a widget to one or more users when creating a widget.

- [List management](#)

Separated the "View or edit list" topic into two topics: View list and Edit list.

Mentioned that values can be imported from a comma-separated values (CSV) file or a text (TXT) file.

Corrected the documentation to include the Clone list function that was omitted from the PRM 9.2.0.0 version of the guide.

May 2022

The following are the topics and the changes made for PRM 9.2.0.0:

- [Change your password](#)

Replaced the image of the window used to access the CHANGE YOUR PASSWORD window. The image was replaced to show that PRM Version has been added to the list of information on that window.

- [Communication templates](#)

Added information about the Images tab on the Communication Templates window and included instructions for adding an image to a template.

- [Dual Control](#)

Provided an overview of the Dual Control functionality.

Outlined procedures to deploy rules in the following situations:

- Dual control is disabled.
- Dual control is enabled, without override functionality.
- Dual control is enabled, with override functionality.

- [External messaging](#)

Updated the topic to show that the "External Messaging window" has been changed to the "External Messaging Status" window.

- [List management](#)

Updated the "View or edit a list" topic and the "Add a list" topic to show and describe the new fields on the ADD LIST and EDIT LIST windows.

- [Log out of PRM](#)

Replaced the image of the window used to log out of PRM. The image was replaced to show that PRM Version has been added to the list of information on that window.

- [Rule manager](#)

Updated the descriptions of the options in the Alert Behavior field.


Updated the Add a Rule section's Rule field descriptions for Real-Time Disposition and Alert Color.

1. Getting started

This section of the guide provides information intended to help you get started with the PRM Analysis and Review user interface.

1.1. Log in to PRM

To access the PRM Analysis and Review user interface, type the URL for your PRM system in your browser, then press **Enter**. The Login window opens.



The login window is titled "ENTER YOUR CREDENTIALS". It contains three input fields: "Organization" (with a house icon), "Username" (with a person icon), and "Password" (with a lock icon). Below these fields is an orange button labeled "LOG IN".

Enter the name of your organization, your username, and your password in the fields provided, then press **LOG IN**.

If the information you entered in the Login window is correct, the main menu and landing page are displayed. See [Main menu](#) for information about the fraud analyst main menu. See [Landing page](#) for information about the contents of the page.

If the information you enter in the Login window is not correct, the system will display an error message. You will have a configured number of times to attempt logging in. If you exceed the allowed number of attempts without a successful login, your profile will be locked, and an administrator will have to unlock it before you can log in again.

1.2. Keyboard shortcuts

Keyboard shortcuts enable you to navigate within the PRM Analysis and Review user interface, take actions, and perform certain operations within tables and grids, using only your keyboard.

To view a list of the keyboard shortcuts, press the "**K**" key on your keyboard or click the button shown below. You will find the button in the lower right corner of each page.



When you press "**K**" or click the button, the KEYBOARD SHORTCUTS window opens.

KEYBOARD SHORTCUTS

Navigation

1

This Screen

K

2

Go to Dashboard

G

then

D

3

Go to Search

G

then

S

4

Go to Pending Alerts

G

then

P

5

Go to Review

G

then

R

6

Go to Reports

G

then

X

7

Open Dimension ID

ALT

+

O

8

Recent Dimension ID

ALT

+

T

Action Hotkeys

1

Get Next Alert

G

then

A

2

Forward

F

3

Block

B

4

Mark

M

5

Mark From Dimension

ALT

+

M

6

Reminder

R

7

Response Required

ALT

+

R

8

Notes

N

9

Documents

D

10

Submit Form

CTRL

+

ENTER

11

Close Current Dimension ID

X

Grid/Table Hotkeys

1

Select Row

SPACE

2

Select Multiple Rows

SHIFT

+

↑

/

↓

3

Transaction Info

I

4

Grid Scroll Right

CTRL

+

→

5

Grid Scroll Left

CTRL

+

←

6

Grid Next Page

SHIFT

+

→

7

Grid Previous Page

SHIFT

+

←

8

Select other Dimension

P

9

Grid Select All

SHIFT

+

A

10

Grid Deselect All

SHIFT

+

X

To find out what a key or key combination enables you to do, move your cursor over the help symbol for that key or key combination.

To close the KEYBOARD SHORTCUTS window, click the "X" in the upper right corner of the window.

NOTE

The procedures described in this document identify the icons and buttons that can be used to perform the various functions from the PRM Analysis and Review user interface. As an alternative, you can perform many of those functions using the keyboard shortcuts.

1.3. Standard grid functionality

This topic describes the functionality available in grids in the Analysis and Review user interface.


1.3.1. Show or hide columns in a grid

Follow these instructions if you want to hide columns that are displayed in a grid, or if you want to display columns that were previously hidden.

- 1. Click the **Show/Hide Columns** icon:



A window opens listing the names of all the columns that can be displayed in the grid. Each column name is preceded by a checkbox. If the checkbox is selected, the column is displayed. If the checkbox has been cleared (that is, the check mark has been removed), the column is not displayed. The type ahead function in the field at the top of the window allows you to quickly find a column name. The checkbox next to the field at the top of the list allows you toggle between selecting all and clearing all checkboxes.



2. Your next step depends on whether you want to show all columns, hide only selected columns, or show only selected columns.
 - If you want all the columns that are available for the grid to be displayed, select the checkbox that is next to the field at the top of the list.
 - If you want to hide only a few of the columns that are available for the grid, select the checkbox that is next to the field at the top of the list and then clear the checkboxes next to the names of the columns you want to hide.
 - If you want to show only a few of the columns that are available for the grid, clear the checkbox that is next to the field at the top of the list and then select the checkboxes next to the columns you want to show.
3. Ten seconds after you have made your selection, your grid configuration for this window is saved so that the next time you open this window it will display the same selections you picked in step 2.

1.3.2. Sort data in a grid

You can change the order of the rows in a grid by sorting the data in one of the columns in either ascending or descending alphanumeric order.

When you sort the data in a column, it applies only to the current page.

You can sort the data in a column using the arrows to the right of the column name. Click the up arrow to sort the column in ascending alphanumeric order or click the down arrow to sort the column in descending alphanumeric order.

The grids also allow multiple column sort. To do this, keep the **Shift** key pressed and click on the sort arrows of other columns.

1.3.3. Filters

You can filter the list of items in a grid by one or multiple columns. When one or more filters are applied to a grid, they are saved and applied to all pages of the grid.

Define a filter by selecting the name of a visible column in the grid, selecting an operator, and then either selecting or entering a value.

Select the column for a filter from a dropdown field that contains a list of all the visible columns in the grid. By default, the field is set to the name of the first visible column in the grid, but you can select the name of a different column from the list.

After you select a column for the filter, select the operator from a dropdown field that contains a list of the standard operators that can be used with the selected column. The operators that are available depend on the data type of the selected column.

The following table lists the operators that are available for each data type:

Data Type	Operator
Boolean	• is equal to • is not equal to
Date	• is equal to • is not equal to • is less than • is greater than • between
Numeric	• is equal to • is not equal to • is less than • is greater than • in • between
String	• is equal to • is not equal to • in • ends like • starts like • contains

After you select the column and operator, select a value from a dropdown list or manually enter a value. If the values for the selected column are masked, you are required to manually enter the value.

You can filter a sorted list of items. The sort criteria remain in place after a filter is applied, and it remains in place

after a filter is removed.


1.3.3.1. Define, apply, and remove filters

You can define one or more filters and apply them to the list of items in a grid. You can also remove filtering from a grid.

1. Click the **Filter** icon (.

The filter panel opens containing three fields: Column, Operator, and Value. The Column field is automatically filled with the name of the first visible column in the grid.

2. On the filter panel, do the following:
 - a. If you do not want to define a filter using the first visible column in the grid, select the name of a different column from the list. The list includes the names of all the visible columns in the grid and all hidden columns. There is a **Hidden** icon next to the hidden columns in the list. The following example indicates that Notification Enabled is a hidden column.



Do not select the name of a column that is empty.

- b. Select an operator from the list. The operators that are available depend on the data type of the selected column. See the table in [Filters](#) for a list of the operators for each data type.
3. Select a value from the list, or manually enter a value. The values displayed in the selection field are from the current page. Click the button at the end of the Value field to change the field from a dropdown list to a manual entry field, or from a manual entry field to a selection field.

NOTE

If you want to use a value that is masked in the grid, you must enter it manually. If you selected the between operator, you must select or enter two values to define the range.

4. If you want to define another filter, click **+ Add Filter**. You can define as many filters as you want.

If you decide that you do not want to apply the filter or filters you have defined, you can click **Remove**. The filter panel will look as it did when you first opened it. There will be only one row of fields, and the Column field will be automatically set to the name of the first column in the grid.

5. When you are finished defining the filter or filters, click **APPLY** to apply them to the grid. The filter or filters are saved and automatically applied to all pages of the grid. An orange dot appears above the Filter icon to indicate that the filter or filters have been applied.
6. If after applying the filter or filters, you decide that you no longer want them applied to the grid, click **Remove**. The filter panel will look as it did when you first opened it. There will only be one row of fields, and the Column field will be automatically set to the name of the first column in the grid. The grid will no longer be filtered, and the orange dot on the Filter icon will disappear.

1.3.4. Reorder columns in a grid

You can change the order in which the columns in a grid are displayed.

1. Find a column you want to move.
2. Click in the column heading and hold the mouse button down.
3. Drag the column to its new location in the grid.
4. Release the mouse button. The column is displayed in the new location in the grid.
5. Repeat steps 1 - 4 for each column you want to move. Ten seconds after you have finished moving columns, your grid configuration for this window is saved so that the next time you open this window it will display the columns in the same order.

1.3.5. Page through multipage grids

The page size determines the maximum number of rows that can be shown on a single page of a grid. For example, if the **Page size** field is set to 50, no more than 50 rows can be shown on a single page of that grid. If there are more than 50 rows available to be shown, the additional rows are shown on a subsequent page or subsequent pages of the grid.

The grids on some screens indicate the total number of rows that are available to be shown on the grid in the bottom left corner of the grid.

For example, if the **Page size** field is set to 50 and there are 80 rows available, the following appears in the bottom left of the first page of the grid: "1 - 50 of 80." If you click the **Next Page (>)** button, the next 30 rows are shown on the next page of the grid, and the following appears in the bottom left corner of the grid: "51 - 80 of 80."

1.3.5.1. IgnoreTotalCount

The IgnoreTotalCount configuration parameter in the ar_ui_element_config table can be used to prevent the system from displaying the total count. It is enabled by default for specific grids on the Review screen. For example, if the **Page size** field is set to 50 and 80 rows are available, the following appears in the bottom left of the first page of the grid: "1 - 50." If you click the **Next Page (>)** button, the next 30 rows are shown on the next page of the grid, and the following appears in the bottom left corner of the grid: "51 - 80."

IgnoreTotalCount is enabled by default for the following grids on the Review screen for the Card, Account, Customer, Terminal, Employee, UAID, and Merchant dimensions:

- All Transactions
- Marked Transactions
- Contextual Marked Transactions

- Alerted Transactions
- Action History

IgnoreTotalCount is also enabled by default for the All Transactions grid on the Review screen for the cross dimensions (Payee Account, Device ID, and IP Address).


Customers can also enable the IgnoreTotalCount configuration parameter for the Profile Tables.

NOTE

The IgnoreTotalCount configuration parameter cannot be changed from the user interface. It can be changed only from the database.

1.3.5.2. Previous page and Next page buttons

The **Previous Page** (<) and the **Next Page** (>) buttons enable you to page backward and forward, respectively, through the pages of a multipage grid. The buttons appear in the bottom left of the grid, between the text indicating which rows are shown and the **Page size** field, as shown below:




The **Previous Page** button is disabled when you are on the first page or only page of a grid.

The **Next Page** button is disabled if the total number of rows available to be shown on the grid is less than the page size.

If you click **Next Page** when the total number of rows available on the grid is equal to the page size, the following message appears: "You are currently on the last page of the grid."

1.3.6. Modify page size (number of rows displayed)

To modify the number of rows that are displayed on each page of a grid, click the down arrow in the **Page Size** field to select a different number from the list. You can display 5, 10, 25, 50, or 100 rows.



When you change the number of rows displayed on one page of the grid, it is changed for all pages of the grid. For example, if there are 18 rows of data, and you change the page size from 10 to 5, then pages 1 through 3 will display 5 rows of data each and page 4 will display the last 3 rows of data.


1.3.7. Refresh data in a grid

You can refresh data in a grid by clicking the **Refresh** icon ()

1.3.8. Printing pages in the Web UI

Use your browser's print function to print pages from the Analysis and Review user interface. Adjust the default settings to obtain the desired result. For example, you could change the layout from "Portrait" to "Landscape" and reduce the size of the image with a "Custom" scale option. You may also want to reduce the size of the margins.

The following image shows selections that allow the entire Review page to be printed. The Layout field is set to "Landscape."



If you are planning to print the Role Management page and do not need to print the navigation pane, you could collapse the navigation pane before selecting your browser's print function.

1.3.9. Context menu and selection toolbar

Actions performed on items listed in a grid can be performed from either the context menu or the selection toolbar.

The following images shows the selection toolbar that appears at the bottom of the window when a user selects an item in the grid. In this case, it is the **Edit**, **Delete**, and **Copy to Clipboard** icons. The image also shows the context menu, which is displayed when a user selects an item in a grid and right-clicks. In this case, the **Edit**, **Delete**, and **Copy to Clipboard** icons and their descriptions are displayed in the context menu.

ACI

DASHBOARD

REPORTS

CONFIGURATIONS

RISK STRATEGY & CONTROL

English

admin

Search

SYSTEM CONFIGURATION

Display Management

Screen Configuration

Auto Text

Data Definitions

Localization

Data Management

System and Application

ACCESS MANAGEMENT

Configuration / System Configuration / Display Management / Auto Text

Auto Text

The Auto Text window lists the auto texts that have been defined and the action(s) and dimension(s) for which each can be used.

Actions

Select actions

+

||

⌵

↺

↻

Help

Actions	Auto Text	Dimensions	Created ...	Created By	Last Modified	Last Modified
☒ Forward	Custom aut...	Employee	2020-10-21...	Default Adm...		
Block	Cardholder r...	Card, Merch...	2020-10-21...	Default Adm...		
All Actions	Customer n...	Card, Merch...	2020-10-21...	Default Adm...		
Reminder	Custom aut...	User Accou...	2020-10-21...	Default Adm...		
Reminder	Custom aut...	Card	2020-10-21...	Default Adm...		

1 - 50 of 86

Page Size 50

☒ 1 selected

Deselect All

✎

🗑

📄

Shift + X to deselect all

Edit Auto Text

Delete Auto Text

Copy to clipboard

Ctrl-C

NOTE

Most of the instructions in this guide only mention the selection toolbar. However, the context menu is available, and you may use it or the selection toolbar.

1.3.10. Copy to clipboard

To copy one or more items from a grid to the clipboard, select the corresponding checkbox or checkboxes, and then click the **Copy to clipboard** icon (shown below) in the selection toolbar.

The following is an example of two items copied to the clipboard and then pasted into an Excel spreadsheet.

	A	B	C	D
1	Word	Type	Description	Status
2	ALL_CONS_COLUMNS	TABLE	Keyword not allowed in queries.	TRUE
3	ALL_LOBS	TABLE	Keyword not allowed in queries.	TRUE
4				

NOTE


You cannot copy unmasked data to the clipboard with the necessary permission.

1.4. Log out of PRM

To log out of the PRM Analysis & Review user interface, click the down arrow next to your username in the top right portion of the window. When the window shown below opens, click **Logout**.

ACI Worldwide
Real-Time Payments

13




Organization: CUSTOMER11
Last Login: 2022-05-12 12:07:56
Last Failed Login: NONE
Local Time: 2022-05-12 12:08:10
Server Time: 2022-05-12 13:08:10
PRM Version: PRM9.2.0.0

[Change Password](#)
[Logout](#)

When you log out, an empty Login window opens. You can either log in again or close your browser.

1.5. Change your password

To change your password, click the down arrow next to your username in the top right portion of the window. When the window shown below opens, click **Change Password**.



Organization: CUSTOMER11
Last Login: 2022-05-12 12:07:56
Last Failed Login: NONE
Local Time: 2022-05-12 12:08:10
Server Time: 2022-05-12 13:08:10
PRM Version: PRM9.2.0.0

[Change Password](#)
[Logout](#)

When the CHANGE USER PASSWORD window opens, enter your current password in the **Your Current Password** field and your new password in the **New Password** and **Confirm Password** fields, then click **SAVE**.

CHANGE USER PASSWORD

Your Current Password

Introduce your password to enable making changes

New Password

Confirm Password

SAVE

CANCEL

The value entered in the New Password field cannot be the same as your current password, and the value entered in the Confirm Password field must match the value entered in the New Password field. Your new password must also meet the password requirements configured for your system:

NOTE

- Your new password cannot contain fewer characters than the configured minimum number, and it cannot contain more characters than the configured maximum number.
- Your new password must match the RegEx for passwords, which is configured on the Security Validation Settings window.
- If the PasswordEQId parameter is set to 1 on the General Settings window, your new password cannot be the same as your username.
- The Password_History parameter set on the General Settings window determines how many past passwords are stored by the system. For example, if the parameter is set to 3, the system will store your last three passwords. You cannot make one of the stored passwords your new password.


Refer to the *Root Administrator and System Administrator User Guide* for information on the Security Validation Settings and General Settings.

1.6. Change your expired password

If the Password_New_Expire parameter is set to 1, users will be required to change their passwords the first time they log in to the Analysis and Review user interface. The value in the PasswordExpire_Days parameter determines the number of days that users' passwords are valid. When the specified number of days is exceeded, users are required to change their passwords. These two parameters are set on the General Settings window. Refer to the

Root Administrator and System Administrator User Guide for more information.

When your password expires, the CHANGE YOUR CREDENTIALS window opens. The first field on the window identifies your organization. The second field contains your username.



To change your password, enter your expired password in the **Old Password** field, enter your new password in the **New Password** and **Reenter New Password** fields, and then click **CHANGE PASSWORD**.

1.7. Main menu

The main menu is displayed after a successful login. Its contents depend on your role and the permissions assigned to that role.

The main menu options for Team Administrators are:

- DASHBOARD
- SEARCH
- REVIEW
- REPORTS
- CONFIGURATIONS
- RISK STRATEGY & CONTROL

The main menu options for Supervisors are:

- DASHBOARD
- SEARCH
- REVIEW

- REPORTS
- RISK STRATEGY & CONTROL

Reports are described in the *Reports User Guide*.

NOTE

Subsequent topics describe the other menu items and the associated windows and functions. See [Configurations](#) and [Risk Strategy & Control](#) for information about the associated windows and functions.

1.8. Landing page


After you log in to PRM successfully, your landing page is displayed.

The landing page identifies your organization, the time of your last successful login, the current server time, and your local time.

The landing page contains two other sections:

- **Recently Visited** - This section displays tiles for the pages you recently accessed. This section can contain up to four tiles. Click a tile to go directly to that page.
- **Useful Links** - This section displays tiles for other pages to which you have access. This section can contain up to eight tiles. Click a tile to go directly to that page.

To return to the landing page from any other page in the Web UI, click the logo in the upper left corner of the window.



2. Dashboard

Your dashboard is shown each time you log in. You can return to your dashboard from any page in the PRM Analysis and Review user interface by clicking **DASHBOARD** in the main menu.

2.1. Dark mode

A toggle switch is available to logged-in users enabling them to switch between light and dark mode versions of the web application.

The user theme selection (light vs dark mode) is saved in the AR database so that every time the user configurations are loaded, the theme is also included.

NOTE

The login page is always in light mode because the browser (Google Chrome and Microsoft Edge) has the corresponding dark mode configurations.

2.2. Widgets

You can customize your dashboard by adding a pre-defined or custom widget. Widgets are configured within the PRM Analysis and Review user interface. Once configured and generated, the widgets are displayed on the dashboard where you can edit, sort, refresh, or remove them.

If you have the *Manage Widgets for Team Members* permission, you can assign a widget to one or more users when you create the widget. Users can modify and remove assigned widgets from their dashboards.

2.2.1. Monitor KPIs

Starting in PRM 9.2.4, users can monitor KPIs for rules, queues, and computed variables using the RT Rules KPI and Rules KPI report widgets. The report widgets provide the following types of information:

- KPI logging time, based on the database system date and time
- Rule ID
- Rule Name (on the Rules KPI report widget only)
- Type
- Last Deployment/Undeployment Date and Time
- Average execution time of a rule, queue, or computed variable
- Minimum execution time for a rule, queue, or computed variable
- Maximum execution time for a rule queue, or computed variable
- Standard deviation for a rule, queue, or computed variable
- 95% execution time average for a rule, queue, or computed variable
- Total count of transactions that triggered the queue or computed variable SQL per minute

The following is a sample Rule KPIs report widget:

Time	Rule Id	Rule Name	Type	Last D...	AG Process Id	Average	Min	Max	Count	Standard Deviation	95 Percentile	Total Execution Time
2023/07/25 12:56	98	ruleAccount1	Rule-NRT		AGNRT01	0.0000	0.0000	3.0000	20	0.6038	1.4316	3.0000
2023/07/25 12:56	104	ruleMerchant1	Rule-NRT		AGNRT01	0.0000	0.0000	0.0000	20	0.0000	0.0000	0.0000
2023/07/25 12:56	106	ruleTerminal	Rule-NRT		AGNRT01	0.0000	0.0000	0.0000	20	0.0000	0.0000	0.0000
2023/07/25 12:56	118	ruleMerchant2	Rule-NRT		AGNRT01	0.0000	0.0000	0.0000	17	0.0000	0.0000	0.0000
2023/07/25 12:56	112	ruleAccount2	Rule-NRT		AGNRT01	0.0000	0.0000	0.0000	17	0.0000	0.0000	0.0000
2023/07/25 12:56	114	ruleCard2	Rule-NRT		AGNRT01	0.0000	0.0000	0.0000	17	0.0000	0.0000	0.0000
2023/07/25 12:56	100	ruleCard1	Rule-NRT		AGNRT01	0.0000	0.0000	0.0000	20	0.0000	0.0000	0.0000
2023/07/25 12:56	224	NonInTransNRT	Rule-NRT		AGNRT01	0.0145	0.0000	3.0000	413	0.2083	0.4297	5.0000
2023/07/25 12:56	120	ruleTerminal2	Rule-NRT		AGNRT01	0.1765	0.0000	3.0000	17	0.7059	1.5600	3.0000
2023/07/25 12:50	118	ruleMerchant2	Rule-NRT		AGNRT01	0.0000	0.0000	0.0000	73	0.0000	0.0000	0.0000
2023/07/25 12:50	98	ruleAccount1	Rule-NRT		AGNRT01	0.0000	0.0000	0.0000	81	0.0000	0.0000	0.0000
2023/07/25 12:50	114	ruleCard2	Rule-NRT		AGNRT01	0.0000	0.0000	0.0000	73	0.0000	0.0000	0.0000
2023/07/25 12:50	224	NonInTransNRT	Rule-NRT		AGNRT01	0.0147	0.0000	4.0000	1499	0.2156	0.4373	22.0000
2023/07/25 12:50	104	ruleMerchant1	Rule-NRT		AGNRT01	0.0004	0.0000	4.0000	81	0.4417	0.9151	3.9998
2023/07/25 12:50	106	ruleTerminal	Rule-NRT		AGNRT01	0.0000	0.0000	0.0000	81	0.0000	0.0000	0.0000
2023/07/25 12:50	112	ruleAccount2	Rule-NRT		AGNRT01	0.0011	0.0000	3.0000	73	0.3487	0.7246	3.0003
2023/07/25 12:50	100	ruleCard1	Rule-NRT		AGNRT01	0.0004	0.0000	4.0000	81	0.4417	0.9151	3.9998
2023/07/25 12:50	120	ruleTerminal2	Rule-NRT		AGNRT01	0.0011	0.0000	3.0000	73	0.3487	0.7246	3.0003

The calculations are performed per minute (every 1 minute), within the entry and rules/queues procedures. They are performed per AG instance, as the aggregation is done by the AG. The system pre-aggregates the data and provides an average of the total execution duration per rule.

The execution time is calculated based on the SYSDATE value.

The statistics are stored in the AG_RULES_KPI_LOG table so that they can later be queried or displayed in the UI. The cleanup period is set by default to 3 days.

The functionality is enabled per system via a parameter in the SystemConfig table, which users can access from General Settings window. The name of the parameter is RulesKPIThresholdMs. If the parameter is set to -1 (Disabled), the rules KPIs are not calculated. The default value for the parameter is 300 milliseconds.

NOTE

Rules KPIs are collected only if the 95 percentile will exceed value in RulesKPIThresholdMs system config parameter.

A refresh parameter in the APPLCNFG table determines how often the system will check if the rule KPI functionality is enabled. The name of the parameter is risk.gateway.enableRulesKpi.update.frequency. The default value for the parameter is 60 seconds.

See [Add the RT Rules KPIs report widget](#) and [Add the RT Rules KPIs report widget](#) topics for instructions on adding the report widgets to your dashboard.

2.2.2. Add a widget

Follow these steps to add a widget:

1. Click **+ ADD WIDGET** link on the dashboard to open the Add WIDGET window.
2. In the **Report Type** field, select a report type from the dropdown list.

NOTE

The report types are listed by category. The categories are Analyst Performance, Rule and Queue, and System Performance.

The Analyst Performance report is the only report type in the Analyst Performance category.

The Rule and Queue category consists of the following report types:

- Near-Real Time Rule Performance
- Queue Status
- Real-Time Rule Performance

The System Performance category consists of the following report types:

- RT Rule KPIs
- Rule KPIs
- Transaction Statistics

After you select the report type, the ADD WIDGET window expands. Additional fields are displayed to enable you to set the parameters for the selected report type.

2.2.2.1. Add the Analyst Performance report widget

The Analyst Performance report lists the following:

- Analyst usernames - If the analyst has multi-team reporting assigned, all analysts from the teams are listed.
- Status (Active or Inactive) - The status is based on whether the analyst took action on a dimension ID within the configured number of minutes.
- Date and time - The date and time the analyst took an audited action on a dimension ID that belongs to the corresponding portfolio.
- Queues to which analysts are assigned.
- Queue type for the corresponding queue.
- Portfolios to which the queues are assigned.
- Count of the alerts analysts have worked from each queue in the selected time interval for the widget.

NOTE

Alerts entering multiple queues are counted. Alerts on which forwards or reminders are performed are considered worked.

Follow these steps to set the parameters for the Analyst Performance widget and to add it to your dashboard.

1. The default time length of inactivity for an analyst's status to be reported as inactive is 15 minutes. If you want to define a different time length of inactivity, in the **Inactive Time Limit (minutes)** field, type or use the up and down arrows to set the number of minutes.
2. From the drop-down list in the **Portfolio** field, select the portfolio whose transactions you want to be included in the report.

NOTE

You can select multiple portfolios to be displayed in the widget. Only the portfolios of the analyst's team are listed for selection. However, if the analyst has multi-team reporting assigned, the portfolios of all the analyst's teams are listed for selection.

3. From the drop-down list in the **Queue Type** field, select one or more queue types to include in the widget.

Queue types available are:

- System Queue
- Smart Queue
- Matching Queue
- Batch (End of Day) Queue
- Matching (End of Day) Queue
- Group Queue

4. From the drop-down list in the **Report Interval** field, select the time interval to be included in the report.
5. The default refresh rate for the widget is 300 seconds. If you want a different refresh rate, type it in the **Refresh Rate** field.

NOTE | Use the up and down arrows to increase or decrease the seconds.

6. The system automatically updates the **Widget Label** field (the name that will appear at the top of the widget). It appends the name of the portfolio and the report interval you selected to the report name, for example, Analyst Performance/PortfolioMerchant1/Past Hour. If you want a different label, type it in the **Widget Label** field.
7. If you have the *Manage Widgets for Team Members* permission, you have the option to use the **Apply Widget to Team Members** field to select one or more users to which the new widget applies.
8. If you need to add color coding to the columns, click **+ADD RULE**.
 - a. Select the Color from the dropdown.
 - b. Select the Column to which to apply the color.
 - c. Select the Operator from the dropdown.
 - d. Enter the Value that will trigger the column to be highlighted.

NOTE | Click **+ ADD RULE** to add another color-coding rule.

9. Click **GENERATE** to create the widget and add it to your dashboard.

2.2.2.2. Add the Near Real-Time Rule Performance report widget

The Near Real-Time Rule Performance report provides the following for the near real-time rules in the selected portfolio:

- Rule name

NOTE | Deployed and un-deployed rules are displayed.

- Portfolio to which the rule is assigned and calculations are done
- Status (deployed or un-deployed)
- Number of alerts in the specified time interval
- Percentage per mille (meaning parts per 1000 - ‰) of the alerted transactions for the portfolio

Follow these steps to set the parameters for the Near Real-Time Rule Performance widget and to add it to your dashboard.

1. From the drop-down list in the **Portfolio** field, select the portfolio whose rules you want to be included in the report.

NOTE

You can select multiple portfolios. However, only the portfolios for the analyst's team are displayed. If the analyst has multi-team reporting assigned, all portfolios for each team are displayed.

2. From the drop-down list in the **Report Interval** field, select the time interval to be included in the report.

The time interval refers to the transaction processing date.

3. The default refresh rate for the widget is 300 seconds (5 minutes). If you want a different refresh rate, type it in the **Refresh Rate** field.
4. The system automatically updates the **Widget Label** field (the name that will appear at the top of the widget). It appends the name of the portfolio and the report interval you selected to the report name, for example: Near Real-Time Rule Performance/PortCard1/Past 2 Days. If you want a different label, type it in the **Widget Label** field.
5. If you have the *Manage Widgets for Team Members* permission, you have the option to use the **Apply Widget to Team Members** field to select one or more users to which the new widget applies.
6. If you need to add color coding to the columns, click **+ADD RULE**.
 - a. Select the Color from the dropdown.
 - b. Select the Column to which to apply the color.
 - c. Select the Operator from the dropdown.
 - d. Enter the Value that will trigger the column to be highlighted.

NOTE

Click **+ ADD RULE** to add another color-coding rule.

7. Click **GENERATE** to create the widget or click **CANCEL** to close the **ADD WIDGET** pop-up window without creating the widget.

2.2.2.3. Add the Queue Status report widget

The Queue Status report lists the following data:

- Name of the queue.
- Type of queue.
- The selected portfolio to which the queue is assigned, for which the depth is calculated.
- Total number of analysts assigned to each queue.

NOTE

Only the analysts of a team are listed; however, if an analyst has multi-team reporting assigned, all analysts on all teams are listed.

- Number of active analysts assigned to each queue.

NOTE The time interval of in activity after which the user is considered inactive is configurable.

- Number of alerts in each queue (Depth)
- Transaction amounts for the alerts in each queue.
- How long ago the oldest alert was added to each queue.

Follow these steps to set the parameters for the Queue Status widget and to add it to your dashboard.

1. In the **Inactive Time Limit (minutes)** field, type the number of minutes after which you want analysts to be reported as inactive.

NOTE You can use the arrows to increase or decrease the number of minutes.

2. From the drop-down list in the **Portfolio** field, select the portfolio you want to be included in the report.

NOTE You can select multiple portfolios. Only the portfolios for the analyst's team are listed. If the analyst has multi-team reporting assigned, the portfolios of all the analyst's teams are listed.

3. From the drop-down list in the **Queue Type** field, select the queue types you want to be included in the report.
4. The default refresh rate for the widget is 300 seconds (5 minutes). If you want a different refresh rate, type it in the **Refresh Rate** field.

Use the arrows to increase or decrease the number of seconds.

NOTE The data for the widget will be updated with the frequency of the calculation job. So, the refresh rate should be equal to or greater than the calculation frequency; otherwise, after refreshing the same data will be displayed.

5. The system automatically updates the **Widget Label** field (the name that will appear at the top of the widget). It appends the name of the portfolio you selected to the report name, for example, Queue Status/PortfolioMerchant1. If you want a different label, type it in the **Widget Label** field.
6. If you have the *Manage Widgets for Team Members* permission, you have the option to use the **Apply Widget to Team Members** field to select one or more users to which the new widget applies.
7. If you need to add color coding to the columns, click **+ADDRULE**.
 - a. Select the Color from the drop-down list.
 - b. Select the Column to which to apply the color.
 - c. Select the Operator from the drop-down list.
 - d. Enter the Value that will trigger the column to be highlighted.

NOTE Click **+ ADD RULE** to add another color-coding rule.

8. Click **GENERATE** to create the widget and add it to your dashboard.

2.2.2.4. Add the Real-Time Rule Performance report widget

The Real-Time Rule Performance report provides the following for the real-time rules in the selected portfolio:

- Rule name

NOTE Deployed and un-deployed rules are displayed.

- Portfolio to which the rule is assigned and calculations are done
- Status (deployed or un-deployed)
- Number of alerts in the specified time interval
- Percentage of alerted transactions for the portfolio
- Percentage of declined transactions for the portfolio
- Percentage of referrals
- Sum of the amount for accepted transactions
- Sum of the amount for declined transactions
- Sum of the amount for referred transactions status information and performance data for the real-time rules in the selected portfolio.

NOTE See the *PRM Extension Guide* for information on how to extend the widget to include newly-defined RT dispositions.

Follow these steps to set the parameters for the Real-Time Rule Performance widget and to add it to your dashboard.

1. From the drop-down list in the **Portfolio** field, select the portfolio whose rules you want to be included in the report.

NOTE You can select multiple portfolios. However, only the portfolios for the analyst's team are displayed. If the analyst has multi-team reporting assigned, all portfolios for each team are displayed.

2. From the drop-down list in the **Report Interval** field, select the time interval to be included in the report.
3. The default refresh rate for the widget is 300 seconds (5 minutes). If you want a different refresh rate, type it in the **Refresh Rate** field.
4. The system automatically updates the **Widget Label** field (the name that will appear at the top of the widget). It appends the name of the portfolio and the report interval you selected to the report name, for example, Real-Time Rule Performance/PortCard1/Past 2 Days. If you want a different label, type it in the **Widget Label** field.
5. If you have the *Manage Widgets for Team Members* permission, you have the option to use the **Apply Widget to Team Members** field to select one or more users to which the new widget applies.
6. If you need to add color coding to the columns, click **+ADD RULE**.

NOTE Click **+ ADD RULE** to add another color-coding rule.

7. Click **GENERATE** to create the widget or click **CANCEL** to close the **ADD WIDGET** pop-up window without creating the widget.

2.2.2.5. Add the RT Rules KPIs report widget

The RT Rules KPIs report widget enables you to monitor the performance of the real-time rules.

Follow these steps to set the parameters for the RT Rule KPIs report and to add the widget to your dashboard.

1. From the drop-down list in the **Analytic Gateway** field, select one or more analytic gateway processes whose activity you want to be included in the report.
2. From the drop-down list in the **Report Interval** field, select the time interval to be included in the report.
3. From the drop-down list in the **Rule Name** field, select the rule or rules to be included in the report.
4. The default refresh rate for the widget is 300 seconds(5 minutes). If you want a different refresh rate, type it in the **Refresh Rate** field.
5. The system automatically updates the **Widget Label** field (the name that will appear at the top of the widget). It appends the name of the selected report interval, analytic gateway process or processes, and rule or rules to the report name. If you want a different label, type it in the **Widget Label** field.
6. If you have the *Manage Widgets for Team Members* permission, you have the option to use the **Apply Widget to Team Members** field to select one or more users to which the new widget applies.
7. If you want to add color coding to the columns, click **+ADD RULE**.
 - a. Select the **Color** from the dropdown list.
 - b. Select the **Column** to which you want the color applied.
 - c. Select the **Operator** from the dropdown.
 - d. Enter the **Value** that will trigger the column to be highlighted in the selected color.

NOTE Click **+ ADD RULE** to add another color-coding rule.

8. Click **GENERATE** to create the widget and add it to your dashboard.

2.2.2.6. Add the Rules KPIs report widget

The Rules KPIs report widget enables you to monitor the performance of the NRT rules.

Follow these steps to set the parameters for the Rule KPIs report and to add the widget to your dashboard.

1. From the drop-down list in the **Analytic Gateway** field, select one or more analytic gateway processes whose activity you want to be included in the report.
2. From the drop-down list in the **Report Interval** field, select the time interval to be included in the report. The default is Past Hour.
3. From the drop-down list in the **Type** field, select one or more of the following:
 - Rule-NRT
 - Queue-NRT
 - Aggregate-NRT

4. From the drop-down list in the **Rule Name** field, select the rule or rules to be included in the report.
5. The default refresh rate for the widget is 300 seconds (5 minutes). If you want a different refresh rate, type it in the **Refresh Rate** field.
6. The system automatically updates the **Widget Label** field (the name that will appear at the top of the widget). It appends the name of the selected report interval, analytic gateway process or processes, and rule or rules to the report name. If you want a different label, type it in the **Widget Label** field.
7. If you have the *Manage Widgets for Team Members* permission, you have the option to use the **Apply Widget to Team Members** field to select one or more users to which the new widget applies.
8. If you want to add color coding to the columns, click **+ADD RULE**.
 - a. Select the **Color** from the dropdown list.
 - b. Select the **Column** to which you want the color applied.
 - c. Select the **Operator** from the dropdown.
 - d. Enter the **Value** that will trigger the column to be highlighted in the selected color.

NOTE Click **+ ADD RULE** to add another color-coding rule.

9. Click **GENERATE** to create the widget and add it to your dashboard.

2.2.2.7. Add the Transaction Statistics report widget

The Transaction Statistics report lists the number of transactions processed and the transaction per second (TPS) rate for each hour of each day in the selected report interval and selected KPI and Analytic Gateway process combination.

Follow these steps to set the parameters for the Transaction Statistics report and to add the widget to your dashboard.

1. From the drop-down list in the **Analytic Gateway** field, select one or more analytic gateway processes whose activity you want to be included in the report.
2. The default refresh rate for the widget is 300 seconds (5 minutes). If you want a different refresh rate, type it in the **Refresh Rate** field.
3. From the drop-down list in the AG KPI name field, select one or more KPIs.
4. From the drop-down list in the **Report Interval** field, select the time interval to be included in the report.
5. The system automatically updates the **Widget Label** field (the name that will appear at the top of the widget). It appends the name of the selected KPI or KPIs, the selected analytic gateway process or processes, and the report interval you selected to the report name, for example, TransactionStatistics/Txn Start to End /AGNRT01/Past Hour. If you want a different label, type it in the **Widget Label** field.
6. If you have the *Manage Widgets for Team Members* permission, you have the option to use the **Apply Widget to Team Members** field to select one or more users to which the new widget applies.
7. If you want to add color coding to the columns, click **+ADD RULE**.
 - a. Select the **Color** from the dropdown list.
 - b. Select the **Column** to which you want the color applied.
 - c. Select the **Operator** from the dropdown.

d. Enter the **Value** that will trigger the column to be highlighted in the selected color.

NOTE Click **+ ADD RULE** to add another color-coding rule.

8. Click **GENERATE** to create the widget and add it to your dashboard.

2.2.3. Edit a widget

To edit a widget on your dashboard, click the **Edit** icon in the upper-right corner of the widget. The EDIT WIDGET window for the report type opens. Modify the values in the fields, as desired. When you finish with your modifications, click **GENERATE** to replace the existing widget.

NOTE

Depending on which fields you modify, the system may change the value in the Report Label field to reflect your modifications. You can override the system-provided label by typing a different label in that field.

2.2.4. Sort a widget

You can sort columns on a widget the same way you sort columns on other grids, that is, by clicking the up or down arrow to the right of the column heading.

The grids also allow multiple column sort. To do this, keep the **Shift** key pressed and click on the sort arrows of other columns.

2.2.5. Refresh a widget

To refresh the data displayed in a widget, click the **Refresh** icon () located in the upper-right corner of the widget.

2.2.6. Remove a widget

To remove a widget from your dashboard, click the **Remove** icon () located in the upper-right corner of the widget.

2.2.7. Custom widgets

Custom widgets are created by Database Administrators having the required permissions. See the *Add Custom Widgets* topic in the **Configuration and Extension Guide**.

3. Search

The search function enables you to select a dimension and specify search criteria for the dimension ID or dimension IDs you want to review.

NOTE

If you are searching for a single dimension ID and you know the dimension and dimension ID for it, you can use the Open Dimension ID link on the DASHBOARD to quickly locate and open the dimension ID.

When you click SEARCH in the main menu, the Search window opens. Select the tab for the dimension you want to search, and then specify the search criteria for the dimension ID or dimension IDs you want to review.

Any dimension IDs for the selected dimension that match the specified search criteria are displayed in a grid below the search fields.

PAN	Address	City	State/Province	Country	Postal Code	Home Phone	Mobile Phone	Email	DOB
123414500147131	Address 1 - 222	Omaha	NJ	DEN	52627	0043 22234567896	047 713485496	email_71@yahoo.co	1963-06-13
1234252729817118	Address 1 - 823	Salinas	FR	USA	69960	0047 22234567818	040 713485489	email_71@yahoo.co	1949-03-27
1234509490027124	Address 1 - 116	Oakland	FR	FRA	24646	0041 22234567847	042 733485423	email_71@yahoo.co	1980-10-12

The dimension IDs in the search results grid are hyperlinks. You can click one of the hyperlinked dimension IDs to open the dimension ID in the Review screen.

The Search window includes links for opening the OPEN DIMENSION ID and RECENT DIMENSION IDS windows,

and there is a button labeled GET NEXT ALERT that you can click to open the next alert in the Review screen.

NOTE

Refer to the *Fraud Analyst User Guide* for the following information:

- Lists of the search fields and operators displayed by default for each dimension.
- Lists of the search fields that are available by default for each dimension.
- A table listing the possible data types for search fields and the operators that are available for each data type.

4. Review

When you click **REVIEW** in the main menu and dropdown submenu of options is displayed. The options are:

- REVIEW ALERTS & DIMENSION IDS
- PENDING ALERTS
- FORWARDS & REMINDERS

NOTE

The PENDING ALERTS and FORWARDS & REMINDERS options are described in this guide. Refer to the *Fraud Analyst User Guide* for detailed information on the REVIEW ALERTS & DIMENSION IDS option.

4.1. Pending alerts

When you select **PENDING ALERTS** from the REVIEW submenu, the Pending Alerts window opens. The Pending Alerts window enables you to view the pending alerts that are in the portfolios assigned to your team. From the Pending Alerts window, you can also open alerts or open the dimension ID of an alert in the Review screen. You can export alert data or copy it to the clipboard, and you can delete alerts.


When the Pending Alerts window opens, you see only the Portfolios field and the **Close all queues** link.

Click the down arrow in the **Portfolios** field to see the list of portfolios assigned to your team. The name of each portfolio is followed by two numbers within parentheses: (*nnn* / *nnn*). The first number is the total number of alerted transactions in the portfolio's queues. The second number is the total number of alerted dimension IDs in the portfolio's queues.

When you select a portfolio from the list in the Portfolios field, the **Queues** field is shown. Click the down arrow in the **Queues** field to see a list of the queues associated with the selected portfolio. The name of each queue is followed by a number in parentheses: (*nnn*). This number is the number of alerted transactions in the queue.

When you select a queue from the list, a tab for that queue is shown. The tab contains a grid listing the pending alerts in the selected queue. If the queue is configured as a Consume and Archive queue, there is an orange line underneath the label on the tab.

The following is a sample Pending Alerts window:



Any queues that you have open on when you log off are saved for your next session. Those queues will be open on the Pending Alerts window the next time you log in.

When you select one or more alerts in the grid, the selection toolbar is shown at the bottom of the page. The following table depicts and describes each of the icons in the toolbar.

Icon	Description
	Use the Copy icon to copy selected row(s) of alert data to the clipboard.
	Use the Open Alert icon to open a selected alert in the Review screen.
	Use the OpenDimension ID icon to open the dimension ID of a selected alert in the Review screen.
	Use the Open Read-Only icon to open the dimension ID of a selected alert in read-only mode in the Review screen.
	Use the Delete Alert(s) icon to delete one or more selected alerts from the current or all queues.
	Use the Export Selection icon to export selected row(s) of alert data to an .xls or .csv file.

Each time you select a queue from the Queues field, a new tab is shown in the Pending Alerts window. Each tab contains a grid listing the pending alerts in the selected queue. To close all tabs, click the **Close all queues** link.

4.1.1. Open a pending alert

Follow these steps to open a pending alert:

1. Select **PENDING ALERTS** from the REVIEW submenu. The Pending Alerts window is displayed.
2. Click the down arrow in the **Portfolios** field to display the list of portfolios assigned to your team, then select the portfolio you want to use. The **Queues** field is displayed.

3. Click the down arrow in the **Queues** field to display the list of queues associated with the selected portfolio, then select the queue you want to use. A tab for the selected queue is displayed. The tab contains a list of the pending alerts in the selected queue.
4. Find the row containing the pending alert you want to open, then select the checkbox to the left of that row. A selection toolbar is displayed at the bottom of the window.
5. Click the **Open Alert** icon in the selection toolbar.

The selected alert opens in the Review screen.

The Review Type in the banner will be Alert. The banner will also identify the queue from which the alert was retrieved.

4.1.2. Open a dimension ID

Follow these steps to open the dimension ID of a pending alert:

1. Select **PENDING ALERTS** from the REVIEW submenu. The Pending Alerts window is displayed.
2. Click the down arrow in the **Portfolios** field to display the list of portfolios assigned to your team, then select the portfolio you want to use. The **Queues** field is displayed.
3. Click the down arrow in the **Queues** field to display the list of queues associated with the selected portfolio, then select the queue you want to use. A tab for the selected queue is displayed. The tab contains a list of the pending alerts in the selected queue.
4. Find the row containing the pending alert for the dimension ID that you want to open, then select the checkbox to the left of that row. A selection toolbar is displayed at the bottom of the window.
5. If you want to be able to take actions against the dimension ID in the alert, click the **Open Dimension ID** icon in the selection toolbar. If you want to open the dimension ID in read-only mode, click the **Open Read-Only** icon in the selection toolbar.

The selected alert opens in the Review screen.

If you use the **Open Dimension ID** icon to open the dimension ID, the Review Type in the banner will be Review. If you use the **Open Read-Only** icon to open the dimension ID, the Review Type in the banner will be Readonly, Review.

4.1.3. Delete one or more pending alerts

Follow these steps to delete one or more pending alerts from the Pending Alerts window:

1. Select **PENDING ALERTS** from the REVIEW submenu. The Pending Alerts window is displayed.
2. Click the down arrow in the **Portfolios** field to display the list of portfolios assigned to your team, then select the portfolio you want to use. The **Queues** field is displayed.
3. Click the down arrow in the **Queues** field to display the list of queues associated with the selected portfolio, then select the queue from which you want to delete one or more alerts. A tab for the selected queue is displayed. The tab contains a list of the pending alerts in the selected queue.
4. Find the row(s) containing the pending alert(s) you want to delete, then select the checkbox(es) to the left of the row(s). A selection toolbar is displayed at the bottom of the window.

5. Click the **Delete Alert(s)** icon in the selection toolbar. You are prompted to indicate whether you want to delete the alert(s) from the current queue or from all queues. After you indicate whether you want the alert(s) deleted from the current queue or from all queues, the system removes the selected alert(s) from the current queue or all queues and from the grid.

4.1.4. Copy pending alert data

Follow these steps to copy alert data from the Pending Alerts window to the clipboard.

1. Select **PENDING ALERTS** from the REVIEW submenu. The Pending Alerts window is displayed.
2. Click the down arrow in the **Portfolios** field to display the list of portfolios assigned to your team, then select the portfolio you want to use. The **Queues** field is displayed.
3. Click the down arrow in the **Queues** field to display the list of queues associated with the selected portfolio, then select the queue you want to use. A tab for the selected queue is displayed. The tab contains a list of the pending alerts in the selected queue.
4. Find the row(s) containing the pending alert data you want to copy, then select the checkbox(es) to the left of the row(s). A selection toolbar is displayed at the bottom of the window.
5. Click the **Copy** icon in the selection toolbar. The displayed data for the selected alert or alerts is copied to the clipboard. You can paste the data into an application such as Microsoft Word or Excel. If a column on the grid is empty, and you paste it into Excel, the column in Excel will contain a hyphen (-).

4.1.5. Export pending alert data

Follow these steps to export alert data to an .xls or .csv file.

1. Select **PENDING ALERTS** from the REVIEW submenu. The Pending Alerts window is displayed.
2. Click the down arrow in the **Portfolios** field to display the list of portfolios assigned to your team, then select the portfolio you want to use. The **Queues** field is displayed.
3. Click the down arrow in the **Queues** field to display the list of queues associated with the selected portfolio, then select the queue you want to use. A tab for the selected queue is displayed. The tab contains a list of the pending alerts in the selected queue.
4. Find the row(s) containing the pending alert data you want to export, then select the checkbox(es) to the left of the row(s). A selection toolbar is displayed at the bottom of the window.
5. Click the **Export Selection** icon in the selection toolbar. You are prompted to indicate whether you want to export the data to an .xls or .csv file. Depending on your permissions, you may have the option of exporting any masked data as unmasked. If you choose to export the data to an .xls file (that is, into Excel), any column in the grid that is empty will contain a hyphen (-) in the corresponding column in the Excel file.

4.2. Forwards & Reminders

When you select FORWARDS & REMINDERS from the REVIEW submenu, the Forwards & Reminders window opens. The Forwards & Reminders window contains the following tabs:

- Reminders
- Forwards sent by me
- Forwards sent to me

- My team

By default, the Reminders tab is selected when the Forwards & Reminders window opens.

4.2.1. Reminders

The Reminders tab enables you to view the reminders that you have not retrieved.

The tab contains a grid that lists the following information for each reminder:

- Type (Reminder)
- Dimension ID
- Dimension
- Reminder Date and Time
- Notes

Select one or more reminders by clicking the corresponding checkbox or checkboxes in the grid. When you select one or more reminders, a selection toolbar appears at the bottom of the window. If you select only one reminder, your action choices are Open for Review, Open & Process, Edit, and Remove. If you select more than one reminder, your action choice is Remove.

4.2.2. Forwards sent by me

The "Forwards sent by me" tab enables you to see forwards that have not been retrieved by the users to whom you forwarded them.

The tab contains a grid that lists the following information for each forward:

- Type (Forward)
- Dimension ID
- Dimension
- Forward Date and Time
- Forwarded By (your full name)
- Forwarded To (the full name of the user to whom you forwarded it)
- Notes

Select one or more forwards by clicking the corresponding checkbox or checkboxes in the grid. When you select one or more forwards, a selection toolbar appears at the bottom of the window. If you select only one forward, your action choices are Open for Review, Edit, and Remove. If you select more than one forward, your action choice is Remove.

4.2.3. Forwards sent to me

The "Forwards sent to me" tab enables you to see the forwards sent to you that you have not retrieved.

The tab contains a grid that lists the following information for each forward:

- Type (Forward)
- Dimension ID
- Dimension
- Forward Date and Time
- Forwarded By (the full name of the user who forwarded it to you)
- Forwarded To (your full name)
- Notes

Select one or more forwards by clicking the corresponding checkbox or checkboxes in the grid. When you select one or more forwards, a selection toolbar appears at the bottom of the window. If you select only one forward, your action choices are Open for Review, Open & Process, Edit, and Remove. If you select more than one forward, your action choice is Review.

4.2.4. My team

The "My team" tab enables team administrators, supervisors, and users with custom roles to which the My Team permission is assigned to see the pending reminders and forwards assigned to their team. This tab, however, does not include the current user's pending forwards and reminders.

The "My team" tab contains a grid that lists the following information for each pending forward and reminder:

- Type (Forward or Reminder)
- Dimension ID
- Dimension
- Forward Date and Time or Reminder Date and Time
- Forwarded By (the full name of the user who forwarded it)
- Forwarded To (the full name of the user to whom it was forwarded)
- Notes

The Forwarded By and Forwarded To columns are empty for reminders.

Select one or more forwards and/or reminders by clicking the corresponding checkbox or checkboxes in the grid. When you select one or more forwards and/or reminders, a selection toolbar appears at the bottom of the window. If you select only one forward or reminder, your action choices are Open for Review, Edit, and Remove. If you select more than one forward and/or reminder, your action choice is Remove.

4.2.5. Edit a reminder

When you select a reminder from the Reminders tab and click the **Edit** icon, the EDIT REMINDER window opens.

From the EDIT REMINDER window, perform these steps to edit the selected reminder.

1. (Optional) Change the descriptive text in the **Description** field.
2. (Optional) Change the date and time in the **Remind at** fields.

You can type in the date box, or you can click on the calendar icon next to the date to select the date from the calendar. You can also type in the time boxes or use the up and down arrows to scroll through the times. Clicking on the box to the right of the time fields allows you to toggle between AM and PM.

3. Click **EDIT REMINDER** to save the reminder and close the window.

4.2.6. Edit a forward

When you select a forward from the **Forwards sent by me** tab, the **Forwards sent to me** tab, or the **My Team** tab, and click the **Edit** icon in the selection toolbar at the bottom of the window, the EDIT FORWARD window opens.

From the EDIT FORWARD window, perform these steps to edit the selected forward.

1. Select a user from the dropdown list in the **Forward to** field.

If you are editing a forward sent by you, this step is optional. If you are editing a forward sent to you, this field will be empty, and you must select a user from the dropdown list.

2. (Optional) Edit the text in the **Memo** field.
3. Edit the date and time for the forward.

If you are editing a forward sent to you, you must either select the **Immediately** option button or change the **Forward at** fields to a future date and/or time.

If you are editing a forward sent by you, and the **Forward at** fields contain a future date and/or time, this step is optional.

To change when the forward will be sent, select either the **Immediately** or the **Forward at** option button to indicate when the forward should happen. If you select **Forward at**, selection boxes appear that enable you to pick the date and time you want the forward to be sent. You can type in the date box, or you can click on the calendar icon next to the date to select the date from the calendar. You can also type in the time boxes or use the up and down arrows to scroll through the times. Click on the box to the right of the time fields to toggle between AM and PM.


4. Click **EDIT FORWARD** to save the forward and close the window.

5. Configurations

The CONFIGURATIONS menu provides access to a set of windows customers can use to maintain system-level configuration items.

The permissions assigned to a user's role determine which windows and functionality are available to the user.

When a Team Administrator, Supervisor, or custom user with the necessary permissions selects the CONFIGURATIONS menu, a navigation pane is presented, and tiles are displayed in the main part of the window. When the user expands the list in the navigation pane, they see the following menu options:



To go to a specific window in the Web UI, the user can expand the list in the navigation pane and then select the desired window from the list, or the user can click a series of tiles until they reach the desired window.

5.1. Teams & users

When you click the TEAMS & USERS tile on the Access Management window, the Teams & Users window opens. From this window, you can view your team or teams. You can also access a window from which you can add, edit, and delete users who belong to the listed team or teams.

The following is a sample Teams & Users window:

Configuration / Access Management / Teams & Users

Teams & Users

From the Teams & Users screen, you can view, add, delete and edit teams. The teams are listed by team name in alphabetical order.
When you click one of the team names link, the users window for the selected team opens.

Teams

Uninvited guests

Help

☐	Team Name	Description	Portfolios	Created D...	Created By	Last Modi...	Last Modi...
☐	Uninvited guests	Team for uni...	PortCard1(C...				

1 - 1
Page Size 50

When there is more than one team, they are listed in alphabetical order by team name. The names of the teams are hyperlinks. When you click one of the hyperlinks, a window opens that lists the users on the respective team.

5.1.1. View users assigned to a team

To view a list of the users assigned to a team, click the hyperlinked team name on the Teams & Users window. If you prefer, you can select the checkbox for the team on the Teams & Users window, and then click the **View Users** icon in the selection toolbar. A team-specific window opens with the name of the selected team at the top.

The team-specific window lists the users assigned to the team in alphabetical order by username. It also lists each user's full name, role, work phone, email address, the name of any secondary teams to which the user is assigned, when the user was created and by whom, and when the user's information was last modified and by whom.

The team-specific window enables you to view, add, edit, and delete users. You can also view a list of the portfolios assigned to the team by clicking the **ASSIGNED PORTFOLIOS** button.

The following is a sample of a team-specific window:

Uninvited guests

Team for uninvited guests

From the view users screen you can view, add, edit, and delete users from the team.
The "ASSIGNED PORTFOLIOS" button is available for teams that support portfolios and allows viewing or altering the portfolio assignment of the team.

ASSIGNED PORTFOLIOS

Users C11Guest5, C11Guest6, C11G...				
☐	Username	Full name	Role	Secondary Team(s)
☐	C11Guest1	C11Guest1	Team Administrator	
☐	C11Guest10	C11Guest10	Team Administrator	
☐	C11Guest2	C11Guest2	Team Administrator	
☐	C11Guest3	C11Guest3	Team Administrator	
☐	C11Guest4	C11Guest4	Team Administrator	
☐	C11Guest5	C11Guest5	Team Administrator	

1 - 10 < > Page Size 50 ▼

5.1.2. Add a user

Follow these steps to add a user:

1. Click + (plus sign) on the team-specific window (that is, the window that lists the users in the selected team) to open the ADD USER window.

ADD USER

[Help](#)

Username*

Work Phone

Password*

Mobile Phone

Confirm Password*

Email Address*

Full Name*

Office Location

Role*

Department

Notes

SAVE **CANCEL**

2. In the **Username** field, type the username for the new user. The username must be unique to the tenant.

The value you enter must meet the length and RegEx requirements for usernames in the FIELDCONFIG table.

3. In the **Password** field, type a password for the user.

The value you enter must meet the length and RegEx requirements for passwords in the FIELDCONFIG table.

Depending on the value of CONFIG table parameter PasswordEqId, you may or may not be allowed to set the password to the same value as the username.

4. In the **Confirm Password** field, type the same password that you entered in the Password field.
5. In the **Full Name** field, type the first and last name of the user.
6. In the **Role** field, select a role for the user from the dropdown list. The role determines which permissions the user will have.

NOTE

The Role list contains all the roles in the system that are at the same level or at a lower level in the role hierarchy than the role assigned to the user who is adding the new user.

7. (Optional) Type the user's work and mobile phone numbers in the respective fields.
8. In the **Email Address** field, type the user's email address.

The value you enter must meet the length and RegEx requirements for email addresses in the FIELDCONFIG table.

9. (Optional) Type the user's office location and department in the respective fields.
10. (Optional) Type any additional information regarding the user in the **Notes** field.
11. Click **SAVE**.

5.1.3. Edit a user

Listed below is the user data that can be edited. Note that some attributes are optional.

Username
Full Name
Role
Work Phone (optional)
Mobile Phone (optional)
Email Address
Office Location (optional)
Department (optional)
Notes (optional)

NOTE

You cannot edit a user whose role is higher than yours in the role hierarchy.

You cannot modify your own username, but you can modify another user's username. If you modify another user's username, you will be prompted to also modify the user's password.

The values you enter in the **Username** and **Email Address** fields must meet the length and RegEx requirements in the FIELDCONFIG table.

To edit a user, select the corresponding checkbox on the team-specific window, and then click the **Edit** icon in the selection toolbar. When the EDIT USER window opens, make your changes. When you are finished making your changes, click **SAVE**.

The following is a sample EDIT USER window:

EDIT USER

? Help

Username*

C11Guest5

Mobile Phone

CHANGE PASSWORD

Email Address

C11Guest5

Full Name*

C11Guest5

Office Location

Role*

Team Administrator

Department

Work Phone

C11Guest5

Notes

C11Guest5

Activity Info

Last Login

2020-07-06 06:52:01

Failed Logins

—

SAVE

CANCEL

NOTE

From this window, you can reset the count of a user's failed login attempts when that user exceeds the maximum number of allowed failed attempts.

5.1.3.1. Change another user's password

To modify another user's password click **CHANGE PASSWORD** on the EDIT USER window. When the CHANGE USER PASSWORD window opens, type your current password and the other user's new password in the respective fields. After you confirm the user's new password, click **SAVE**.

CHANGE USER PASSWORD [X]

Your Current Password

Introduce your password to enable making changes

New Password

Confirm Password

SAVE **CANCEL**

NOTE

The new password must meet the length and RegEx requirements for passwords in the FIELDCONFIG table.

Depending on the value of CONFIG table parameter PasswordEQId, you may or may not be allowed to set the password to the same value as the username.

The value of the CONFIG table parameter Password_History is taken into account. None of the previous <_n_> passwords can be used for the new password.

5.1.4. Delete a user

Users can be deleted, but there are restrictions and caveats:

- You cannot delete a user whose role is higher than yours in the role hierarchy.
- You cannot delete yourself.
- You will be prompted to confirm that you want to delete the user when:
 - The user has no queues, no forwards, and no alert in queue notifications are assigned.
 - The user has queues assigned.
 - The user has alert in queue notifications assigned.
 - The user had forwards assigned.
 - The user has queues, alert in queue notifications, and forwards assigned.

To delete one or more users, select the corresponding checkbox or checkboxes on the team-specific window, and

then click the **Delete** icon in the selection toolbar. If prompted to confirm that you want to delete the user, click **YES**.


6. Risk strategy & control

The RISK STRATEGY & CONTROL menu items enable you to configure the system in accordance with your institution's strategy for managing the risk associated with fraudulent transaction activity. The menu items enable you to configure various tools used to identify suspicious or fraudulent activity and generate alerts, as well as the tools used by fraud analysts to manage alerts.

The permissions assigned to a user's role determine which windows and functionality are available to the user.

6.1. Team Administrator

When a Team Administrator or a custom user with the necessary permissions selects the RISK STRATEGY & CONTROL menu, a navigation pane is presented, and tiles are displayed in the main part of the window. When the user expands the list in the navigation pane, they see the following menu options:




To go to a specific window in the Web UI, the user can expand the list in the navigation pane and then select the

desired window from the list, or the user can click a series of tiles until they reach the desired window.

6.2. Supervisor

When a Supervisor, or a custom user with the necessary permissions, selects the RISK STRATEGY & CONTROL menu, a navigation pane is presented, and tiled are displayed in the main part of the window. When the user expands the list in the navigation pane, they see the following menu options:



To go to a specific window in the Web UI, the user can expand the list in the navigation pane and then select the desired window from the list, or the user can click a series of tiles until they reach the desired window.

7. Skip rule, queue, or computed variable execution

Users who are assigned the necessary permissions can prevent the execution of a rule, queue, or computed variable. This functionality enables them to improve performance by removing from processing those rules, queues, or computed variables that take too much time to execute.

The permissions are:

- Skip Rule Execution
- Skip Queue Execution
- Skip Computed Variable Execution

By default, the permissions are not assigned to the default PRM user roles. They can be assigned to only a custom role.

To apply skip execution to a rule, queue, or computed variable, a user must follow these steps:

1. Go to the Rule Manager, Queue Manager (Smart tab), or Computed Variable Manager window.
2. Select only one rule, queue, or computed variable.
3. Select **Skip Execution** from the context menu or selection toolbar.

The user is prompted to confirm that they want the selected rule, queue, or computed variable skipped. The prompt identifies the portfolios that will be impacted.

If the user confirms that they want the selected item skipped, the value in the Skip Execution column on the Rule Manager, Queue Manager (Smart tab), or Computed Variable Manager window changes from No to Yes, and the rule, queue, or computed variable is added to the SKIP_RULES_LIST table in the database.

IMPORTANT

When Skip Execution is applied to a computed variable, any deployed rules or queues that contain that computed variable will also be skipped.

To remove skip execution from a rule, queue, or computed variable for which skip execution has been set, a user must follow these steps:

1. Go to the Rule Manager, Queue Manager (Smart tab), or Computed Variable Manager window.
2. Select the skipped rule, queue, or computed variable.
3. Select **Remove Skip Execution** from the context menu or selection toolbar.

The user is prompted to confirm that they want to remove skip execution from the selected rule, queue, or computed variable. The prompt identifies the portfolios that will be impacted.

If the user confirms that they want to remove skip execution from the selected item, the value in the Skip Execution column on the Rule Manager, Queue Manager (Smart tab), or Computed Variable Manager window changes from No to Yes, and the rule, queue, or computed variable is removed from the SKIP_RULES_LIST table in the database.

7.1. Rule manager

ACI Proactive Risk Manager (PRM) Analysis and Review system processing is based on user-defined rules. The system checks incoming transactions against each rule. If the transaction matches the definition of at least one rule, the system tags the transaction as an alert. Analysts can then examine each alert and take action.

To use rules, you must define rules, assign them to portfolios, and then deploy them. These tasks are performed from the Rule Manager window.

You can create simple or complex rules using field values, conditions, statements, and time frame considerations.

7.1.1. Open the Rule Manager window

Use the following process to open the Rule Manager window and view the list of rules.

1. Go to **Risk Strategy & Control**.
2. Select **Rule Management**.
3. Select **Rule Manager**.

The Rule Manager window opens. By default, the Near Real-Time tab is displayed.

Risk Strategy & Control / Rule Management / Rule Manager

Rule Manager

From the Rule Manager screen, you can view, add, delete, edit, and clone rules. You can assign rules to portfolios and deploy them into production, or deactivate a rule so it is no longer in production.

Near Real Time
Real Time
Batch (End of Day)

Dimensions

	Rule ID	Rule Name	Dimension	Alert Color	Assigned	Deployed	Pending	Alert Behavior	Skips	Last Skip Dt
☐	203	autoactAcct	Account		2	2		Discard		
☐	206	autoactCard	Card		2	2		Discard		
☐	207	autoactEmpl	Employee		2	2		Discard		
☐	209	autoactMerch	Merchant		2	2		Discard		
☐	211	autoactTerm	Terminal		2	2		Discard		
☐	215	autoactUAID	User Account ID		2	2		Discard		
☐	213	autoactUAN	Customer		2	2		Discard		
☐	236	BadBinCards	Card		2	0	+2	Discard		
☐	139	C11AcctCateg300	Account		2	2		Discard		
☐	126	C11AcctRRRRule	Account		2	2		Discard		
☐	140	C11CardCateg300	Card		2	2		Discard		
☐	128	C11CardRRRRule	Card		2	2		Discard		
☐	141	C11EmplCateg300	Employee		2	2		Discard		
☐	130	C11EmplRRRRule	Employee		2	2		Discard		
☐	142	C11MerchCateg300	Merchant		2	2		Discard		
☐	132	C11MerchRRRRule	Merchant		2	2		Discard		
☐	143	C11TermCateg300	Terminal		2	2		Discard		
☐	134	C11TermRRRRule	Terminal		2	2		Discard		
☐	145	C11UAIDCateg300	User Account ID		2	2		Discard		
☐	138	C11UAIDRRRRule	User Account ID		2	2		Discard		

1 - 37 < Page Size 50 >

4. Optional: To view the Real-Time or Batch (End of Day) rules, select the corresponding tab.

NOTE

Your institution must license Real-Time and Batch rules; otherwise, those tabs are not visible. If you are migrating from a previous version of ACI Proactive Risk Manager and currently have real-time or batch functionality, you do not have to license the optional modules.

Descriptions of each rule type are as follows:

Near Real-Time

This rule generates an alert on the current transaction based on any value in any data element in the transaction, if it occurs in a transaction with a tiebreaker. These transaction data element values include demographic data (for example, the card expiration date or cardholder's address). The system generates this alert *after* authorization is complete.

Real-time

This rule is applied to transactions during online authorization processing to provide the authorizing entity with a recommendation whether it should approve or decline the transaction.

Batch (End of Day)

This rule generates an alert on the most recent transaction based on totals and comparisons of totals across multiple days.

- Optional: On each tab, use the **Dimensions** field to filter the rules assigned to the selected dimensions.
- Optional: Click a rule name to see a preview of its name, description, entrance criteria, and logic. Use the **Preview side** buttons to switch between displaying the preview below the grid to displaying it to the right of the grid.

The screenshot shows the 'Rule Manager' interface. At the top, there are tabs for 'Near Real Time', 'Real Time', and 'Batch (End of Day)'. Below the tabs is a 'Dimensions' dropdown menu. The main area contains a table with columns: Rule ID, Rule Name, Dimension, Alert Color, Assigned, Deployed, Pending, Alert Behavior, Skips, and Last Skip Date. The table lists several rules, including 'autoactAcct', 'autoactCard', 'autoactEmpl', 'autoactMerch', 'autoactTerm', 'autoactUAID', and 'autoactUAN'. Below the table, there is a 'Preview side' section with a 'Rule Name' dropdown and a 'Description' text area. To the right of the preview section, there is a 'Rule Logic' section with a list of criteria and logic rules.

Rule ID	Rule Name	Dimension	Alert Color	Assigned	Deployed	Pending	Alert Behavior	Skips	Last Skip Date
203	autoactAcct	Account		2	2		Discard		
205	autoactCard	Card		2	2		Discard		
207	autoactEmpl	Employee		2	2		Discard		
209	autoactMerch	Merchant		2	2		Discard		
211	autoactTerm	Terminal		2	2		Discard		
215	autoactUAID	User Account ID		2	2		Discard		
213	autoactUAN	Customer		2	2		Discard		

7.1.2. Add a rule

To add a rule, follow these steps.

- Go to **Risk Strategy & Control > Rule Management > Rule Manager**.

The Rule Manager window opens. By default, the Near Real-Time tab is displayed.

- On the Rule Manager window, select the tab for the type of rule that you want to create.

NOTE

Your institution must license Real-Time and Batch rules, otherwise those tabs are not visible. If you are migrating from a previous version of ACI Proactive Risk Manager and currently have real-time or batch functionality, you do not have to license the optional modules.

3. Click the plus (+) sign. Depending on which tab you have selected, one of the following windows opens:
 - ADD NEAR REAL-TIME RULE window
 - ADD REAL-TIME RULE window
 - ADD BATCH (END OF DAY) RULE window
4. On the ADD <rule type> RULE window, perform the following steps.
 - a. Enter the information for the type of rule that you are creating. See [Rule field descriptions](#).
 - b. Optional: When you finish defining the new rule, click **SYNTAX CHECK**.
 - c. Click **SAVE**. The ADD <rule type> RULE window closes, and the new rule is added to the Rule Manager window.

7.1.2.1. Rule field descriptions

Different rule fields can apply to each rule type. Listed below are the rule fields and their respective descriptions. The rule type associated with each field is specified in parentheses.

Real-time disposition (real-time rule only)

This is the advice provided to the payment engine when the rule criteria are met, like Authorize or Decline. When you add an RT rule, you must select a disposition code from the drop-down list.

- If the selected disposition code is set to **Allow RT Rule Comments** (a checkbox on the Add Real-Time Disposition Code and Edit Real-Time Disposition Code windows), then the **RT Rule Comments** field shows on the Add Real-Time Rule window when that disposition code is selected from the drop-down list.
- If the selected disposition code is set to **Allow RT Duration** (a checkbox on the Add Real-Time Disposition Code and Edit Real-Time Disposition Code windows), then the **RT Rule Disposition Duration** field shows on the Add Real-Time Rule window when that disposition code is selected from the drop-down list. Specify the duration in minutes.

If you enter comments and/or specify a duration, that information is sent along with the recommended disposition to the third party that sent the transaction to PRM.

Dimension (all rule types)

The dimension for which the rule will be executed.

Alert Color (all rule types)

Select the Alert Color for the rule. This colors the transaction line in the Review screen.

Queues for Alerts (Near Real-time Rule and Batch Rule)

- **Create matching queue:**

The system creates a new queue using the name of this rule and sends all alerts from this rule to that queue.
- **Assign group queue:** The system assigns the alerts created from this rule to a queue.
- **None:** The system does not create or assign a queue for the alerts.

- **Alert Behavior:** This flag specifies how the system should handle an alert triggered by this rule when an analyst closes the alert.
 - Discard - An alert is created if it meets the criteria of the rule. The alert is accessible in a queue or from multiple queues and once accessed, the user can work, take actions and close the alert.
 - Archive - An alert is created if it meets the criteria of the rule. The alert is accessible in a queue or from multiple queues and once accessed, the user can work, take actions and close the alert.
In addition, the alert is copied to the Alerts Tracking table within the database. This provides additional details such as a Reviewer ID and a Tracking ID.
Choose this option if you want to preserve the alert for internal audits or further investigation. See the *PRM Database Reference Manual* for a complete list of available fields held in the Alerts Tracking Table.
 - Keep in Queue - An alert is created if it meets the criteria of the rule. The alert is accessible in a queue or from multiple queues and once accessed, the user can work, take actions and then opt to leave the alert in an open status or close the alert.
If the user chooses to leave the alert open, it effectively remains accessible in the relevant queues again, which allows other users to pick up and work the alert.

NOTE

This is different behavior from other features like forwarding the alert and placing a reminder on an alert.

In addition, the alert is copied to the Alerts Tracking table within the database. This provides additional details such as a Reviewer ID and a Tracking ID.
Choose this option if you want to preserve the alert for internal audits or further investigation. See the *PRM Database Reference Manual* for a complete list of available fields held in the Alerts Tracking Table.

- **Email notification for Pending Alerts:** Email notification that alerts have been pending for a specified number of minutes.

Rule Score (Near Real-Time Rule)

A numeric value assigned to the rule to indicate the likelihood of fraud.

Response Required (Near Real-Time Rule and Batch Rule)

Indicates whether to send the alert for manual review, which requests an individual response for each transaction alerted by this rule.

Visible for Team-Only (Near Real-Time Rule and Batch Rule)

Restricts the rule so that teams assigned to different portfolios do not see this rule. Otherwise, the team to which the person who created the rule is assigned can see the rule.

Rule Auto-Actions (Near Real-Time Rule and Batch)

Specifies what the system must do when it processes a transaction that meets the rule criteria. If the Dimension Level ID is overridden, the auto action is not applied.

NOTE

When adding an auto action, the fields vary depending on the **Action** selected.

Entrance Criteria or Rule Logic

You can enter SQL statements for one, but not both, of these.

- Entrance Criteria is the SQL statement executed prior.

- Rule Logic is the SQL Syntax for the rule.

NOTE

When creating a rule, you can apply Entrance Criteria and Rule Logic. Click the icons on the right side of the Entrance Criteria and Rule Logic to select predefined data to include in the SQL logic fields. You can reuse these data variables in any rule, which increases efficiency when writing rules.

NOTE

For historical reasons, there are several Entry procedure parameters of type CHAR, whereas the mapped column is of type VARCHAR. This means that for the values sent to the procedure, space padding is applied, and the value is saved in the table column with these spaces, even though the column is of type VARCHAR. Take into consideration space padding for the respective values when you write rules.

The following table describes the icons in the Entrance Criteria and Rule Logic sections of the window.

Icon	Description
	Click this icon to display a list of transaction variables that you can include in the Entrance Criteria or Rule Logic. Transaction variables are variables from incoming transactions that match the dimension of the current rule.
	Click this icon to display a list of the transaction history fields that you can include in the Rule Logic. Transaction history fields are transactional fields from SHORTWINDOW.
	Click this icon to display a list of demographic fields that you can include in the Rule Logic. Demographic fields are from the MASTER table of the current rule's dimension.
	Click this icon to display a list of computed variables that you can include in the Entrance Criteria or Rule Logic. Computed variables are a list of the computed variables (aggregates) in the system for the current rule's dimension, without the auto-action attribute, that correspond to the current rule type.

7.1.3. Edit a rule

To edit a rule, follow these steps.

1. Go to **Risk Strategy & Control > Rule Management > Rule Manager**.

The Rule Manager window opens. By default, the Near Real-Time tab is displayed.

2. On the Rule Manager window, perform the following steps.
 - a. Select the tab that lists the type of rule you want to edit.

NOTE

Your institution must license Real-Time and Batch rules, otherwise those tabs are not visible. If you are migrating from a previous version of ACI Proactive Risk Manager and currently have real-time or batch functionality, you do not have to license the optional modules.

- b. Select the checkbox for the rule you want to edit.

c. Select the **Edit** icon from the context menu or the selection toolbar. Depending on which tab you have selected, one of the following windows opens:

- EDIT NEAR REAL-TIME RULE window
- EDIT REAL-TIME RULE window
- EDIT BATCH (END OF DAY) RULE window

3. On the EDIT RULE window, perform the following steps.

a. Make your changes.

Never deployed rule

If the rule has never been deployed, you can modify the value in any field, except for the Dimension field.

Undeployed rule

If the rule is undeployed, but was previously deployed, you can modify the value in any field, except for the Rule Name and Dimension fields.

Deployed rule

If the rule is deployed, which fields you can modify depends on your permissions:

- If you have the Manage Rules permission, but not the Manage Deployed Rules permission, you can modify only the Alert Color and Alert Color Priority fields in a deployed rule.
- If you have the Manage Deployed Rules permission, you can modify the following fields in a deployed rule:

Alert Color
Alert Color Priority
Real-Time Rule Disposition (real-time rules only)
Real-Time Rule Disposition Duration (real-time rules only)
Real-Time Rule Disposition Comment (real-time rules only)
Email Notification
Rule Score
Response Required
Description
Visible for Team-Only
Rule Auto-Actions
Entrance Criteria
SQL Logic

Regardless of your permissions, you cannot modify the following fields in a deployed rule:

Rule name
Dimension
Alert Behavior
Queue Assignment

NOTE

The Manage Rules permission is assigned to the default roles Team Administrator and Supervisor.

The Manage Deployed Rules permission is not assigned to any of the default roles. That permission can only be assigned to a custom role.

- a. Optional: When you finish editing the rule, click **SYNTAX CHECK**.
- b. Click **SAVE**. The EDIT <rule type> RULE window closes, and your changes are shown on the Rule Manager window.

If the rule is not deployed, when you click SAVE, the system automatically checks the syntax. If the rule passes the syntax check, the EDIT window closes, and the changes are displayed in the grid on the Rule Manager window.

If the rule is deployed, when you click SAVE, the system automatically checks the syntax. If the rule passes the syntax check, a message window opens. The message is "Saving the Changes will trigger an automatic redeploy of all rules and queues already deployed on the same portfolio(s) as the edited rule. Are you sure you want to save the change(s)?" If you click NO or "X", the message window closes, the operation is canceled, and the EDIT window remains opens. If you click YES, the system redeploys all rules and queues deployed on the same portfolio(s) as the edited rule.

7.1.4. Delete a rule

To delete one or more rules, follow these steps.

1. Go to **Risk Strategy & Control > Rule Management > Rule Manager**.
The Rule Manager window opens. By default, the Near Real-Time tab is displayed.
2. Select the tab that lists the type of rule or rules you want to delete.

NOTE

Your institution must license Real-Time and Batch rules, otherwise those tabs are not visible. If you are migrating from a previous version of ACI Proactive Risk Manager and currently have real-time or batch functionality, you do not have to license the optional modules.

3. Select the checkbox or checkboxes for the rule or rules you want to delete.
4. Select the **Delete** icon from the context menu or the selection toolbar. The selected rule or rules are removed from the Rule Manager window.

NOTE

Deployed rules cannot be deleted. You must remove a rule from production before you can delete it.

If you want to delete a rule with a matching queue, you must confirm that you want to delete the matching queue, as well as the selected rule.

7.1.5. Clone a rule

NOTE

If you are cloning a real-time rule, you can use the context menu to make the cloned rule a near real-time rule. You can also use the context menu to make a cloned a near real-time rule a real-time rule.

To clone a rule, follow these steps.

1. Go to **Risk Strategy & Control > Rule Management > Rule Manager**.

The Rule Manager window opens. By default, the Near Real-Time tab is displayed.

2. On the Rule Manager window, perform the following steps.

- a. Select the tab that lists the type of rule you want to clone.

NOTE

Your institution must license Real-Time and Batch rules, otherwise those tabs are not visible. If you are migrating from a previous version of ACI Proactive Risk Manager and currently have real-time or batch functionality, you do not have to license the optional modules.

- b. Select the checkbox for the rule you want to clone.
- c. Select the **Clone as** from the context menu or **Clone** the selection toolbar.

NOTE

If you select a real-time rule and then select **Clone as** from the context menu, you must select either **RT Rule** or **NRT Rule**. You can clone a real-time rule as either a real-time rule or a near real-time rule.

If you select a near real-time rule and then select **Clone as** from the context menu, you must select either **RT Rule** or **NRT Rule**. You can clone a near real-time rule as either a real-time rule or a near real-time rule.

Depending on which tab you have selected, or if you used **Clone as**, whether you selected RT Rule or NRT rule, one of the following windows opens:

- ADD NEAR REAL-TIME RULE window
- ADD REAL-TIME RULE window
- ADD BATCH (END OF DAY) RULE window

NOTE

The Name field contains the name of the rule being cloned preceded by the word CLONE and a hyphen.

3. On the ADD <rule type> RULE window, perform the following steps.
 - a. Make your changes. See [Add a rule](#) for descriptions of the fields.
 - b. Optional: When you finish defining the new rule, click **SYNTAX CHECK**.
 - c. Click **SAVE**. The ADD <rule type> RULE window closes, and your new rule is added to the Rule Manager window.

7.1.6. Assign rules to portfolios

You can assign rules to portfolios that match the rule's dimension. You can also unassign rules from portfolios.


Use the following process to assign one or more rules to a portfolio in its dimension.

1. Go to **Risk Strategy & Control > Rule Management > Rule Manager**.

The Rule Manager window opens. By default, the Near Real-Time tab is displayed.

2. Select the tab that corresponds to the type of rules (Near Real-Time, Real-Time, or Batch) you want to assign to portfolios.
3. Select the rule or rules that you want to assign to portfolios.
4. Click **Assign** in the context menu or click the **Assign rules to portfolios** icon () in the selection toolbar.

The ASSIGN <rule type> RULES TO PORTFOLIOS window opens.



The Available Rules section lists by dimension the rule or rules you selected on the Rule Manager window.

The Assigned to Portfolios section lists the rules that are assigned to the same dimension or dimensions as the rule or rules you selected. The rules in this section are listed by portfolio and dimension.

NOTE

If, instead of clicking **Assign** in the context menu or clicking the **Assign rules to portfolios** icon in the selection toolbar, you click the **Assign rules to portfolios** icon that is above the grid, the Available Rules section will list all the rules from the open tab, and the Assigned to Portfolios section will list all the rules from the open tab that are already assigned to portfolios.

5. On the ASSIGN <rule type> RULES TO PORTFOLIOS window, perform the following steps.
 - a. In the Available Rules list, select the checkboxes that correspond to the rules that you want to assign to a portfolio.

Use the filter to find the rules you want to assign to a portfolio.
 - b. Click the arrow button that is between the two sections.
 - c. In the Assigned to Portfolios list, select the checkbox or checkboxes for the portfolio or portfolios to which you want to assign the selected rule or rules.

Use the filter and/or expand the list to find the portfolio or portfolios to which you want to assign the selected rule or rules.

NOTE

You can assign a rule only to a portfolio that is assigned to the same dimension as the rule.

d. Click **SAVE**.

The ASSIGN <rule type> RULES TO PORTFOLIOS window closes.

The Rule Manager window shows the updated assignment information.

7.1.7. Export rules

You can export all rules or only selected rules and save the exported data to a file.

7.1.7.1. Export all rules

To export all rules, follow these steps.


1. Go to **Risk Strategy & Control > Rule Management > Rule Manager**.

The Rule Manager window opens. By default, the Near Real-Time tab is shown.

2. On the Rule Manager window, select the tab that lists the type of rule or rules whose data you want to export.
3. On the selected tab, follow these steps.
 - a. Optional: Apply a filter to the rules to show a subset of the rules on the selected tab.
 - b. Click the **Export All** icon (), which is located above the grid.

NOTE | If you applied a filter, when you click **Export All**, only the filtered data is saved to the file.

The EXPORT window opens.



4. On the EXPORT window, follow these steps.

- a. Optional: Select the **Unmask content for export** checkbox if you want the sensitive data saved in the clear.
- b. Select one of the **EXPORT AS** options to indicate the type of file to which you want the exported data saved.

NOTE

If you plan to later import the data you are now exporting, be sure to export it as .XML. The import function allows you to import data in .XML format only.

The EXPORT window closes and the file containing the exported data is downloaded to your machine.

NOTE

For export to .XLS, due to Microsoft Excel cell size limitations, the information is truncated to max: 32,767 characters.

7.1.7.2. Export selected rules

To export one or more rules, follow these steps.


1. Go to **Risk Strategy & Control > Rule Management > Rule Manager**.

The Rule Manager window opens. By default, the Near Real-Time tab is displayed.

2. On the Rule Manager window, select the tab that lists the type of rule or rules you want to export.
3. On the selected tab, follow these steps.
 - a. Optional: Apply a filter the rules to display a subset of the rules on the selected tab.
 - b. Select the checkbox or checkboxes of the rule or rules whose data you want to export.

- c. Select **Export Selection** from the context menu or click the **Export Selection** icon () in the selection toolbar.

The EXPORT window opens.



4. On the EXPORT window, follow these steps.
- Optional: Select the **Unmask content for export** checkbox if you want the sensitive data saved in the clear.
 - Select one of the **EXPORT AS** options to indicate the type of file to which you want the exported data saved.

NOTE

If you plan to later import the data you are now exporting, be sure to export it as .XML. The import function allows you to import data in .XML format only.

The EXPORT window closes and the file containing the exported data is downloaded to your machine.

7.1.8. Import rules and computed variables

PRM enables you to import rules and computed variables. You may want to do so after you have tested rules and computed variables in a test environment and are ready to migrate them to a production environment. Another reason could be that you are upgrading from a previous version of PRM.

To import rules and variables, follow these steps.


- Go to **Risk Strategy & Control > Rule Management > Rule Manager**.

The Rule Manager window opens. By default, the Near Real-Time tab is displayed.

- On the Rule Manager window, select the tab that corresponds to the type of rules (Near Real-Time, Real-Time, or Batch (End of Day)) you want to import.

3. On the selected tab, click the **Import rules and computed variables** icon () , which is located above the grid.

The IMPORT RULES AND COMPUTED VARIABLES window opens.



4. On the IMPORT RULES AND COMPUTED VARIABLES window, follow these steps.
5. Select the **Overwrite existing data** checkbox if the imported file contains rules or computed variables with the same names as existing ones and you want to replace the existing ones.

NOTE

You cannot overwrite deployed or previously deployed rules.

If you do not select the **Overwrite existing data** checkbox, the system will import only items that have different names.

- a. Click **BROWSE** to select the .XML file to import.

The system accepts .XML files exported from PRM 8.4 and higher.

- b. Click **IMPORT**.

The IMPORT RULES AND COMPUTED VARIABLES window closes. A status bar appears until the rules and computed variables have been imported.

NOTE

The system automatically assigns a rule to a matching queue unless the rule is already assigned to a group queue with the same name as an existing one.

If the import of a computed variable used in a rule fails, the rule is not be imported.

7.1.9. Deploy a rule

A rule is not run against incoming transactions until it has been deployed. Deploying a rule puts it into production. Before a rule can be deployed, it must be assigned to one or more portfolios.

7.1.9.1. Dual control

Dual control is a workflow feature that can be used to provide oversight in the deployment of rules. The feature is configured separately for each dimension. Only the Root Administrator or a custom user with the necessary permission can modify the dual control configuration for a dimension.

7.1.9.1.1. Dual control disabled

When dual control is disabled for a dimension, any user whose role is assigned the Manage Rules or Manage Deployed Rules permission can deploy a rule on that dimension.

By default, dual control is disabled.

See [Dual control disabled](#) for procedures on deploying rules when dual control is disabled.

7.1.9.1.2. Dual control without override

When dual control without override is enabled for a dimension, a user whose role is assigned the Manage Rules or Manage Deployed Rules permission can deploy a rule on that dimension, unless one of the following items is true:

- The user attempting to deploy the rule is the one who created the rule, and the rule has not been modified.
- The user attempting to deploy the rule is the one who last modified the rule.

See [Dual control without override](#) for procedures on deploying rules when dual control without override is enabled.

7.1.9.1.3. Dual control with override

When enabling dual control for a dimension, customers can choose to also configure an override code. Trusted users can be given the override code so that they can enter it when prompted and thereby override the dual control restrictions.

When dual control with override is enabled for a dimension, a user whose role is assigned the Manage Rules or Manage Deployed Rules permission can deploy a rule on that dimension, unless one of the following items is true:

- The user attempting to deploy the rule is the one who created the rule, the rule has not been modified, and the user does not know the override code.
- The user attempting to deploy the rule is the one who last modified the rule, and the user does not know the override code.

See [Dual control with override](#) for procedures on deploying rules when dual control with override is enabled.

7.1.9.2. Configuring the processing order for real-time rules

The real-time rules assigned to each portfolio are executed in the order in which they are listed on the Assigned to Deploy section of the DEPLOY REAL-TIME RULES window. The order in which the real-time rules are executed matters because when one of the real-time rules in the list is run against a transaction, and it is triggered, PRM will not execute the rest of the real-time rules in the list against that transaction.

See any of the following procedures for instructions on how to configure the order in which the real-time rules are executed:

- [Dual control disabled](#)
- [Dual control without override](#)
- [Dual control with override](#)

7.1.9.3. Dual control disabled

To deploy a rule when dual control is disabled for the dimension to which the rule is assigned, follow these steps.

1. Go to **Risk Strategy & Control > Rule Management > Rule Manager**.

The Rule Manager window opens. By default, the Near Real-Time tab is displayed.

2. On the Rule Manager window, perform the following steps:
 - a. Select the tab that corresponds to the type of rule you want to deploy. There are tabs for near real-time, real-time, and batch (end of day) rules.
 - b. Optional: Use the Dimension filter to display only the rules for the dimension to which the rule or rules you want to deploy are assigned.
 - c. Select the checkbox for the rule you want to deploy. You can select more than one rule.


NOTE | The selected rule or rules must be assigned to at least one portfolio.

- d. Select **Deploy** in the context menu or click the **Deploy** icon () in the selection toolbar.

The DEPLOY RULES window opens.

NOTE | The title of the window that opens corresponds to the type of rule you select on the Rule Manager window. If you select a rule from the Near Real-Time tab on the Rule Manager window, then the DEPLOY NEAR REAL-TIME RULES window will open. If you select a rule from the Real-Time tab or the Batch (End of Day) tab, then, respectively, the DEPLOY REAL-TIME RULES or DEPLOY BATCH (END OF DAY) RULES window will open.

3. On the DEPLOY RULES window, perform the following steps:
 - a. In the Available to Deploy section of the DEPLOY RULES window, select the portfolio or portfolios to which the rule or rules you want to deploy are assigned.



- b. Click the middle arrow button to display the selected portfolio or portfolios and the rules assigned to them, in the Assigned to Deploy section of the window.
- c. (Optional) You can modify the order in which the real-time rules will be executed by changing the order in which they are listed on the Assigned to Deploy section of the window. The rule listed at the top of the list will be executed first. To move a rule up or down in the list, you can either hover over the rule or move it by dragging and dropping with the mouse. When you hover, the up and down arrows appear to the left of the rule. Click the up arrow to move a rule higher in the list or click the down arrow to move it lower in the list.

NOTE

The real-time rules assigned to each portfolio are executed in the order in which they are listed on the Assigned to Deploy section of the DEPLOY REAL-TIME RULES window. The order in which the real-time rules are executed matters because when one of the real-time rules in the list is run against a transaction, and it is triggered, PRM will not execute the rest of the real-time rules in the list against that transaction.

- d. Click **DEPLOY RULES**.

The rule or rules are deployed, the DEPLOY RULES window closes, and the grid on the Rule Manager window is updated.

NOTE

If there are other rules assigned to the selected portfolio or portfolios which have not been deployed, all of those rules will also be deployed, assuming the selected portfolio or portfolios are on a dimension with dual control disabled.

7.1.9.4. Dual control without override

IMPORTANT

You cannot deploy a rule on a dimension for which dual control without override is enabled if either of the following is true:

- You created the rule, and the rule has not been modified.

- You are the user who last modified the rule.

To deploy a rule when dual control without override is enabled for the dimension to which the rule is assigned, follow these steps:

1. Go to **Risk Strategy & Control > Rule Management > Rule Manager**.

The Rule Manager window opens. By default, the Near Real-Time tab is displayed.

2. On the Rule Manager window, perform the following steps:
 - a. Select the tab that corresponds to the type of rule you want to deploy. There are tabs for near real-time, real-time, and batch (end of day) rules.
 - b. Select the checkbox for the rule you want to deploy. You can select more than one rule.


NOTE The selected rule or rules must be assigned to at least one portfolio.

- c. Select **Deploy** in the context menu or click the **Deploy** icon () in the selection toolbar.

The DEPLOY RULES window opens.

NOTE The title of the window that opens will correspond to the type of rule you selected on the Rule Manager window. If you selected a rule from the Near Real-Time tab on the Rule Manager window, then the DEPLOY NEAR REAL-TIME RULES window opens. If you selected a rule from the Real-Time tab or the Batch (End of Day) tab, the title of the DEPLOY RULES window will reflect corresponding rule type.

3. On the DEPLOY RULES window, follow these steps:
 - a. In the Available to Deploy section of the DEPLOY RULES window, select the portfolio or portfolios to which the rule or rules you want to deploy are assigned.



- b. Click the middle arrow button to display the selected portfolio or portfolios and the rules assigned to them, in the Assigned to Deploy section of the window.

NOTE

The rules you created and that have not yet been edited on dimensions for which dual control is enabled appear as read-only and are visually highlighted in the Assigned to Deploy section.

The rules created by other users and last edited by you on dimensions for which dual control is enabled appear as read-only and are visually highlighted in the Assigned to Deploy section.

- c. (Optional) You can modify the order in which the real-time rules will be executed by changing the order in which they are listed on the Assigned to Deploy section of the window. The rule listed at the top of the list will be executed first. To move a rule up or down in the list you can either hover over the rule or move it by dragging and dropping with the mouse. When you hover, the up and down arrows appear to the left of the rule. Click the up arrow to move a rule higher in the list or click the down arrow to move it lower in the list.

NOTE

The real-time rules assigned to each portfolio are executed in the order in which they are listed on the Assigned to Deploy section of the DEPLOY REAL-TIME RULES window. The order in which the real-time rules are executed matters because when one of the real-time rules in the list is run against a transaction, and it is triggered, PRM will not execute the rest of the real-time rules in the list against that transaction.

- d. Click **DEPLOY RULES**.

NOTE

If the selected portfolio or portfolios only have rules on which dual control applies (that is, all selected rules are read-only and cannot be deployed by you), then the DEPLOY RULES button is disabled. You must manually close the DEPLOY RULES window.

When you click DEPLOY RULES, PRM performs as follows:

- PRM does not deploy the following rules:
 - Any rules that were created by you that have not been modified and that are assigned to portfolios on dimensions for which dual control without override is enabled.
 - Any rules that were last modified by you and that are assigned to portfolios on dimensions for which dual control without override is enabled.
- PRM deploys the following rules:
 - Any rules assigned to the selected portfolio or portfolios on dimensions for which dual control without override is enabled and that were created by you but were last modified by another user.
 - Any rules assigned to the selected portfolio or portfolios on dimensions for which dual control without override is enabled and that were not last modified by you.
 - Any rules assigned to the selected portfolio or portfolios on dimensions for which dual control is disabled.

The DEPLOY RULES window closes, and the grid on the Rule Manager window is updated.

7.1.9.5. Dual control with override

You cannot deploy a rule on a dimension that has dual control enabled with override functionality if either of the following is true:

- You created the rule, the rule has not been modified, and you do not know the override code for the dimension to which the rule is assigned.
- You are the user who last modified the rule, and you do not know the override code for the dimension to which the rule is assigned.

To deploy a rule when dual control with override is enabled for the dimension to which the rule is assigned, follow these steps.

NOTE These steps assume you know the override code for the dimension to which the rule is assigned.

1. Go to **Risk Strategy & Control > Rule Management > Rule Manager**.

The Rule Manager window opens. By default, the Near Real-Time tab appears.

2. On the Rule Manager window, perform the following steps:
 - a. Select the tab that corresponds to the type of rule you want to deploy. There are tabs for near real-time, real-time, and batch (end of day) rules.
 - b. Select the checkbox for the rule you want to deploy. You can select more than one rule.


NOTE The selected rule or rules must be assigned to at least one portfolio.

- c. Select **Deploy** in the context menu or click the **Deploy** icon () in the selection toolbar.

The DEPLOY RULES window opens.

NOTE The title of the window that opens corresponds with the type of rule you selected on the Rule Manager window. If you selected a rule from the Near Real-Time tab on the Rule Manager window, then the DEPLOY NEAR REAL-TIME RULES window opens. If you selected a rule from the Real-Time tab or the Batch (End of Day) tab, the title of the DEPLOY RULES window reflects corresponding rule type.

3. On the DEPLOY RULES window, follow these steps:
 - a. In the Available to Deploy section of the DEPLOY RULES window, select the portfolio or portfolios to which the rule or rules you want to deploy are assigned.



- b. Click the middle arrow button to display the selected portfolio or portfolios and the rules assigned to them, in the Assigned to Deploy section of the window.
- c. (Optional) You can modify the order in which the real-time rules will be executed by changing the order in which they are listed on the Assigned to Deploy section of the window. The rule listed at the top of the list will be executed first. To move a rule up or down in the list you can either hover over the rule or move it by dragging and dropping with the mouse. When you hover, the up and down arrows appear to the left of the rule. Click the up arrow to move a rule higher in the list or click the down arrow to move it lower in the list.

NOTE

The real-time rules assigned to each portfolio are executed in the order in which they are listed on the Assigned to Deploy section. The order in which they are executed matters because when one of them is run against a transaction, and it is triggered, PRM will not execute the rest of the rules in the list against that transaction.

- d. Click the **Override** icon () in the Assigned to Deploy section.

The OVERRIDE DUAL CONTROL window opens.

The screenshot shows a modal window titled "OVERRIDE DUAL CONTROL". It features three text input fields, each with an asterisk indicating a required field: "Current Username *", "Password *", and "Card Override Code *". Below the input fields, there is a light blue bar containing two buttons: a grey "SAVE" button and a blue "CLOSE" button.

4. On the OVERRIDE DUAL CONTROL window, follow these steps:
 - a. Enter your username, your password, and the override code for the dimension assigned to the rule or rules you are attempting to deploy.
 - b. Click **SAVE**.

The OVERRIDE DUAL CONTROL window closes. The **DEPLOY RULES** button on the DEPLOY RULES window is enabled.

5. On the DEPLOY RULES window, click **DEPLOY RULES**. The rule or rules are deployed, the DEPLOY RULES window closes, and the grid on the Rule Manager window is updated.

NOTE Other rules assigned to the selected portfolio will also be deployed, assuming the selected portfolio or portfolios are on a dimension with dual control disabled.

7.1.10. Skip-Bad-Rule functionality

By default, when a bad rule is encountered during rule processing, the transaction is rolled back, and no alerts are generated. If the error in the rule's SQL is not fixed, and the transaction is not resubmitted immediately, fraud may be missed because alerts are not generated promptly.

Here are examples of actions that result in a bad rule:

- Changing the name of a column or table that is used in a rule's SQL
- Changing the data type of a column that is used in a rule's SQL
- Deleting a column or table that is used in a rule's SQL
- Typing incorrectly the name of a column or table when creating a rule

The purpose of the Skip Bad Rule feature is to allow the system to skip a bad rule and continue processing the

transaction. When the Skip Bad Rule feature is enabled and a bad rule is encountered during rule processing, the system skips the bad rule and continues to the next rule in the procedure.

The SkipBadRule parameter in the SystemConfig table is used to enable and disable the Skip Bad Rule feature. The SkipBadRule parameter can be enabled or disabled from the General Settings window by a Root Administrator, or a user assigned a custom role with the necessary permissions. If the parameter is set to 0 (disabled), the system discontinues rule processing and rolls back the transaction when it encounters a bad rule. If the parameter is set to 1 (enabled), when the system encounters a bad rule, it skips the bad rule and continues to the next rule.

NOTE

If the Skip Bad Rule feature is disabled, the errors generated by bad rules upon execution are logged in the AG Events table and the Trace table. If the Skip Bad Rule feature is enabled, the errors generated by bad rules upon execution are not logged; the count value is increased, and the RuleID is stored on the RuleQueue table.

7.1.10.1. Skips and Date/Time Last Skipped

When the Skip Bad Rule feature is enabled, the system uses the skips counter to track the number of times a rule is skipped. The system also tracks the date and time when the rule was last skipped. The system displays this information on the Rule Manager window in the Skips and the Last Skip Date and Time columns.

If the Skip Bad Rule feature has been enabled, the system sets the skips counter to 0 and the last skip date and time to null when a rule is created. If the rule is skipped while being processed against a transaction, the system increments the counter by 1, and sets the last skip date and time to the date and time the rule was skipped.

When the Skip Bad Rule feature is enabled, the Reset Skips icon () is visible above the grid, and it is enabled. The icon is not visible when the feature is disabled.

When you click the Reset Skips icon, the skips counter is reset to 0 and the last skip date and time is set to null for all rules that are visible to your team.

7.2. Dataset generator

The Dataset Generator is used to create datasets to test rules. You can create a dataset using the current NRT database. However, if you wish to avoid impacting the performance of the user interface or system, you can use a database replica as dataset.

If you choose to use a database replica, there are additional steps you must take. There are parameters that must be modified, and an additional script that must be run for additional database configuration.

- The required parameters, which can be set on the General Settings window, are:
 - UseRuleTesterDataSource - Set this parameter to Enabled to indicate that a secondary database, if configured, is to be used. By default, it is disabled.
 - RuleTesterReadOnlyDataSource - Set this parameter to Enabled to indicate that the database replica is read-only. By default, it is disabled, which means the replica to be used is not read-only.
 - RuleTesterUseDetailAsDataset - Will dictate if the test on the database replica will be run on the DETAIL table or a Dataset. Default value: 0 (Tests will run against the Dataset.)

(See the *Root Administrator and System Administrator User Guide* for additional information about the General Settings parameters.)

- A script must be run to indicate the database path of the read-only database replica against which the Rule Tester will run. The script can be found in the Rule Tester folder in the additional_scripts.zip distribution file.

A separate database connection for the Rule Tester must be configured using the following columns in the PRM_TENANTS table at root database level schema:

- RULE_TESTER_SERVER_NAME
- RULE_TESTER_DATABASE_NAME
- RULE_TESTER_URL
- RULE_TESTER_USER_NAME
- RULE_TESTER_PASSWORD
- RULE_TESTER_DB_MIN_CONNECTION
- RULE_TESTER_DB_MAX_CONNECTION

NOTE

The PRM server has to be restarted after running the Additional Scripts for setting the Rule Tester replica.

7.2.1. Generate a dataset using the current NRT database

Follow these steps to generate a dataset using the current NRT database.

1. Go to **Risk Strategy & Control**.
2. Go to **Rule Management > Dataset Generator**.

The screenshot shows the 'Dataset Generator' interface. At the top, there's a breadcrumb trail: 'Risk Strategy & Control / Rule Management / Dataset Generator'. Below it, the title 'Dataset Generator' is followed by a subtitle: 'Use the Dataset Generator to create realistic datasets for testing new and edited rules.' A blue 'GENERATE DATASET' button is in the top right corner. The main form area is titled 'GENERATE DATASET' and includes a 'Name' field, 'Performance Settings' (Time out generation after 60 minutes, Time out rule test after 60 minutes), 'Time Range' (Last 3 days, Last 7 days, Last 2 weeks, Last 30 days, Custom), 'Start Date' and 'End Date' pickers, and a 'DATASET ENTRANCE CRITERIA' section. The 'DATASET ENTRANCE CRITERIA' section has a 'CHECK SYNTAX' button and a 'Clear' button.

3. In the GENERATE DATASET area, type a **Name** for the dataset.
4. In the Time Range area, select the range of days to include in the dataset. Or, use the calendar pickers to select a range of dates.

5. To ensure optimal performance, you can modify the following settings from their default settings:
 - **Time out generation after 60 minutes**
 - **Time out a rule test after 60 minutes**
6. Use the SQL editor to add criteria for the dataset. You can include transaction fields, demographic fields, and operators. The following is an example:

```
DETAIL.RECORD_SOURCE_ID IN (13, 17, 27, 32) AND
DETAIL.SD_TRAN_CDE_CAT IN ('21', '22', '29',
'31', '32', '33', '39')
```

7. Click **CHECK SYNTAX** to validate the syntax.
8. Click **GENERATE DATASET**.

The system generates a dataset a new dataset for testing rules.

Dataset Generator

Use the Dataset Generator to create realistic datasets for testing new and edited rules.

GENERATE DATASET

LAST DATASET GENERATED				
Name	Time Range	Transaction Count	Marked Transaction Count	Status
newdataset	2023-07-24 to 2023-07-27 (3 days)	0	0	Available

GENERATE DATASET

Name:

Time Range: Last 3 days Last 7 days Last 2 weeks Last 30 days Custom

Performance Settings:

Time out generation after: minutes

Time out rule test after: minutes

Start Date: End Date: 3 days

DATASET ENTRANCE CRITERIA

NOTE

While the dataset is being generated, you can navigate to other windows and continue with your work.

7.2.2. Generate a dataset using a replica of the NRT database

Follow these steps to generate a dataset that is the read-only replica of the current NRT database.

NOTE

Both the UseRuleTesterDataset and RuleTesterReadOnlyDataSource parameters must be enabled.

1. Go to **Risk Strategy & Control**.
2. Go to **Rule Management > Dataset Generator**.

The Dataset Generator window opens. The Name field contains the word DETAIL and is read only. The Generate Dynamic Running Days switch is disabled.

3. To ensure optimal performance, you can modify the following settings from their default settings:
 - **Time out generation after 60 minutes**
 - **Time out a rule test after 60 minutes**
4. Your next steps depend on whether you leave the **Generate Dynamic Running Days** switch disabled or enable it.
 - **Disabled** - If you leave the Generate Dynamic Running Day switch disabled, then:
 - a. Use the Date Picker to select the date range for the dataset.

The Date Picker allows a maximum of DAYSTOKEEP of DETAIL table from the read-only database. If the DETAIL table of the read-only database has a 90 days retention period, the Date Picker will allow a selection of a maximum 90 days in the past from the current date.

- b. Click **GENERATE DATASET**.

The system will do the following:

- Count the total number entries from Detail for the selected time range.

The data is filtered by User's Team Portfolios.

- Count the total number of entries from Detail Flag table for the selected time range.

The data is filtered by User's Team Portfolios.

The data is correlated with the transactions picked up from Detail table.

- c. Once a dataset has been generated from the Dataset Generator window, the user will be able to test a rule from the Rule Tester window.

The details on the Rule Tester window will be displayed in read-only mode as follows:

- Name: DETAIL

- Start Date: As per user selection in DatePicker
 - End Date: As per user selection in DatePicker
 - Transactions: Total Count from DETAIL table from the read-only database for the time range selected by user.
 - Marked Transactions: Total count from DETAIL_FLAG table from the read-only database for the time range selected by user.
 - Transactions Used in Test: Dynamically updated based on the number of transactions processed during testing; the maximum value is the value of Transactions section.
 - STATUS:
 - RUNNING_A_TEST - During the processing
 - AVAILABLE - If there are no tests in progress
 - In Use By - The First and Last Name of the user running the test or N/A when no tests are in progress.
 - The Test Results and Previous Test Results will display statistical data based on the same logic already implemented.
- **Enabled** - If you enable the Generate Dynamic Running Days switch, then:
- a. Select a predefined date range from the Dataset Generator window.

On the Dataset Generator window the available options are:

Last 3 Days
 Last 7 days
 Last 2 weeks
 Last 30 days

- b. Click **GENERATE DATASET**.

The system will do the following:

- Count the total number entries from Detail for the selected time range.

The data is filtered by User's Team Portfolios.

- Count the total number of entries from Detail Flag table for the selected time range.

The data is filtered by User's Team Portfolios.

The data is correlated with the transactions picked up from Detail table.

NOTE

Since the system will automatically regenerate the counts, these numbers will differ from one day to the next, as per the volumes available in the DETAIL and DETAIL_FLAG tables.

- c. Once a dataset has been generated from the Dataset Generator window, the user will be able to test a rule from the Rule Tester window.

The details on the Rule Tester window will be displayed in read-only mode as follows:

- Name: DETAIL
- Start Date: As per user selection in predefined date range
- End Date: As per user selection in predefined date range
- Transactions: Total Count from DETAIL table from the read-only database for the date range selected by user.
- Marked Transactions: Total count from DETAIL_FLAG table from the read-only database for the date range selected by user.
- Transactions Used in Test: Dynamically updated based on the number of transactions processed during testing; the maximum value is the value of Transactions section.
- STATUS:
 - RUNNING_A_TEST - During the processing
 - AVAILABLE - If there are no tests in progress
- In Use By - The First and Last Name of the user running the test or N/A when no tests are in progress.
- The Test Results and Previous Test Results will display statistical data based on the same logic already implemented.

7.3. Test a rule

The Rule Tester maximizes the efficiency of a rule before deploying it into production. It does this by testing the rule against a dataset of transaction and demographic data.

Follow these steps to test a rule:

1. Go to **Risk Strategy & Control > Rule Management > Rule Tester**.

Risk Strategy & Control / Rule Management / Rule Tester

Rule Tester

Use the Rule Tester to maximize the efficiency of a rule before deploying it into production. The rule is tested against a dataset consisting of transaction and demographic data. If you do not have a relevant dataset, you can use the Dataset...

Dataset Details

Name
Start Date
End Date
Transactions
Marked Transactions
Transactions Used in Test
Status
In Use By

Mark Types

There are no nodes to display

TEST RESULTS

Date	Time	Duration	Alerts
No. of Included Transactions	No. of Days Processed	Total Number of Days Included	Test Status
Action		Total	% of Alerts
Marked		-	-
Unmarked		-	-
Overlap by null rule		-	-
Overlap by non null rule		-	-
Marked and overlap by null rule		-	-
Marked and overlap by non null rule		-	-

PREVIOUS TEST RESULTS

Date	Time	Duration	Alerts
No. of Included Transactions	No. of Days Processed	Total Number of Days Included	Test Status
Action		Total	% of Alerts
Marked		-	-
Unmarked		-	-
Overlap by null rule		-	-
Overlap by non null rule		-	-
Marked and overlap by null rule		-	-
Marked and overlap by non null rule		-	-

Test Rule
TEST
Help

NOTE If you do not have a relevant dataset, you can use the Dataset Generator to create one.

2. From the **Test Rule** list, select a rule that has not been previously deployed.

NOTE You can also right-click a rule that has not been previously deployed from the Rule Manager page and select **Test Rule**.

3. In the **Mark Types** list, select the mark types to include in the test.

4. Click **Test**. You can navigate to other windows and continue with your work while the test is running. If you need to stop the test before it completes, click **Cancel Test**.

NOTE If the dataset is in use, the Test button is disabled, the Status field in Dataset Details indicates the dataset is being used, and the In Use By field lists the username of the user running the test.

If the dataset is not in use, the value in the Status field is "AVAILABLE".

The system shows a progress bar. The percentage in the Test Progress field is incremented as the Rule Tester completes its processing for each day. For example, if there are five days in the specified date range, and the Rule Tester has finished processing the transactions for two of those days, the percentage will be 40%.

The following fields in the TEST RESULTS section are updated as testing progresses:

- Date - The date on which the test was initiated.
- Time - The time at which the test was initiated.
- Duration - The length of time the test has run.
- Alerts - The number of alerted transactions found in the dataset.
- No. of Included Transactions - The number of transactions already processed in the specified date range.

NOTE This value is incremented each time the Rule Tester finishes processing transactions for one of the days in the specified date range.

- No. of Days Processed - The number of days, part of the specified date range, already processed.

NOTE This value is incremented each time the Rule Tester finishes processing transactions for one of the days in the specified date range.

- Total Number of Days Included - The total number of days specified in the date range.
- Test Status - The status of the transaction batch being processed. The valid values for the Test Status field in the TEST RESULTS section are as follows:


Running
Completed
Canceled By User
Canceled By System
Canceled By Timeout

The valid values for the Test Status field in the PREVIOUS TEST RESULTS section are as follows:


Completed
Canceled By User
Canceled By System
Canceled By Timeout

5. Review the results of the test.

- a. Expand the **Alerted Transactions that are Marked (Hits)** and the **Alerted Transactions that are not Marked (False Positives)** sections. For performance reasons, the data is not expanded by default.



- b. Click **Load Results** in each section to see the Hits and/or False Positives.



- The Hits table shows all transactions that were previously marked by a user and were alerted on by a rule during this test.
- The False Positives table shows all transactions that were *not* previously marked by a user but were alerted by a rule during this test.

The following screenshot shows an example of False Positives:

Test Rule

myTestRule

TEST

ALERTED TRANSACTIONS THAT ARE MARKED (HITS)

ALERTED TRANSACTIONS THAT ARE NOT MARKED (FALSE POSITIVES)

Transaction Date and Time	Mark Type	Amount 1	NRT Score	NRT Reason Code 1	Date Key
2020-10-20 23:51:03		400.00	795	93	
2020-10-20 23:44:08		400.00	268	55	
2020-10-20 23:29:22		925.97	529	63	
2020-10-20 23:28:22		377.36	22	25	
2020-10-20 23:28:09		300.00	194	55	
2020-10-20 23:27:22		716.72	958	80	
2020-10-20 23:27:22		956.32	381	97	
2020-10-20 23:26:22		786.37	54	2	
2020-10-20 23:26:22		981.69	234	29	

1 - 50 of 297

Page Size 50

If additional tests are run against a different dataset or after updating the rule logic, the PREVIOUS TEST RESULTS section lets you see if the test results have improved.

7.4. Queues

Queues contain alerts that require an analyst's review. By assigning queues to analysts, team administrators can control the types of alerts sent to each analyst. If an alert matches more than one queue, it is distributed to every queue it matches.

You can assign more than one queue to each analyst. You can also assign the same queue to multiple analysts.

Described below are the different types of queues:

Smart

Custom queues based on SQL. You can add, delete, edit, and clone Smart queues. You can also assign Smart queues to portfolios and deploy them.

Batch (End of Day)

Profile queues based on SQL that are checked while running the dedicated Batch (End of Day) jobs. You can add, delete, edit, and clone Batch queues. You can also assign Batch queues to portfolios and deploy them.

Forward

Custom queues configured as forward queues to which analysts can forward alerts from the Review window. You can add, delete, edit, and clone Forward queues.

Group

Queues that do not have custom SQL logic and are used to group multiple rules unassigned to Smart Queues. You can add, delete, edit, and clone Group queues.

Matching

Rule-based queues created from the Rule Manager. Manage these queues from the Rule Manager window.

System

Orphan, Watch, Catch-All, Compromise, Forward, and Timeout queues created by the system. These queues cannot be edited, deleted, or cloned.

7.4.1. Roles and permissions

By default, Team Administrators and Supervisors are assigned the permissions needed to perform both the Queue Manager and Queue Assignment functions. Customers, however, can create custom roles to separate the management and assignment functions. The permissions that pertain to the Queue Manager window are:

- View Queues
- Manage Queues

The permissions that pertain to the Queue Assignment window are:

- View Queue Assignments
- Manage Queue Assignments

7.4.2. Queue manager

Queues contain alerts that require review. You define queues and assign them to analysts to control the types of alerts that analysts receive. If an alert matches more than one queue, it is distributed to every queue it matches.

To view a list of active queues, follow these steps:

1. Go to **Risk Strategy & Control**.
2. Click **Workflow & Queue Management**.
3. Click **Queue Manager**. The Queue Manager window opens.

Risk Strategy & Control / Workflow & Queue Management / Queue Manager

Queue Manager

This window enables you to perform the following queue functions: view, add, delete, edit, and clone. The functions that are available depend on the type of queue you select. The types of queues are Smart, Batch (End of Day), Forward, Group, Matching and System.

Smart Matching Group Batch (End of Day) Forward **System**

	Queue ID	Queue Name	Dimension	Alert Color	Assigned	Deployed	Pending	Alert Behavior	Created Date and Time
☐	-7	Compromise Queue	Card, Merchant, Customer, T...		4	4		Discard	
☐	-3	Orphans Queue	Card, Merchant, Customer, T...		14	14		Discard	
☐	-4	Watch Queue	Card, Merchant, Customer, T...		14	14		Discard	
☐	-6	Forwards Queue	Card, Merchant, Customer, T...		14	14		Discard	
☐	-2	Catch-All Queue	Card, Merchant, Customer, T...		14	14		Discard	
☐	-5	TimeOut Queue	Card, Merchant, Customer, T...		14	14		Discard	

1 - 42 Page Size 50

The tabs above the table enable you view the different types of queues.

Depending on the type of queue, you can use this window to add, edit, clone, or delete queues, assign queues to portfolios, and deploy queues. You can also export one or more selected queues or all queues.

Use the **Dimensions** field to filter all queues, except for Group queues, for a specific dimension.

Since the Smart queues and Batch (End of Day) queues can be assigned to portfolios and deployed, only their tabs include the following columns:

- Assigned - Number of portfolios to which the queue is assigned.
- Deployed - Number of portfolios to which the queue is deployed.
- Pending - Number of portfolios to which the queue is assigned, but not yet deployed.

Click a queue's name in the table to preview details like its name, description, entrance criteria, and SQL syntax.

7.4.2.1. Add a queue

You can add a new queue for any queue type except Matching or System type queues.

1. From the Queue Manager, go to the tab for the type of queue that you want to add.
2. Click **+**.
3. Specify the details for the queue like **Queue Name**, **Alert Behavior**, **Alert Color**, and **Description**.
4. If you want to send an **Email Notification for Pending Alerts**, click the toggle.
 - a. In the Email Notification window, specify the details for the email and click **Save**.
5. The following are details for specific queue types:

Batch or Smart queue

6. Select the **Dimension**. Depending on the selected Dimension, fields corresponding to this Dimension are available in the SQL condition. Rules move alerts into queues. The queues can only be assigned to Portfolios that match this queue's Dimension. Finally, the alerts are run against this Dimension and assigned to the Portfolio matched by the alerted transaction.
 - You can make the queue visible to only the team members who created or edited queue.
 - Use the SQL editor to define Entrance Criteria or Queue Logic. You can select from a predefined list of SQL logic variables and reuse these variables in any queue. Click the icons to the right to select transaction variables, transaction history fields, demographic fields (only for Smart queues), or computed variables.

NOTE | If the Queue Logic is completed, there is no need to include Entrance Criteria and vice versa.

1. Click **Syntax Check** to verify your SQL code. A syntax check is automatically run when you save the queue.

Forward queue

2. Select the **Dimension**.

Only queues assigned to Portfolios that match this Dimension can be forwarded to this queue.
You can make the queue visible to only the team members who created or edited queue.

3. Click **Save Queue**.

7.4.2.2. Edit, delete, or clone a queue

The following actions are only available for some types of queues.

1. To edit a queue, select its corresponding checkbox, and then select the **Edit** icon from the context menu or the toolbar at the bottom of the page. When the EDIT QUEUE page opens, make your changes.

NOTE

You can only edit the alert color and notification for alerts pending in the queue for deployed Smart or Batch (End of Day) queues.

2. To delete one or more queues, select the corresponding checkboxes, and then select the **Delete** icon from the context menu or the toolbar at the bottom of the page.

NOTE

You cannot delete deployed queues.

3. To clone a queue, select the corresponding checkbox, and then select the **Clone** icon from the context menu or the toolbar at the bottom of the page. When ADD QUEUE page opens, make your changes to create the new queue.

NOTE

When cloning, click the name of the queue to preview its details.

7.4.2.3. Export queues

To export queues, filter and sort the data and then:

1. Click **Export Selection** on the toolbar. You can save the data to a .CSV or .XLS file.

2. Click the **Export All** icon above the table. You can save the data to a .CSV, .XLS, or .PDF file.

NOTE

For export to .XLS, due to Microsoft Excel cell size limitations, the information is truncated to max: 32,767 characters.

7.4.3. Queue assignment

Use the Queue Assignment page to distribute and prioritize alerts for analysts. By assigning queues to analysts, you can control the types of alerts that are sent to each analyst. If an alert matches more than one queue, it is distributed to every queue it matches.

1. Go to **Risk Strategy & Control**.
2. Click **Workflow & Queue Management**.
3. Click **Queue Assignment**.

The page has the following sections:

Available

Lists the dimensions. You can expand each dimension to show the portfolios to which it is assigned. Then you can expand each portfolio to see the queues assigned to it.

Use the checkbox under the Available section to **Hide Undeployed Queues**.

Workspace

Click the + to expand the area, so you can review the queues that you plan to assign to a user before you select the user. If you choose not to use the Workspace, you can assign the queues directly from the Available section to the Assigned section.

Assigned

Lists the users on the team identified in the Team field.

7.4.3.1. Assign queues to users

You can assign and unassign queues to users. You can also copy the queue assignment from one user to another.

1. If you have more than one team, select the **Team** to which you want to assign queues. If you have only one team, the **Team** field shows the name of that team and is disabled.
2. In the Available section, select the checkboxes that correspond to the queues that you want to assign to one or more team members.

To find the queues that you want to assign to a team member, use the filter field or expand the dimension and the portfolio to which the queues belong.

3. If you expanded the Workspace, click the arrow between the Available section and the Workspace.

The Workspace lists the selected queues. You can revise and drag and drop to prioritize the list. You can also hold your cursor over the name of a queue until you see a double arrow to the left of the queue name. Click the up or down arrow to change the queue's priority.

When you are done, select the queues to assign to the team members.

4. In the Assigned section, select the checkboxes for the team members to which you want to assign the queues.

To find the team members to which you want to assign the selected queues, use the filter field.

5. Click the arrow between the Workspace and the Assigned section.

The selected queues and their portfolios are listed under the selected users.

NOTE

If you do not want to use the Workspace, you can collapse it. Then, you assign the queues by clicking the arrow button between the Available section and the Assigned section.

6. Click **SAVE**.

7.4.3.2. Unassign queues from a user

1. In the Assigned section, expand a user's tree to see their portfolio and queue assignments.
2. Hold your cursor over the queue that you want to unassign.

NOTE

If you want to unassign all queues by portfolio, hold your cursor over the portfolio whose queues you want to unassign. Then, proceed with the rest of these steps.

3. Click the minus sign that appears at the end of the queue (or portfolio) name.
4. Click **SAVE**.

7.4.3.3. Copy queue assignments from one user to another

Use these steps to copy queue assignments from a user to other users on the current team:

1. In the Assigned section, select the user from which you wish to copy the queue assignment.
2. Select the **Copy to** icon.
3. On the COPY QUEUES TO USER window:
 - a. Select the users to which you want to copy the queue assignment.
 - b. Select to **Override** (default) the user's existing assignments or to **Append** the selected queues to the user's existing queue assignments.
 - c. Click **SAVE CHANGES**.
4. Click **SAVE**.

NOTE

You can also use the **Copy from** icon to copy queue assignments to selected users from other users.

7.5. Computed variables

A computed variable is SQL code that references data from an inbound transaction, demographic data, or transactional historical data which can be used as criteria in a rule. Computed variables make writing rules and using queues quicker. For example, you can write a condition that says: `if amount greater than 500 set @mycomputedvariable to 1`. Then, you can create a rule that generates an alert using `mycomputedvariable`, like `if merchant = starbucks and @mycomputedvariable = 1`.

Use the Computed Variables Manager to view, add, delete, edit or clone computed variables.

To access the page:

1. Go to **Risk Strategy & Control**.
2. Go to **Feature Management > Computed Variables Manager**.

Computed Variables Manager

From the Computed Variables Manager screen, you can view, add, delete, edit, and clone computed variables. The content of a computed variable can be related to data from inbound transactions, demographic data or other data within the system. The available types of computed variables are: Real-Time, Near Real-Time and Batch (End of Day) which can be used while creating Rules or Queues.

Near Real-Time Real-Time Batch (End of Day)						
Dimensions		Select Dimension + 📄 🔍 📌 🔄 👤 Help				
Comput...	Computed Variable Name	Dimension	Pending ...	Created Date and Time	Created By	
☐ 72	@travelAboveValueLimitAct	Account	N	2019-07-29 07:36:58	Automatic PRM Server Task	
☐ 71	@travelAboveValueLimitUAID	User Account ID	N	2019-07-29 07:36:58	Automatic PRM Server Task	
☐ 70	@travelAboveValueLimitEmpl	Employee	N	2019-07-29 07:36:58	Automatic PRM Server Task	
☐ 69	@travelAboveValueLimitUAN	Customer	N	2019-07-29 07:36:58	Automatic PRM Server Task	
☐ 68	@travelAboveValueLimitCard	Card	N	2019-07-29 07:36:58	Automatic PRM Server Task	
☐ 67	@travelInValueLimitAct	Account	N	2019-07-29 07:36:58	Automatic PRM Server Task	
☐ 66	@travelInValueLimitUAID	User Account ID	N	2019-07-29 07:36:58	Automatic PRM Server Task	
☐ 65	@travelInValueLimitEmpl	Employee	N	2019-07-29 07:36:58	Automatic PRM Server Task	
☐ 64	@travelInValueLimitUAN	Customer	N	2019-07-29 07:36:58	Automatic PRM Server Task	
☐ 63	@travelInValueLimitCard	Card	N	2019-07-29 07:36:58	Automatic PRM Server Task	
☐ 62	@hasGamblingNotifAct	Account	N	2019-07-29 07:36:58	Automatic PRM Server Task	
☐ 61	@hasGamblingNotifUAID	User Account ID	N	2019-07-29 07:36:58	Automatic PRM Server Task	

1 - 24 < > Page Size 50 ▾

- Use the **Dimensions** field to filter the Computed Variables in the table by a group that contains information like card or account.
- Click a tab to see a list of computed variables for the selected type: Real-Time, Near Real-Time, and Batch (End of Day). Each tab has a series of columns with information about the computed variable. The following columns require additional explanation:

Pending

Shows Y if Dual Control is enabled and another authorized user must approve a computed variable that you created or updated.

Visible for Team Only

Indicates if this option is enabled. If it is, then the computed variable is only visible to the team members who created or edited the computed variable. If not, the computed variable is visible to anyone in the organization with access to the Computed Variables Management page. This is useful when you have several teams in an organization with varying business and operational needs, like a fraud team and AML team.


Auto Action

(Not applicable to Real-time tab) Indicates if Auto Action is enabled. If it is, the computed variable can be referenced in any type of rule, or those with auto-action set. If not, you can use computed variables only in rules without auto-action set.

Dependency Count

Shows the number of rules or queues a computed variable is used in.

- Click a computed variable name to see a preview of its Name, Description, Entrance Criteria and Computed Variable Logic.



7.5.1. Add computed variables

Use the following steps to add a computed variable.

1. On the Computed Variables Manager page, click the tab for the type of computed variable that you want to create.
2. Click +.
3. Give the variable a Name starting with @ (for MSSQL) or v_ (for Oracle). In SQL this indicates a variable name.
4. Select a **Dimension**. A Dimension defines the group that contains information like Card, Account, Merchant, or Terminal information.
5. Select a **Format**. The options are as follows:

MSSQL	Oracle
BIT	DATE
DATETIME	FLOAT
INT	INTEGER
MONEY	TIMESTAMP
VARCHAR	VARCHAR

For Auto Action Only computed variables, the format options are:

MSSQL	Oracle
BIT	INTEGER
INT	

6. (Not applicable to Real-time tab) Select **Auto Action Only** if the computed variable can be referenced in any type of rule, or only those with an auto-action set. When this setting is disabled, you can use the computed variable in a rule without auto-action.

7. Select **Visible for Team Only** if the computed variable is visible to only the team members who created or edited the computed variable. If Visible for Team Only is not selected, the computed variable is visible to anyone in the organization with access to the Computed Variables Management page. This is useful when you have several teams in an organization with varying business and operational needs, like a fraud team and AML team.
8. Use the SQL editor to add transaction variables or a clear option as Entrance Criteria. For example, the variable named @travelInValueLimitCard might have the following Computed Variable logic:

```
set @travelInValueLimitCard = (select case when exists (select 1 from
travel_notifications tn WITH(NOLOCK) where tn.action_level_id=@ACTION_LEVEL_ID
and tn.action_level_key=@ACTION_LEVEL_KEY and @DD_DATE between
tn.travel_start_date and tn.travel_end_date and tn.expected_max_spend_amt >
@MD_TRAN_AMT1)
then 1 else 0 end)
```

In the SQL editor, you can add the following data to the Computed Variable logic:

- Transaction variables
- Transaction history
- Demographic data

For example, if you want to determine if the UAN has an active travel notification with a limit below the current transaction amount:

```
set @travelInValueLimitUAN = (select case when exists (select 1 from
travel_notifications tn WITH(NOLOCK) where
tn.action_level_id=@ACTION_LEVEL_ID and
tn.action_level_key=@ACTION_LEVEL_KEY and @DD_DATE between
tn.travel_start_date and tn.travel_end_date and tn.expected_max_spend_amt >
@MD_TRAN_AMT1) then 1 else 0 end)
```

9. Click **Save**. If Dual Control is enabled, another user must authorize your changes unless you have an override code.
 - If you have an override code, click **Override**. Enter your credentials and code and click **OK**. The Computed Variable is saved.
 - If you do not have a code, the Pending column for your computed variable has a Y to indicate that another user must authorize your computed variable. When that user logs onto the system, they must select the variable and click the **Edit for Approval** icon. Then they can **Approve** or **Discard** the variable.

If this user edits the variable, they must also submit it for authorization. When the next user opens the variable to authorize it, they can click **Current SQL** to view the currently authorized logic versus the request for the change to the logic. After reviewing this information, they can decide whether to **Approve** or **Discard** the changes.

7.5.2. Edit, delete, or clone a computed variable

To edit a computed variable, select its corresponding checkbox, and then select the Edit icon from the context menu or the toolbar at the bottom of the page. When the EDIT COMPUTED VARIABLE page opens, make your changes.

To delete one or more computed variables, select the corresponding checkboxes, and then select the Delete icon from the context menu or the toolbar at the bottom of the page.

NOTE

You cannot delete a computed variable if it is referenced in any real-time rules, near real-time rules, batch queues, or smart queues, regardless of whether those rules or queues are deployed.

Complete the following steps to delete a computed variable referenced in one or more real-time or near real-time rules:

1. Undeploy the rule(s) if not already undeployed.
2. Delete the rule(s).
3. Delete the computed variable.

Complete the following steps to delete a computed variable referenced in one or more batch or smart queues:

1. Undeploy the queue(s) if not already undeployed.
2. Delete the queue(s).
3. Delete the computed variable.

To clone a computed variable, select the corresponding checkbox, and then select the Clone icon from the context menu or the toolbar at the bottom of the page. When CLONE COMPUTED VARIABLE page opens, make your changes to create the new computed variable.

NOTE

When cloning, click the name of the computed variable to see its entrance criteria and computed variable logic in a preview pane.

7.5.3. Export computed variables

To export computed variables, filter and sort the data and then:

- Click **Export Selection** on the toolbar. You can save the data to a .CSV or .XLS file.
- Click the **Export All** icon above the table. You can save the data to a .CSV, .XLS, or .PDF file.

NOTE

For export to .XLS, due to Microsoft Excel cell size limitations, the information is truncated to max: 32,767 characters.


7.6. List management

Use the List Management page to load data from a file, view the data in the table, and delete data from the table.

The PRM_REF_DATA table contains data such as lists of compromised accounts, VIP accounts, and risky IP addresses. Users can create rules that reference the lists so that incoming transactions are checked against the data.

To access the page:

1. Go to **Risk Strategy & Control**.
2. Go to **List Management**.



The List Management page shows the lists that are currently available for use in rules.

- Use the **Change Column Visibility** icon to show (or hide) columns in the table.
- Use this window to view the list details or add, edit, clone, and delete lists.

7.6.1. View a list

1. On the List Management page, click the hyperlinked name of the list whose definition and data you want to see.

Alternatively, you can select the checkbox for the list, and then either click the **View List** icon () in the selection toolbar, or right-click and select **View** from the right-click menu.

The VIEW LIST window opens.

VIEW LIST

Help

LIST DEFINITION

List Name

PRM_REF_DATA

List Type

Custom

☐ Sync with Real-time

☒ Periodical Clean-up

Days to Keep

☒ Partition list

No. of Partitions

Value Column Name

PRM_REF_DATA_ID

Column Type

NVARCHAR

Format Details

50

☒ Use as Key

Value Column Name

PRM_REF_DATA_VALUE

Column Type

NVARCHAR

Format Details

50

☒ Use as Key

Value Column Name

DDATE

Column Type

DATE_TIME

Format Details

yyyy-MM-dd

☒ Use as Key

LIST VALUES

CLOSE

NOTE

To quickly view the list's values, click the down arrow next to the LIST DEFINITION heading to collapse the definition and expand the LIST VALUES section.

- Click **CLOSE**.

7.6.2. Add a list

- On the List Management page, click **+**.

ADD LIST

[Help](#)

List Name *
PRM_REF_DATA

Description
Please provide list description...

List Type *
[Dropdown]

☐ Sync with Real-time

☐ Periodical Clean-up

Days to Keep [Input]

☐ Partition list

No. of Partitions [Input]

Value Column Name *
[Input]

Column Type *
[Dropdown]

Format Details *
[Input]

☐ Use as Key

[+ ADD COLUMN](#)

SAVE LIST **CLOSE**

2. From the Add List page, type the name of the new list in the field to the right of **PRM_REF_DATA**.

The List Name cannot contain more than 50 characters.

3. Select a **List Type**.

4. If you want the new list to be kept consistent with the real-time database, select the **Sync with Real-time** checkbox.

5. Use the toggle to determine if the table should have a **Periodical Clean-up**.

a. **Days to Keep** determines the default cleanup period and is entered when the table is created.

6. Use the toggle to determine if the table should have a **Partition List**.

a. Set the **No. of Partitions** required (minimum of two).

- On Oracle database, partition's type is HASHED, and partition key is columns' set selected as primary key.
- On SQL Server database, new objects are created:
 - partition schema with name 'ps_' + table_name.
 - partition function with name 'pf_' + table_name.
 - sequence with name 'seq_' + table_name.
 - new column PartitionBucketKey is added to table. It stores sequence value.
 - a partitioned clustered index is created using primary keys columns + PartitionBucketKey on

partition schema 'ps_'+ table_name + '(PartitionBucketKey).

7. Enter the information for each column in the list.

- The **Value Column Name** is the name of the field or column. For example, if the column will store card numbers, you might name this Card. You can add up to 20 columns in each list.
- Set a data type from the **Column Type** list.
- The value in **Format Details** depends on the selection in **Column Type**.
 - For Varchar (maximum 900 characters) and Nvarchar (maximum 450 characters), type a size.
 - For Number, type the precision and scale in this format: 18,2. Precision is the total number of digits. Scale is the number of digits after the decimal separator.
 - For Date and Time, type the date format like yyyy-MM-dd HH:mm:ss.

8. Select the **Use as Key** checkbox to select columns that contain unique identifiers, like PANs.

9. Click **+ADD COLUMN** to add more columns. Return to step 5.

10. Click **SAVE LIST**.

7.6.3. Edit a list

1. On the List Management page, select the checkbox for the list whose values you want to edit.

NOTE You cannot edit the list definition information.

2. Click the **Edit List** icon in the selection toolbar, or right-click and select **Edit** from the right-click menu.

The EDIT LIST window opens.

NOTE To quickly view the list's values, click the down arrow next to the LIST DEFINITION heading to collapse the definition and expand the LIST VALUES section.

3. If you are editing a list, in the LIST VALUES section, you can do the following:

- Click the **Import Values** icon to import list values. You can import values from a comma-separated values (CSV) file or a text (TXT) file.
- Select the checkbox for a list value, then click the trash can (Delete elements) icon to delete the value.

4. Click **Close**.

7.6.4. Clone a list

1. On the List Management page click the checkbox for the list that you want to clone. If you click the row, the list opens in view-only mode.

2.



Click the clone button, + This opens an ADD LIST window of the selected list. The data values are maintained with the following exceptions:

- The original list name is used but appended with `_CLONE` as the initial name of the clone.
 - Fields from the `PRM_REF_DATA` table used in the selected list are automatically applied to the clone, but fields not from the `PRM_REF_DATA` table in the selected list are not included in the clone.
 - Other field values are automatically applied to the clone.
3. If applicable, edit the default List Name by removing the `"_CLONE"` text that was appended to the original and make other changes to give a name that represents the intent of the list.
 4. Make changes to the remaining fields as necessary. Use the Help link on the ADD LIST window to obtain field information as needed.
 5. Click **SAVE LIST**.

7.6.5. Delete lists


1. On the List Management page, select the checkbox for the list to edit or delete.
2. Click the **Delete Lists** icon in the toolbar, as needed, at the bottom of the table.

NOTE If a list is used in rules, queues, or aggregates, the system confirms that you want to delete.

7.7. External messaging

When you click the EXTERNAL MESSAGING MANAGEMENT tile on the Configuration window, the External Messaging Status window opens. It displays the statuses of requests and notification messages sent to external systems such as a host, mobile alerting system, or dispute management system. The External Messaging Status window enables you to view and manage external message processing. If no external message data is available, the following message is displayed when the window opens: "There are no External Messages available."

The following is a sample External Messaging Status window:



The window contains a filter that enables you to select a status and display only the requests and notification messages with that status.

7.7.1. State and nonstate actions

There are two types of actions, state and nonstate. Each is handled differently.

In the case of state actions, the external message is sent to request that the external system perform a specific state action. PRM does not consider the action to be completed until the external system responds indicating that the action was performed. The following actions are state actions:

- Mark
- Block/Unblock
- POC Block
- Response Required
- Watch
- Override
- Travel Notification

In the case of nonstate actions, the external message is sent to notify the external system that the action took place in PRM. The following actions are nonstate actions:

- Letter
- Notes
- Email
- Reminder
- Forward
- Export
- Notification Notes
- Manual Notification
- Call - deprecated
- Alert
- Delete Alert
- Remove Alert from Queue
- Notify

7.7.2. Statuses

Actions sent to an external system are given a status that you can use to determine the progress of the external message processing. The statuses are:

Requested

The action has been initiated but not yet sent to the external system.

Submitted

The action has been sent to the external system, but a response has not been received.

Failed

The action could not be sent to the external system.

Completed

The action was sent to the external system, and a response was received.

In Progress

The action is in progress and being prepared to be executed.

Not Processed

The action was not processed because it did not meet the Message Logic - Message Level criteria.

7.7.3. Managing external messages

You can take several management actions depending on the status of a message on the External Messaging Status window.

- If a message has a status of Failed or Submitted, you can retry sending the same action to the external system.

To retry an action, select the message in the grid, and then click the **Retry** icon in the selection toolbar.

NOTE

The Retry action will be performed on all messages that were processed as part of the selected message batch when Enable Batch is set (Batch = 'Y').

- If a message has a status of Requested, you can update its status to Complete in the event that the external system's update did not reach PRM.

To change a message's status to Complete, select the message in the grid, and then click the **Complete** icon in the selection toolbar.

NOTE

The Complete action will be performed on all messages that were processed as part of the selected message batch when Enable Batch is set (Batch = 'Y').

- You can reset an incomplete action. The reset action is available for messages with a status of Requested, Submitted, or Failed. It will revert the action that triggered the message. For example, if a block was applied, resetting it from the External Messaging Status window removes the block.

To reset an action, select the message in the grid, and then click the **Reset** icon in the selection toolbar.

NOTE


The Reset action is not available for mark/unmark messages and messages corresponding to nonstate actions.

7.8. Communication templates

Communication templates allow analysts to contact customers about suspicious or fraudulent behavior on their accounts. Using the templates, analysts can send letters and emails personalized with recipient information and transaction details. Templates consist of text and tags.

To open the **Communication Templates** window:

1. Go to **Risk Strategy & Control**.
2. Click **Action Codes & Configuration**.
3. Click **Communication Templates**.



The Communications Templates window contains the following tabs:

- Templates
- Tags
- Images

7.8.1. Templates

The Templates tab lists all communication templates available in the system. From this window, you can select a dimension to view, add, edit, or delete templates.

The Templates grid lists the following information:

- Name

- Type
- Dimension
- Portfolio
- Description
- Created Date and Time
- Created By
- Modified Date and Time
- Modified By

7.8.2. Tags

Included in communication templates, tags are replaced with data from the database. For example, if your template includes the CITY tag for the Terminal dimension, CITY is replaced with the city stored in the database for the terminal. If that stored city is Seattle, the CITY tag would be replaced with Seattle when you generate a letter or email.

The Tags tab lists all the tags available in the system. From this window, you can select a dimension to view, add, edit, or delete a tag.

7.8.3. Images

You can upload images, such as company logos, and include them in communication templates.

The Images tab lists the images that have been uploaded and are available for use in communication templates. The grid contains the following information about each image:

- Image (the file name for the image)
- Description
- Type (for example, PNG)
- Created By (full name of the user)
- Created Date and Time

From this tab, you can add an image, export all or only selected images, copy an image to the clipboard, or delete one or more images.

7.8.4. Add templates

You can add communication templates to define a standard message for letters or emails sent to customers. When adding email or letter content you can use text, tags, and images.

NOTE

You must have Manage Communication Templates or View Communication Templates permissions to navigate to the Communication Templates page. The Team Administrator role will have both permissions assigned by default.

1. Go to **Risk Strategy & Control > Action Codes and Configurations > Communication Templates** to open

the Communication Templates window.

2. On the Communication Templates window, click + (plus sign) to open the ADD COMMUNICATION TEMPLATE window.
3. Use the fields on the ADD COMMUNICATION TEMPLATE window to add a new communication template:

Type

Select either Letter or Email.

Template Name

Enter a name for the new template.

Dimension

Select the dimension for which the new template will be available.

Logo Image

Optional: Select one of the uploaded images or leave the field blank.

Title Content

Optional: Enter the text that you want to appear below the Logo Image or leave the field blank.

Available Portfolios

Select the portfolio or portfolios for which the new template will be available.

Description

Optional: A short description of the template.

NOTE

If you selected Letter in the Type field, the next field on the ADD COMMUNICATION TEMPLATE window is Letter Content. If you selected Email in the Type field, the next field on the ADD COMMUNICATION TEMPLATE window is Email Content.

Letter Content/Email Content

Enter the text and add the tags needed to create the letter or email content. Click the button in the upper right corner of the field to find and select the tags you want to use.

4. Click **SAVE** to save the newly defined communication template or **CLOSE** to cancel the action.

7.8.5. Edit templates

If the contents of standard messages sent by letter or email to customers need to be updated, you can edit existing communication templates. When editing email or letter template you can use text, tags, and images.

NOTE

You must have Manage Communication Templates or View Communication Templates permissions to navigate to the Communication Templates page. The Team Administrator role will have both permissions assigned by default.

1. Go to **Risk Strategy & Control > Action Codes and Configurations > Communication Templates** to open the EDIT COMMUNICATION TEMPLATE window.

2. On the EDIT COMMUNICATION TEMPLATE window, make your changes. You can modify any field, except for the Dimension field.
3. Click **SAVE** to save the changes or **CLOSE** to cancel the action.

7.8.6. Add tags

Tags can be added to be used in communication templates to quickly set up a letter or e-mail on the Review Screen.

NOTE You must have Manage Communication Templates or View Communication Templates permissions to navigate to the Communication Templates page. The Team Administrator role will have both permissions assigned by default.

1. To add a tag, go to **Risk Strategy & Control > Action Codes and Configurations > Communication Templates**.
2. On the Communication Templates page, select the Tags tab.
3. On the Tags tab, click the +. The Tags overlay screen appears. The field definitions are as follows:

Tag Name

A unique identifier of the tag.

Special characters are not allowed except for "_".

Dimension

Table

The Detail or Master tables from which the tagged field will be chosen.

Field Name

The field name/column for which you wish to define a tag.

Contains sensitive data

If the field needs to be masked, this checkbox should be ticked.

Field Type

A read-only field automatically populated with the data type of the column selected.

Field Format

An input field enabled only when the Date and Number field types are selected.

The format of the Date or Numbers to be used must be entered.

Valid values for Date, Date and Time, Number or Currency Field Without Symbol Formats are listed below:

Date

DATE.MEDIUM, DATETIME.SHORT.MEDIUM, DATETIME.MEDIUM.MEDIUM, MMM yyyy, yyyy-MM-dd hh:mm:ss a, DATETIME.SHORT.SHORT

Number

###,##0.0000

Currency field without symbol

#,##0.00

Description

A short description of the tag.

4. Click **SAVE** to save the newly defined tag or **CLOSE** to cancel the action.

7.8.7. Edit tags

Tags can be edited from the Tags tab on the Communications Templates page.

NOTE

You must have Manage Communication Templates or View Communication Templates permissions to navigate to the Communication Templates page. The Team Administrator role will have both permissions assigned by default.

1. To edit a tag, go to **Risk Strategy & Control > Action Codes and Configurations > Communication Templates**.
2. On the Communication Templates page, select the Tags tab.
3. Select the tag's corresponding checkbox, and then select the Edit icon. You can also edit the tag from the Context Menu.
4. The field definitions are as follows:

Table

The Detail or Master tables from which the tagged field will be chosen.

Field Name

The field name/column for which you wish to define a tag.

Contains sensitive data

If the field needs to be masked, this checkbox should be ticked.

Description

A short description of the tag.

Field type

Data type of the selected field. Read-only.

Field Format

This input field is enabled only when the Date and Number field types are selected. The format of the Date or Numbers to be used must be entered.

Valid values for Date, Date and Time or Currency Field Formats are listed below:

Date

DATE.MEDIUM, DATETIME.SHORT.MEDIUM, DATETIME.MEDIUM.MEDIUM, MM YYYY, YYYY-MM-DD
h.h: mm:ss a, DATETIME.SHORT.SHORT

Number

###,##0.0000

Currency field without symbol

#,##0.00

5. Click **SAVE** to save the newly edited tag or **CLOSE** to cancel the action.

7.8.8. Add image

Use the ADD IMAGE window to upload images, such as company logos, and include them in communication templates.

1. Click the **UPLOAD IMAGE** button to upload an image for use as a logo on a communication template. PNG and JPG file types are accepted.
2. Add a meaningful description for the image.
3. Click **SAVE** or **CLOSE**.