

1. connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.

1. Connect the USB webcam to an available USB port on the computer.
2. Wait for Windows to detect the device automatically.
3. If prompted, install the required drivers from the webcam manufacturer.
4. Open **Device Manager** and verify that the webcam appears under **Cameras or Imaging Devices**.
5. Open the **Camera** app:
 - Press **Windows Key**
 - Type **Camera**
 - Open the Camera application
6. Check whether the webcam video feed appears on the screen.
7. Click the **Capture Photo** button to take a picture.
8. Verify that the photo is saved in the **Pictures > Camera Roll** folder.

2. Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.

1. Connect the printer:
 - For a USB printer, connect the USB cable to the computer.
 - For a network printer, connect the printer to the same Wi-Fi/network as the computer.
2. Turn on the printer and ensure it is ready.
3. Install the printer driver:
 - Open **Settings** → **Devices** → **Printers & Scanners**.
 - Click **Add a printer or scanner**.
 - Select the printer from the list.
 - If Windows does not find the driver automatically, install the driver provided by the manufacturer.
4. Verify printer installation:
 - Open **Control Panel** → **Devices and Printers**.
 - Confirm that the printer appears in the list.
5. Print a test page:
 - Right-click the printer.
 - Select **Printer Properties**.
 - Click **Print Test Page**.
6. Check the printed page to ensure the printer is working correctly.

3. Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem. Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting.

1. Disconnect the Printer

- Unplug the printer's USB cable from the computer.
- Wait a few seconds.
- Attempt to print a document.
- Observe that the printer is unavailable or shows **Offline/Not Detected**.

2. Open Device Manager

- Press **Windows + X**.
- Select **Device Manager**.

3. Check for Printer Issues

- Expand **Printers, Print Queues, or Universal Serial Bus Controllers**.
- Look for:
 - A **yellow warning icon (⚠)**.
 - An **Unknown Device** entry.
 - The printer missing from the list.

4. Reconnect the Printer

- Plug the USB cable back into the computer.
- Ensure the printer is powered ON.

5. Scan for Hardware Changes

- In Device Manager, click **Action** on the menu bar.
- Select **Scan for hardware changes**.
- Windows will search for newly connected devices.

6. Verify Detection

- Check whether the printer appears correctly under **Printers** or **Print Queues**.
- If detected, the warning icon should disappear.

7. Update Driver (If Needed)

- Right-click the printer.
- Select **Update Driver**.
- Choose **Search automatically for drivers**.

8. Print a Test Page

- Open **Control Panel** → **Devices and Printers**.
- Right-click the printer.
- Select **Printer Properties** → **Print Test Page**.
- Confirm successful printing

4. A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications. Hint: Check if another app is using the webcam or if Zoom permissions are enabled.

Troubleshooting: Webcam Works in Camera App but Not in Zoom

Problem

The webcam functions correctly in the Windows Camera app, but no video appears during Zoom meetings.

1. Close Other Applications Using the Webcam

- Exit the **Camera app** and any other video applications such as:
 - Microsoft Teams
 - Skype
 - Google Meet (browser tabs)
 - OBS Studio
- Reopen Zoom and check the video.

2. Verify Camera Permissions in Windows

- Open **Settings** → **Privacy** → **Camera**.
- Make sure:
 - **Camera access for this device** is ON.
 - **Allow apps to access your camera** is ON.
 - **Allow desktop apps to access your camera** is ON.

3. Check Zoom Camera Settings

- Open Zoom.
- Click **Settings** → **Video**.
- Under **Camera**, select the correct webcam from the drop-down list.
- Verify that a live preview appears.

4. Restart Zoom

- Completely close Zoom.
- Open **Task Manager** and ensure Zoom is not running in the background.
- Launch Zoom again and test the camera.

5. Check Device Manager

- Press **Windows + X** → **Device Manager**.
- Expand **Cameras**.
- Ensure the webcam appears without a warning icon.
- If necessary:
 - Right-click the webcam.
 - Select **Update Driver**.

6. Test the Webcam in Zoom

- Start a new meeting.
- Click **Start Video**.
- Confirm that your webcam video is displayed.