

Start

Configure S3 bucket: [here](#)

VPC

How to create VPC and subnets: [here](#)

First, create a VPC

The screenshot shows the AWS VPC console interface. At the top, a green notification bar states: "You successfully created vpc-0f2bedf344eeb994f / VPC-Company-Production-Network". The main heading is "vpc-0f2bedf344eeb994f / VPC-Company-Production-Network". Below this, the "Details" tab is active, displaying various VPC configurations:

- VPC ID:** vpc-0f2bedf344eeb994f
- State:** Available
- Block Public Access:** Off
- DNS hostnames:** Disabled
- DNS resolution:** Enabled
- Tenancy:** default
- DHCP option set:** dopt-0531e230b3c3a546f
- Main network ACL:** acl-0c47d982048bc6e0d
- Default VPC:** No
- IPv4 CIDR:** 10.0.0.0/16
- IPv6 CIDR (Network border group):** -
- Network Address Usage metrics:** Disabled
- Main route table:** rtb-0d8aef61a39b69776
- Encryption control ID:** -
- Encryption control mode:** -
- Route 53 Resolver DNS Firewall rule groups:** -
- IPv6 pool:** -
- Owner ID:** 967883358429

Below the details, there are tabs for "Resource map", "CIDRs", "Flow logs", "Tags", and "Integrations". The "Resource map" tab is currently selected.

Create public subnet & Private subnet:

The screenshot shows the AWS Subnets console interface. At the top, a green notification bar states: "You have successfully created 1 subnet: subnet-0228462bb306b745f". The main heading is "Subnets (6) Info". Below this, there is a search bar and a table listing the subnets:

Name	Subnet ID	State	VPC	Block Public...	IPv4 CIDR
-	subnet-06ccbf48cd1c11f11	Available	vpc-0323b64209f368ca0 Testi...	Off	172.31.0.0/20
-	subnet-087cbf9d09a9148ef	Available	vpc-0323b64209f368ca0 Testi...	Off	172.31.64.0/20
-	subnet-01a2def073d7c6b6c	Available	vpc-0323b64209f368ca0 Testi...	Off	172.31.16.0/20
-	subnet-06e61a165a7d41235	Available	vpc-0323b64209f368ca0 Testi...	Off	172.31.80.0/20
Company-SupplyChain-Private-Subnet	subnet-0665b30531f3dd914	Available	vpc-0f2bedf344eeb994f VPC-...	Off	10.0.1.0/24
Company-Public-Subnet	subnet-0228462bb306b745f	Available	vpc-0f2bedf344eeb994f VPC-...	Off	10.0.2.0/24

Important Note: This is our goal.

The Internet gateway or IGW should be inside the public subnet. Anything that is inside the public subnet that has the IGW has a public IP that ANYONE can see and access.

Moreover, for a private subnet, a private instance, sometimes you need to download stuff from the Internet, but do not want to expose your own IP because you only have one IP, and it is private. Therefore, you need a NAT gateway.

The NAT gateway alone cannot access the Internet if placed in the private subnet; thus, the NAT gateway has to have access from the IGW routable back into NAT and back into the private instance.

Internet > IGW > NAT > Private Subnet/Instance

Analogy: Chef > Waiter > Customer


Both the public subnet & public route table have an IGW.

While both the private subnet & private route table have a NAT gateway.


In simple terms, a NAT gateway stays in the public subnet because the public subnet also has IGW or Internet access. The private subnet and its instances only take the NAT IP and its ID to use, since that is NAT's responsibility, to provide data on behalf of the private client.

Internet gateway


Initially, both public and private instances cannot connect to the Internet. So we need the Internet Gateway & Network Address Translation Gateway.




Here are the steps:



Need a route table that manages where the traffic goes:



From the public subnet, there's already a route table to the private network. But now we need a new routing table to connect to the Internet.



By default, it will connect to the private VPC IP. Now, add and connect to the Internet gateway for Internet access.

Menu VPC > Route tables > rtb-01733b670d96944b5 > Edit routes

Edit routes

Destination	Target	Status	Propagated	Route Origin
10.0.0.0/16	local	Active	No	CreateRouteTable
Q 0.0.0.0/0	Q local	-	No	CreateRoute
	Internet Gateway			
	Q igw-0e9c01c66e5fc57cf			

Buttons: Add route, Cancel, Preview, Save changes, Remove

Next, go to Public subnet and edit routable:

Menu VPC > Subnets > subnet-0228462bb306b745f > Edit route table association

Edit route table association

Subnet route table settings

Subnet ID: subnet-0228462bb306b745f

Route table ID: rtb-01733b670d96944b5 (Company-Public-RouteTable)

Routes (2)

Destination	Target
10.0.0.0/16	local
0.0.0.0/0	igw-0e9c01c66e5fc57cf

Buttons: Cancel, Save

Now, it should work.

```
1 | n8n-Instance-Docker 2 | AttackerSide-Attac... 3 | ServerSide-Attac... 4 | DefenderSide-Attac... 5 | Settings 6 | Load-balancer + |

Welcome to Ubuntu 24.04.3 LTS (GNU/Linux 6.14.0-1018-aws x86_64)

* Documentation:  https://help.ubuntu.com
* Management:    https://landscape.canonical.com
* Support:       https://ubuntu.com/pro

System information as of Mon Jan 26 07:56:51 UTC 2026

System load: 0.08      Temperature: -273.1 C
Usage of /: 25.9% of 6.71GB  Processes: 110
Memory usage: 24%      Users logged in: 0
Swap usage: 0%         IPv4 address for ens5: 10.0.2.201

Expanded Security Maintenance for Applications is not enabled.

0 updates can be applied immediately.

Enable ESM Apps to receive additional future security updates.
See https://ubuntu.com/esm or run: sudo pro status

The list of available updates is more than a week old.
To check for new updates run: sudo apt update

The programs included with the Ubuntu system are free software;
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/copyright.

Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.

To run a command as administrator (user "root"), use "sudo <command>".
See "man sudo_root" for details.

ubuntu@ip-10-0-2-201:~$
```

Now, the public subnet is public on the Internet, and the private subnet is still private.

Next, on the reverse proxy CLI (public instance), install nginx.

```
sudo apt update && sudo apt install nginx -y
```

```
sudo systemctl enable nginx
```

```
sudo systemctl start nginx
```

```
sudo systemctl status nginx
```

Private Subnet

Creating a private subnet

Create an AMI image and launch it.

Make sure:

- VPC
- No public IP, since it's a private subnet

Private-Server-key

Create new key pair

▼ Network settings

Info

VPC - required

Info

vpc-0f2bedf344eeb994f (VPC-Company-Production-Network)

10.0.0.0/16

Subnet

Info

subnet-0665b30531f3dd914

Company-SupplyChain-Private-Subnet

VPC: vpc-0f2bedf344eeb994f Owner: 967883358429 Availability Zone: us-east-1a (use1-az1)

Zone type: Availability Zone IP addresses available: 251 CIDR: 10.0.1.0/24

Auto-assign public IP

Info

Disable

Firewall (security groups)

Info

A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.

Create security group

Select existing security group

Security group name - required

Private-Server

This security group will be added to all network interfaces. The name can't be edited after the security group is created. Max length is 255 characters. Valid characters: a-z, A-Z, 0-9, spaces, and . - / ! # \$ % & ' () * + , ; : < > [\] ^ _ { | } ~

▼ Summary

Number of instances

Info

1

Software Image (AMI)

Canonical, Ubuntu, 24.04, amd64...read more

ami-0b6c6ebed2801a5cb

Virtual server type (instance type)

t3.micro

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 8 GiB

Cancel

Port and the IP range should be the same as the VPC or ONLY to the public subnet IP. In this case, it is the same as the VPC.

EC2 > Instances > Launch an instance

Private-Server

This security group will be added to all network interfaces. The name can't be edited after the security group is created. Max length is 255 characters. Valid characters: a-z, A-Z, 0-9, spaces, and ._-:/()#,@[]+=&;{}!\$*

Description - *required* [Info](#)

Private-Server

Inbound Security Group Rules

▼ Security group rule 1 (TCP, 8080, 10.0.0.0/16)

Remove

Type [Info](#)

Protocol [Info](#)

Port range [Info](#)

Source type [Info](#)

Source [Info](#)

Description - *optional* [Info](#)

Custom TCP

TCP

8080

Custom

Q Add CIDR, prefix list or security group

10.0.0.0/16 X

e.g. SSH for admin desktop

Add security group rule

Result:

As you can see, it does not have a public IP, but a private IP that can only be used within the VPC.

Instance summary for i-0bb9933e040831de1 (Private-Server) Info Updated less than a minute ago			Connect Instance
Instance ID i-0bb9933e040831de1	Public IPv4 address -	Private IPv4 addresses 10.0.2.214	
IPv6 address -	Instance state Running	Public DNS -	
Hostname type IP name: ip-10-0-2-214.ec2.internal	Private IP DNS name (IPv4 only) ip-10-0-2-214.ec2.internal		

Only the reverse proxy instance machine that is within the same VPC can communicate with this private server or app.

Connect from the public instance to the private instance

(from Public instance)

aws Search [Alt+S]

EC2 > Security Groups > sg-Oe3874035fe5a7ce8 - Load-Balancer > Edit inbound rules

Edit inbound rules [Info](#)

Inbound rules control the incoming traffic that's allowed to reach the instance.

Security group rule ID	Type Info	Protocol Info	Port range Info	Source Info
sgr-04a5ed493f18af8b8	HTTP	TCP	80	Custom
-	SSH	TCP	22	Custom

[Add rule](#)

⚠ Rules with source of 0.0.0.0/0 or ::/0 allow all IP addresses to access your instance. We recommend setting security group rules to all

Inbound rule:

- HTTP, Custom, 0.0.0.0/0
- The SSH IP range is your router's public IP. It is safer.
Example: 32.34.390.0/24 for your router's public IP

Outbound: leave it as default (0.0.0.0/0)

(from private instance)

EC2 > Security Groups > sg-Oe6ee758106ebfc38 - Private-Server > Edit inbound rules

Edit inbound rules [Info](#)

Inbound rules control the incoming traffic that's allowed to reach the instance.

Security group rule ID	Type Info	Protocol Info	Port range Info	Source Info	Description - optional Info
sgr-01ad5aba9d9523025	HTTP	TCP	80	Custom	
sgr-0cdfea142de9bb1ab	SSH	TCP	22	Custom	

[Add rule](#)

Search: sg-Oe3874035fe5a7ce8

Security Groups

- default | sg-015c62fb44416b7b7
- Load-Balancer | sg-Oe3874035fe5a7ce8
- Private-Server | sg-Oe6ee758106ebfc38

Prefix lists

- com.amazonaws.us-east-1.dynamodb | pl-02cd2c6b
- com.amazonaws.global.ipv6.cloudfront.origin-facing | pl-02d12e369a4312e03

Next, from your laptop, open Tabby and connect to the public instance:

```
PS C:\Users\User\Organized_Downloads> scp -i .\Load-Balancer-key.pem .\Private-Server-key.pem ubuntu@98.92.205.49:/home/ubuntu/
The authenticity of host '98.92.205.49 (98.92.205.49)' can't be established.
ED25519 key fingerprint is SHA256:R3HGaeQYFPuAALCan2gc0gkhH90Cdna7W0Ik90g20Ic.
This key is not known by any other names.
Are you sure you want to continue connecting (yes/no/[fingerprint])?
Warning: Permanently added '98.92.205.49' (ED25519) to the list of known hosts.
Private-Server-key.pem      100% 1678    5.9KB/s   00:00
PS C:\Users\User\Organized_Downloads>
```

(from Windows)

(from Tabby)

```
ubuntu@ip-10-0-1-252:~$ ls
ubuntu@ip-10-0-1-252:~$ who am i
ubuntu pts/0 2026-01-26 11:22 (58.97.219.104)
ubuntu@ip-10-0-1-252:~$ ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host noprefixroute
        valid_lft forever preferred_lft forever
2: ens5: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 9001 qdisc mq state UP group default qlen 1000
    link/ether 02:f6:27:c0:d2:05 brd ff:ff:ff:ff:ff:ff
    altname enp0s5
    inet 10.0.1.252/24 metric 100 brd 10.0.1.255 scope global dynamic ens5
        valid_lft 2148sec preferred_lft 2148sec
    inet6 fe80::f6:27ff:fec0:d205/64 scope link
        valid_lft forever preferred_lft forever
ubuntu@ip-10-0-1-252:~$ ls
Private-Server-key.pem
```

Next, open a terminal in a folder that contains the private-key.pem and the load-balancer.pem

Next,

```
scp -i .\load-balancer.pem private-key.pem
ubuntu@{public-IP-from-public-instance}:/home/ubuntu
```

This should upload the private-key.pem to the public instance because ONLY the public instance can communicate with the private subnet/instance because both are within the same VPC.

Inside the public instance CLI, type these commands:

```
ls
```

```
chmod 400 private-key.pem
```



```
ssh -i private-key.pem ubuntu@{private-IP-from-private-instance}
```

If you don't follow, you get these errors:

```
ubuntu@ip-10-0-1-252:~$ ls
Private-Server-key.pem
ubuntu@ip-10-0-1-252:~$ ssh ubuntu@10.0.2.37
The authenticity of host '10.0.2.37 (10.0.2.37)' can't be established.
ED25519 key fingerprint is SHA256:1M09DtC2wZnsCHge4Qczfed6S+CcQG0RrMTnSPqNCJk.
This key is not known by any other names.
Are you sure you want to continue connecting (yes/no/[fingerprint])? yes
Warning: Permanently added '10.0.2.37' (ED25519) to the list of known hosts.
ubuntu@10.0.2.37: Permission denied (publickey).
ubuntu@ip-10-0-1-252:~$ ssh -i Private-Server-key.pem ubuntu@10.0.2.37
@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@
@                WARNING: UNPROTECTED PRIVATE KEY FILE!                @
@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@@
Permissions 0664 for 'Private-Server-key.pem' are too open.
It is required that your private key files are NOT accessible by others.
This private key will be ignored.
Load key "Private-Server-key.pem": bad permissions
ubuntu@10.0.2.37: Permission denied (publickey).
```

After you enter the private instance CLI, you cannot have access to the internet; thus you cannot download or update the system. That's why we need to configure NAT gateway ontop of the Internet gateway.

Without the NAT gateway, you will experience this:

```
[1] 1225
Reading package lists... Done
Building dependency tree... Done
Reading state information... Done
Calculating upgrade... Done
0 upgraded, 0 newly installed, 0 to remove and 0 not upgraded.
Ign:1 http://security.ubuntu.com/ubuntu noble-security InRelease
Ign:2 http://us-east-1.ec2.archive.ubuntu.com/ubuntu noble InRelease
Ign:3 http://us-east-1.ec2.archive.ubuntu.com/ubuntu noble-updates InRelease
Ign:4 http://us-east-1.ec2.archive.ubuntu.com/ubuntu noble-backports InRelease
Ign:1 http://security.ubuntu.com/ubuntu noble-security InRelease
Ign:2 http://us-east-1.ec2.archive.ubuntu.com/ubuntu noble InRelease
Ign:3 http://us-east-1.ec2.archive.ubuntu.com/ubuntu noble-updates InRelease
Ign:4 http://us-east-1.ec2.archive.ubuntu.com/ubuntu noble-backports InRelease
Ign:1 http://security.ubuntu.com/ubuntu noble-security InRelease
Ign:2 http://us-east-1.ec2.archive.ubuntu.com/ubuntu noble InRelease
Ign:3 http://us-east-1.ec2.archive.ubuntu.com/ubuntu noble-updates InRelease
Ign:4 http://us-east-1.ec2.archive.ubuntu.com/ubuntu noble-backports InRelease
Err:1 http://security.ubuntu.com/ubuntu noble-security InRelease
  Cannot initiate the connection to security.ubuntu.com:80 (2620:2d:4002::1:103). - connect (101: Network is unreachable) Cannot initiate the connection to security.ubuntu.com:80 (2620:2d:4002::1:103). - con
(101: Network is unreachable) Cannot initiate the connection to security.ubuntu.com:80 (2620:2d:4002::1:101). - connect (101: Network is unreachable) Cannot initiate the connection to security.ubun
m:80 (2620:2d:4002::1:102). - connect (101: Network is unreachable) Cannot initiate the connection to security.ubuntu.com:80 (2620:2d:4002::1:101). - connect (101: Network is unreachable) Cannot initia
e connection to security.ubuntu.com:80 (2620:2d:4002::1:101). - connect (101: Network is unreachable) Cannot initiate the connection to security.ubuntu.com:80 (2620:2d:4002::1:101). - connect (101: Netwo
k is unreachable) Cannot initiate the connection to security.ubuntu.com:80 (2620:2d:4002::1:101). - connect (101: Network is unreachable) Cannot initiate the connection to security.ubuntu.com:80 (2620:2d:4002
:1:101). - connect (101: Network is unreachable) Cannot initiate the connection to security.ubuntu.com:80 (2620:2d:4002::1:101). - connect (101: Network is unreachable) Cannot initiate the connection to se
curity.ubuntu.com:80 (2620:2d:4002::1:101). - connect (101: Network is unreachable) Cannot initiate the connection to security.ubuntu.com:80 (2620:2d:4002::1:101). - connect (101: Network is unreachabl
ed out could not connect to security.ubuntu.com:80 (91.189.91.83), connection timed out could not connect to security.ubuntu.com:80 (185.125.190.81), connection timed out could not connect to security.ubunt
(91.189.92.24), connection timed out could not connect to security.ubuntu.com:80 (185.125.190.83), connection timed out could not connect to security.ubuntu.com:80 (91.189.92.22), connection timed ou
t could not connect to security.ubuntu.com:80 (91.189.92.23), connection timed out could not connect to security.ubuntu.com:80 (91.189.91.82), connection timed out
Err:2 http://us-east-1.ec2.archive.ubuntu.com/ubuntu noble InRelease
  Cannot initiate the connection to us-east-1.ec2.archive.ubuntu.com:80 (2680:1f18:5c55:4c01:32a9:41b2:cfa3:904a). - connect (101: Network is unreachable) Cannot initiate the connection to us-east-1.ec2.arch
ive.ubuntu.com:80 (2680:1f18:5c55:4c01:32a9:41b2:cfa3:904a). - connect (101: Network is unreachable) Cannot initiate the connection to us-east-1.ec2.archive.ubuntu.com:80 (2680:1f18:5c55:4c01:b55:f4cf:830eb
81a). - connect (101: Network is unreachable) Cannot initiate the connection to us-east-1.ec2.archive.ubuntu.com:80 (2680:1f18:5c55:4c00:7447:7a97:f860:d02). - connect (101: Network is unreachable) Cannot i
nitiate the connection to us-east-1.ec2.archive.ubuntu.com:80 (2680:1f18:5c55:4c00:7637:a2bc:ccef:30d5). - connect (101: Network is unreachable) cannot initiate the connection to us-east-1.ec2.archive.ubunt
.com:80 (2680:1f18:5c55:4c04:bffe:122c:b055:e084). - connect (101: Network is unreachable) Cannot initiate the connection to us-east-1.ec2.archive.ubuntu.com:80 (2680:1f18:5c55:4c05:17c8:ad29:43bf:e048). - c
onnect (101: Network is unreachable) Cannot initiate the connection to us-east-1.ec2.archive.ubuntu.com:80 (2680:1f18:5c55:4c01:eddc:fdfa:1470:af0c). - connect (101: Network is unreachable) Cannot initiate t
he connection to us-east-1.ec2.archive.ubuntu.com:80 (2680:1f18:5c55:4c02:7669:c120:50a2:9af4). - connect (101: Network is unreachable) Cannot initiate the connection to us-east-1.ec2.archive.ubuntu.com:80 (
2680:1f18:5c55:4c03:ed99:571ff:f041:fac8). - connect (101: Network is unreachable) could not connect to us-east-1.ec2.archive.ubuntu.com:80 (34.201.250.36), connection timed out could not connect to us-east-1
.ec2.archive.ubuntu.com:80 (3.47.126.146), connection timed out could not connect to us-east-1.ec2.archive.ubuntu.com:80 (34.237.137.22), connection timed out could not connect to us-east-1.ec2.archive.ubunt
om:80 (52.91.41.124), connection timed out could not connect to us-east-1.ec2.archive.ubuntu.com:80 (54.465.17.230), connection timed out could not connect to us-east-1.ec2.archive.ubuntu.com:80 (18.232.15
0.247), connection timed out could not connect to us-east-1.ec2.archive.ubuntu.com:80 (54.144.148.213), connection timed out could not connect to us-east-1.ec2.archive.ubuntu.com:80 (52.207.133.243), conne
ction timed out could not connect to us-east-1.ec2.archive.ubuntu.com:80 (54.87.19.168), connection timed out could not connect to us-east-1.ec2.archive.ubuntu.com:80 (3.209.10.109), connection timed out
Err:3 http://us-east-1.ec2.archive.ubuntu.com/ubuntu noble-updates InRelease
```

NAT Gateway Configuration

Set up NAT Gateway: [here](#)

- Create NAT Gateway
- In the Private Subnet, & routable: add the NAT gateway IP and its ID
- Just watch the video or refer to the Important Note at the top of this documentation.

Then, restart the private instance and update again. It should work and have access to the internet.

On the private instance:

Next, `sudo apt install apache2 -y`

(Yes, the public instance uses nginx and the private uses Apache. It is normal.)

Then, configure the private instance and its html files.

```
sudo apt update
```

```
sudo apt install -y apache2
```

```
echo "<h1>Project Success: I am the Private Server</h1>" | sudo tee  
/var/www/html/index.html
```

Back to the public instance (connect the public instance to open/display publicly):

```
sudo nano /etc/nginx/sites-available/default
```

Change the original to this (or ignore the comments):

```
server {
```

```
    listen 80 default_server;
```

```
    listen [::]:80 default_server;
```

```
    root /var/www/html;
```

```
    index index.html index.htm;
```

```
server_name _;
```

1. THE REVERSE PROXY LOGIC

```
location / {
```

```
# Replace 10.0.2.XXX with your Private Instance's ACTUAL Private IP
```

```
proxy_pass http://10.0.2.XXX;
```

```
# Standard Proxy Headers
```

```
proxy_set_header Host $host;
```

```
proxy_set_header X-Real-IP $remote_addr;
```

```
proxy_set_header X-Forwarded-For $proxy_add_x_forwarded_for;
```

2. THE "FAIL" LOGIC

```
# This tells Nginx: if the private server gives an error, use our custom page
```

```
proxy_intercept_errors on;
```

```
}
```

3. CUSTOM ERROR MESSAGE

```
# If the private server is down (502) or timed out (504), show this page
```

```
error_page 404 500 502 503 504 /custom_error.html;
```

```
location = /custom_error.html {
```

```
root /var/www/html;
```

```
internal;
```

```
}
```

```
}
```

Save and exit.

Create an error-handling file:

```
sudo nano /var/www/html/custom_error.html
```

Add this:

```
<html>
```

```
<body style="text-align: center; font-family: sans-serif; padding-top: 50px;">
```

```
<h1>⚠️ Something is Wrong at the Public Instance</h1>
```

```
<p>I am the Reverse Proxy. I am working, but I cannot reach the Private Web Server.  
Check /var/www/html/</p>
```

```
</body>
```


```
</html>
```

Save and exit.

Check typos: `sudo nginx -t`

Restart: `sudo systemctl restart nginx`

Lastly, get the public IP from the public instance and enter it in the search browser. You should see the text that says, “Project Success: I am the Private Server”



Project Success: I am the Private Server

Note: DO NOT OPEN THE WEBSITE USING “open address”. Instead, copy the blue-highlighted IP or copy it. Else the website won’t open or work.

i-03035f16a3cd073d6 (Load-Balancer)

Details

Status and alarms

Monitoring

Security

Networking

Storage

▼ Instance summary

Info

Instance ID

 i-03035f16a3cd073d6

Public IPv4 address

 3.239.236.34 | [open address](#) 

Verdicts:

- The IP is a public IP
 - Acts as a reverse proxy
- The text is from the private instance/subnet
 - Uses a NAT gateway on top of the Internet gateway
 - Can access the internet, but the Internet cannot access back or is unable to see

END