This document is intended for use of NDML KRA registered intermediaries for the purpose of using New Bulk Image Upload Utility.

NSDL Database Management Limited

NDML – KRA

Procedure to successfully download and integrate Bulk Image Upload Utility.

Below is the stepwise procedure which user need to follow for downloading and integration of Bulk Image Upload Utility.

Step 1. Go to https://kra.ndml.in/kra-web/



Step 2. Click on Download module



Step 3. Once click on Download option, system will display one window where user can download Bulk image upload utility.



Step 4. Once user click on Bulk Image Upload link, a ZIP file gets downloaded on users' system.



Step 5. Once the file has been successfully downloaded in system. User need to copy and paste this file in C drive.

If user is saving this file in C drive, he doesn't need to make any changes in properties file

Note: User can also paste this file on E and D drive but if user has to make some change in properties file (which will be discussed and explained in below document)

Procedure for using C drive

- Copy ***(Bulk_Image_Upload_Utility_Pan_Based)*** file



- Create a folder in **C drive (Note: Recommended not to create folder for MI).** Kindly Extract file in C drive directly.



- Paste the copied file ***(Bulk_Image_Upload_Utility_Pan_Based)*** in that folder



- User no need to right click on the file >> **7-Zip** >> **Extract Here**



- When user click on **Extract Here** option, System will display new window where user has to enter Password and click on **OK** action button



- After entering Password user has to click on **OK** action button **(Password : NDML@1234)**



- Once user click on **OK** action button, system will validate password and extract file in targeted folder. User can open **ndml** folder and see extracted file.



- For image uploading, user need to upload image in below folder ***ndml >> kra >> filesystem >> autoupload >> images >> FILES***



Procedure for using D or E drive

- Copy ***(Bulk_Image_Upload_Utility_Pan_Based)*** file



- Paste the utility file in D drive.



- User no need to right click on the file >> **7-Zip** >> **Extract Here**



- When user click on **Extract Here** option, System will display new window where user has to enter Password and click on **OK** action button



- After entering Password user has to click on **OK** action button **(Password : NDML@1234)**



- Once user click on **OK** action button, system will validate password and extract file in targeted folder. User can open **ndml** folder and see extracted file.



- For image uploading, user need to upload image in below folder ***ndml >> kra >> filesystem >> autoupload >> images >> FILES***



Since user has extracted file in D or E drive, he has to make some changes in properties file. Procedure regarding changes is explained below.

- User has to go in ***ndml >> kra >> kra-properties***



- User has to open **kra-autoupload.properties** file



- Now in this file user has to change file path location from **C drive to D or E** drive. And save the file.

; #ENTER ROOT DIRECTORY FOR AUTO UPLOAD COMPLETED FILES
; ROOT_DIR_FOR_AUTO_UPLOAD_COMPLETED_FILES =
C:\\ndml\\kra\\filesystem\\autoupload\\indexfile\\COMPLETED\\

; #ENTER ROOT DIRECTORY FOR AUTO UPLOAD TEMP FILES
; ROOT_DIR_FOR_AUTO_UPLOAD_TEMP_FILES =
C:\\ndml\\kra\\filesystem\\autoupload\\indexfile\\TEMP\\

; #ENTER ROOT DIRECTORY FOR AUTO UPLOAD IMAGE FILES
; ROOT_DIR_FOR_AUTO_UPLOAD_IMAGE_FILES =
C:\\ndml\\kra\\filesystem\\autoupload\\images\\FILES\\

; #ENTER ROOT DIRECTORY FOR AUTO UPLOAD IMAGE COMPLETED FILES
; ROOT_DIR_FOR_AUTO_UPLOAD_IMAGE_FILES_COMPLETED =
C:\\ndml\\kra\\filesystem\\autoupload\\images\\COMPLETED\\

; #ROOT DIR FOR AUTO UPLOAD LOGS FILES
; ROOT_DIR_FOR_AUTO_UPLOAD_LOGS_FILES =
C:\\ndml\\kra\\filesystem\\autoupload\\indexfile\\LOGS\\
End --- Commented on 19-12-2016 for Bug-6207

```
*kra-autoupload.properties - Notepad
File  Edit  Format  View  Help

# Start --- Commented on 19-12-2016 for Bug-6207
; #ENTER ROOT DIRECTORY FOR AUTO UPLOAD COMPLETED FILES
; ROOT_DIR_FOR_AUTO_UPLOAD_COMPLETED_FILES = D:\\ndml\\kra\\filesystem\\autoupload\\indexfile\\COMPLETED\\

; #ENTER ROOT DIRECTORY FOR AUTO UPLOAD TEMP FILES
; ROOT_DIR_FOR_AUTO_UPLOAD_TEMP_FILES = D:\\ndml\\kra\\filesystem\\autoupload\\indexfile\\TEMP\\

; #ENTER ROOT DIRECTORY FOR AUTO UPLOAD IMAGE FILES
; ROOT_DIR_FOR_AUTO_UPLOAD_IMAGE_FILES = D:\\ndml\\kra\\filesystem\\autoupload\\images\\FILES\\

; #ENTER ROOT DIRECTORY FOR AUTO UPLOAD IMAGE COMPLETED FILES
; ROOT_DIR_FOR_AUTO_UPLOAD_IMAGE_FILES_COMPLETED = D:\\ndml\\kra\\filesystem\\autoupload\\images\\COMPLETED\\

; #ROOT DIR FOR AUTO UPLOAD LOGS FILES
; ROOT_DIR_FOR_AUTO_UPLOAD_LOGS_FILES = D:\\ndml\\kra\\filesystem\\autoupload\\indexfile\\LOGS\\
# End --- Commented on 19-12-2016 for Bug-6207

# Start --- Added on 19-12-2016 for Bug-6207
#ENTER ROOT DIRECTORY FOR AUTO UPLOAD COMPLETED FILES
ROOT_DIR_FOR_AUTO_UPLOAD_COMPLETED_FILES = \\ndml\\kra\\filesystem\\autoupload\\indexfile\\COMPLETED\\
```

Step 6. Selection of mode

There are two modes available for bulk image upload;

1. PAN based mode (by default activated)
2. Ack based mode

User if wanted to activate Ack based mode he has to follow below procedure;

To activate Ack based mode, user has to make changes in property file.

- User has to go in ***ndml >> kra >> kra-properties***



- Open kra-properties file



- User has to comment out **Mode = ACK_BASED** and comment **Mode = PAN_BASED**

```
##############################################################################
#                                KRA AUTO UPLOAD
#
#                                2012,All Rights Reserved.
##############################################################################

#USERNAME OF THE USER
USERNAME = P0077

# Commented on 19-12-2016 for Bug-6207
; #ROOT DIRECTORY FOR AUTO UPLOAD FILES FOR POP
; ROOT_DIR_FOR_AUTO_UPLOAD_FILES = C:\\ndml\\kra\\filesystem\\autoupload\\indexfile\\FILES\\KYC\\

# Added on 19-12-2016 for Bug-6207
#ROOT DIRECTORY FOR AUTO UPLOAD FILES FOR POP
ROOT_DIR_FOR_AUTO_UPLOAD_FILES = \\ndml\\kra\\filesystem\\autoupload\\indexfile\\FILES\\KYC\\

#FOLDER NAME OF KYC DOCUMENTS.DO NOT ADD FILE SEPARATOR
FOLDER_NAME_OF_KYC_DOCS = KYC

#FOLDER NAME OF INSURANCE DOCUMENTS.DO NOT ADD FILE SEPARATOR
FOLDER_NAME_OF_INSURANCE_DOCS = INSURANCE
MAX_PAN = 25
#MODE = PAN_BASED
MODE = ACK_BASED

FILE_UPLOAD_URL = https://kra.ndml.in/kra-web/AutoUploadServlet
FILE_UPLOAD_URL_PAN_BASED = https://kra.ndml.in/kra-web/AutoUploadPanBasedServlet
```

Step 7. Upload of Document

Depending upon selection of mode user has to upload document

1. PAN based mode (by default activated)

   If user is using PAN based mode for uploading document, he has to upload PDF file. File name should be that particular person PAN number only for example – AQHCP8918W.pdf



2. Ack based mode

   If user is using Ack based mode for uploading document, he has to upload PDF and other jpeg or png document with index file.

   Steps are as follows

   - Upload documents in ***ndml >> kra >> filesystem >> autoupload >> images >> files***



- Upload index file in ***ndml >> kra >> filesystem >> autoupload >> indexfile >> Files >> KYC >> KYC***



- Index file should be as per desired format only.

  Format for index file is as below;

  Acknowledgement number ^ serial number ^ 8 (document format number) ^ file name

  Note: Document format number,
  - For PDF only **8** should be used
  - For Signature file **3** should be used **(doc format jpeg/png)**
  - For Photo file **4** should be used **(doc format jpeg/png)**

  Examples;
  - 2141148708^1^8^KIOPN4714A.pdf
  - 2141148708^2^3^Sig.png
  - 2141148708^3^4^photo.png

Step 8. Run Batch file

After uploading of images user has to run Batch file, procedure for running batch file is as follows;

- For running batch file user has to go to ***ndml >> bin >> StandAloneUploader_2***



- User has to double click on **StandAloneUploader_2** batch file.

  Once user double click on batch file system will open one window where user has to input his login credentials



- User has to entered below details;
  - MI User ID
  - MI Password
  - MI ID
  - Select MI radio button
  - Choose one option from File's for KRA or File's For OKRA

  Once user has entered all the details user has to click on **OK** action button

- As user click on **OK** action button system verify credentials and run batch file, if user has inputted wrong password or Ids then system will show **authentication error** and batch file will not run.



For any Information and queries please contact customer care center @ 022 4914 2600/01/02/04/05/06 or email at Info.kra@nsdl.co.in

For any Escalation you may contact Mr. Pratik Chavan.

Landline Number – 022 2499 4945

Email ID - PratikC@nsdl.co.in