

Router Initial configuration

```
ROUTER(config)#  
ROUTER(config)#interface ethernet 0/0  
ROUTER(config-if)#ip address 50.0.0.1 255.0.0.0  
ROUTER(config-if)#no shutdown  
ROUTER(config-if)#exit  
ROUTER(config)#exit  
ROUTER#  
*Aug 17 14:14:46.178: %SYS-5-CONFIG_I: Configured from console by console  
ROUTER#show ip interface brief  
Interface                IP-Address      OK? Method Status      Prot  
GigabitEthernet0/0/0/0    50.0.0.1        YES manual up          up  
GigabitEthernet0/0/0/1    unassigned      YES TFTP  down        down  
GigabitEthernet0/0/0/2    unassigned      YES TFTP  down        down  
GigabitEthernet0/0/0/3    unassigned      YES TFTP  down        down  
ROUTER#
```

```
ROUTER#configure terminal  
Enter configuration commands, one per line. End with CNTL/Z.  
ROUTER(config)#username mari password muthu  
ROUTER(config)#line console 0  
ROUTER(config-line)#password testmari  
ROUTER(config-line)#login local  
ROUTER(config-line)#exit  
ROUTER(config)#exit  
ROUTER#ex  
*Aug 17 14:17:00.519: %SYS-5-CONFIG_I: Configured from console by console  
ROUTER#exit
```

```
ROUTER#configure terminal  
Enter configuration commands, one per line. End with CNTL/Z.  
ROUTER(config)#username mari password muthu  
ROUTER(config)#line console 0  
ROUTER(config-line)#password testmari  
ROUTER(config-line)#login local  
ROUTER(config-line)#exit  
ROUTER(config)#exit  
ROUTER#ex  
*Aug 17 14:17:00.519: %SYS-5-CONFIG_I: Configured from console by console  
ROUTER#exit
```

```
ROUTER(config)#line vty 0 4
ROUTER(config-line)#transport input telnet
ROUTER(config-line)#password marimuthu
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)#
```

Enable Telnet



