


Search Labs	
☐ ☐ ☐ ☐ ☐ ☐ ☐ ☐ ☐ ☐	
..	
☐ 1- LAB ACL.unl	30 Aug 2026 05:59
☐ 4-IPV6.unl	19 Aug 2026 22:28
☒ 2-LAB NAT.unl	+ Move to Rename Clone Delete
☐ 3-LAB VPN.unl	04 Sep 2025 09:25

Lab Preview



- Lab Name : 2-LAB NAT
- Author : 1
- Version : 1
- Lab ID : 6cfd89c0-011c-43ab-8ac4-0c3f6c243eba
- Description :

What is NAT?
Network Address Translation (NAT) is a technique used by routers to let **multiple devices on a private local network** share a **single public IP address** when communicating with the internet.

Main Types of NAT:


Static NAT: Creates a permanent, one-to-one mapping between one private IP and one public IP.

Dynamic NAT: Maps a private IP to a public IP chosen from a shared pool of available public addresses.


Port Address Translation (PAT): Allows many private IPs to share a single public IP address by assigning unique port numbers to each connection.

**CCNA CORE
WAN LAB**
Title: NAT with WAN
By Meganadhan M A

Main Types of NAT:



Example Image:



Head Office (HO) Router configuration

```
HO-EDGE#
HO-EDGE#sh ip int br
Interface IP-Address OK? Method Status Protocol
Ethernet0/0 unassigned YES TFTP up
Ethernet0/1 unassigned YES TFTP up
Ethernet0/2 unassigned YES TFTP down
Ethernet0/3 unassigned YES TFTP down
HO-EDGE#config t
Enter configuration commands, one per line. End with Ctrl-Z to quit.
HO-EDGE(config)#int e0/0
HO-EDGE(config-if)#ip add 10.0.0.1 255.0.0.0
HO-EDGE(config-if)#no sh
HO-EDGE(config-if)#ex
HO-EDGE(config)#int e0/1
HO-EDGE(config-if)#ip add 20.0.0.1 255.0.0.0
HO-EDGE(config-if)#no sh
HO-EDGE(config-if)#ex
```

Pic.1

```
HO-EDGE(config)#
HO-EDGE(config)#ip route 0.0.0.0 0.0.0.0 20.0.0.2
HO-EDGE(config)#
```

Default route assigning, Pic.2

```
HO-EDGE(config)#int e0/0
HO-EDGE(config-if)#ip nat inside
HO-EDGE(config-if)#ex
HO-EDGE(config)#
*Sep 18 10:10:14.157: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVI0, changed state to up
HO-EDGE(config)#int e0/1
HO-EDGE(config-if)#ip nat outside
HO-EDGE(config-if)#ex
HO-EDGE(config)#
HO-EDGE(config)#access-list 10 permit 10.0.0.0 0.255.255.255
HO-EDGE(config)#ip nat inside source list 10 int e0/1 overload
HO-EDGE(config)#
HO-EDGE(config)#
```

Head Office (HO) Router configuration

NAT ting configuration of the local private network to the public IP


Pic. 4


Head Office (HO) Router configuration

Activating the DHCP pool for obtaining the IP address for the client machine automatically


Pic. 3

```
HO-EDGE((config)#
HO-EDGE(config)#ip dhcp pool lan
HO-EDGE(dhcp-config)#network 10.0.0.0 255.0.0.0
HO-EDGE(dhcp-config)#default-router 10.0.0.1
HO-EDGE(dhcp-config)#dns-server 8.8.8.8
HO-EDGE(dhcp-config)#ex
HO-EDGE(config)#
HO-EDGE(config)#do sh ip int br
Interface IP-Address OK? Method Status Protocol
Ethernet0/0 10.0.0.1 YES manual up up
Ethernet0/1 20.0.0.1 YES manual up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down
```





Automatically assigned the IP address by the DHCP Server



OUTPUT – I on Win1



[Advanced search](#)


Google Search

I'm Feeling Lucky


Google offered in: [हिन्दी](#) [ಕನ್ನಡ](#) [മലയാളം](#) [ਪੰਜਾਬੀ](#) [ગુજરાતી](#) [தமிழ்](#) [मराठी](#) [සිංහල](#) [বাংলা](#)

```
HO-EDGE(config)#
HO-EDGE(config)#ip route 0.0.0.0 0.0.0.0 20.0.0.2
HO-EDGE(config)#
```

Once the route is added on the HO router, the default route 0.0.0.0 (IP) 0.0.0.0 (Subnet mask) for private IP and public IP is set to the gateway, meaning we can automatically get internet access from the ISP.



OUTPUT – II on Win1



```
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.
C:\Documents and Settings\user>cd \
C:\>ncpa.cpl
C:\>
```

Network Connections

File Edit View Favorites Tools Advanced Help

Back Forward Stop Search Folders

Address Network Connections

LAN or High-Speed Internet

Local Area Connection

Local Area Connection Status

General Support

Connection status

Address Type:	Assigned by DHCP
IP Address:	10.0.0.3
Subnet Mask:	255.0.0.0
Default Gateway:	10.0.0.1


Details...


Windows did not detect problems with this connection. If you cannot connect, click Repair.

Repair

Close

Automatically assigned the IP address by the DHCP Server





OUTPUT – I on Win2




[Advanced search](#)

Google offered in: [हिन्दी](#) [ಕನ್ನಡ](#) [മലയാളം](#) [பேர்த்](#) [தமிழ்](#) [ગુજરાતી](#) [සිංහල](#) [বাংলা](#)

```
HO-EDGE(config)#  
HO-EDGE(config)#ip route 0.0.0.0 0.0.0.0 20.0.0.2  
HO-EDGE(config)#
```

Once the route is added on the HO router, the default route 0.0.0.0 (IP) 0.0.0.0 (Subnet mask) for private IP and public IP is set to the gateway, meaning we can automatically get internet access from the ISP.



OUTPUT – II on Win2

PNETLab | TopologyTerminalnat

labs.surennetwork.com/store/public/admin/labs/terminal?terminals=eyJ0YWJzljpbeyJuYW11IjoieSE8tRURHRSlInVybCI6Ii9odG1sNS8jL2NsaWVudC9NekUwTmpteU1ESTRBR01BYlhsemNXdz0/dG9rZW49MjQ2MjIjIGQIGkY0Q0M1NTE...

Incognito (2)Finish update

HO-EDGEWin1Win2

FileEditViewHistoryBookmarksToolsHelp

FacebookRainmail Intranet Page

14.139.191.50

Search

☆📄⬇️🏠💬☰



NCCCR

राष्ट्रीय तटीय अनुसंधान केन्द्र

पृथ्वी विज्ञान मंत्रालय, भारत सरकार

NATIONAL CENTRE FOR COASTAL RESEARCH

MINISTRY OF EARTH SCIENCES, GOVERNMENT OF INDIA

Welcome to the Rainmails Intranet Page.
If you want to publish content for your intranet, Edit this page. Copy your files into the html directory.

User Links

..: Rainmail Intranet Login ..

Account: @nccr.gov.in

Password:

Login

Get User Profile from Email address

Set Mail forwarding/auto responder rules

Download Links

Java for Windows

Rainmail Client for Windows

Java for Linux

Rainmail Client for Linux

Outlook Calendar Client

Chat client

Hylafax client

Rainmail VPN Installer

VNCviewer for Windows



System / Support Links

Web Administrator Page

Rainmail Server Administrator Guide

Rainmail Server Users Guide

Rainmail Intranet Support Page

Carizen Home Page

Blackberry / Mobile Clients

Blackberry (OS: 4.7+)

Blackberry (OS: 4.5, 4.6)

Android Smart Phones

Windows Mobile

Symbian (Nokia) Phones

Firefox automatically sends some data to Mozilla so that we can improve your experience.

Choose What I Share

Start

C:\WINDOWS\system32...Network ConnectionsRainmail Intranet Pa...

3:27 AM


35°C Mostly sunny

Search



03:58 PM 18-09-2026

OUTPUT – III on Win2



OUTPUT – IV on Win2

Please wait while the page loads

PNETLab | TopologyTerminalnat

labs.surennetwork.com/store/public/admin/labs/terminal?terminals=eyJ0YWJzljpbeyJuYW1lIjoieSE8tRURHRSlInVybCI6Ii9odG1sNS8jL2NsaWVudC9NekUwTmpteU1ESTRBR01BYlhsemNXdz0/dG9rZW49MjQ2MjIjIGQIGkY0Q0M1NTE1...

Incognito (2)Finish update

HO-EDGEWin1Win2

FileEditViewHistoryBookmarksToolsHelp

FacebookCarbonio Authenticationhttps://14.139.191.49/webui/ Rainmail Intranet Page

14.139.191.50Search



NCCCR

राष्ट्रीय तटीय अनुसंधान केन्द्र

पृथ्वी विज्ञान मंत्रालय, भारत सरकार

NATIONAL CENTRE FOR COASTAL RESEARCH

MINISTRY OF EARTH SCIENCES, GOVERNMENT OF INDIA

Welcome to the Rainmails Intranet Page.
If you want to publish content for your intranet, Edit this page. Copy your files into the html directory.

User Links

..: Rainmail Intranet Login ..

Account: @nccr.gov.in

Password:

Login

Get User Profile from Email address

Set Mail forwarding/auto responder rules

Download Links

Java for Windows

Rainmail Client for Windows

Java for Linux

Rainmail Client for Linux

Outlook Calendar Client

Chat client

Hylafax client

Rainmail VPN Installer

VNCviewer for Windows



System / Support Links

Web Administrator Page

Rainmail Server Administrator Guide

Rainmail Server Users Guide

Rainmail Intranet Support Page

Carizen Home Page

Blackberry / Mobile Clients

Blackberry (OS: 4.7+)

Blackberry (OS: 4.5, 4.6)

Android Smart Phones

Windows Mobile

Symbian (Nokia) Phones

Firefox automatically sends some data to Mozilla so that we can improve your experience.

Choose What I Share

Start

C:\WINDOWS\system32...Network ConnectionsRainmail Intranet Pa...

3:29 AM

35°C Mostly sunny

Search



04:00 PM 18-09-2026

```
HO-EDGE x Win1 x Win2 x DC-EDGE x VPC1 x VPC2 x
C:\WINDOWS\system32\cmd.exe - ping 30.0.0.12
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>cd \

C:\>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 10.0.0.3
    Subnet Mask . . . . . : 255.0.0.0
    Default Gateway . . . . . : 10.0.0.1

C:\>ping 20.0.0.2

Pinging 20.0.0.2 with 32 bytes of data:

Reply from 20.0.0.2: bytes=32 time=2ms TTL=254
Reply from 20.0.0.2: bytes=32 time=1ms TTL=254
Reply from 20.0.0.2: bytes=32 time=1ms TTL=254
Reply from 20.0.0.2: bytes=32 time=1ms TTL=254

Ping statistics for 20.0.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 2ms, Average = 1ms

C:\>ping 30.0.0.1

Pinging 30.0.0.1 with 32 bytes of data:

Reply from 30.0.0.1: bytes=32 time=1ms TTL=254
Reply from 30.0.0.1: bytes=32 time=1ms TTL=254
Reply from 30.0.0.1: bytes=32 time=1ms TTL=254
Reply from 30.0.0.1: bytes=32 time=2ms TTL=254

Ping statistics for 30.0.0.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 2ms, Average = 1ms

C:\>ping 30.0.0.2

Pinging 30.0.0.2 with 32 bytes of data:

Reply from 30.0.0.2: bytes=32 time=2ms TTL=253
Reply from 30.0.0.2: bytes=32 time=1ms TTL=253
Reply from 30.0.0.2: bytes=32 time=1ms TTL=253
Reply from 30.0.0.2: bytes=32 time=2ms TTL=253

Ping statistics for 30.0.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 2ms, Average = 1ms

C:\>ping 30.0.0.10

Pinging 30.0.0.10 with 32 bytes of data:

Reply from 30.0.0.10: bytes=32 time=5ms TTL=61
Reply from 30.0.0.10: bytes=32 time=3ms TTL=61
Reply from 30.0.0.10: bytes=32 time=3ms TTL=61
Reply from 30.0.0.10: bytes=32 time=4ms TTL=61

Ping statistics for 30.0.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 3ms, Maximum = 5ms, Average = 3ms
```

```
HO-EDGE x Win1 x Win2 x DC-EDGE x VPC1 x VPC2 x
C:\WINDOWS\system32\cmd.exe - ping 30.0.0.12
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 1ms, Maximum = 2ms, Average = 1ms

C:\>ping 30.0.0.1

Pinging 30.0.0.1 with 32 bytes of data:

Reply from 30.0.0.1: bytes=32 time=1ms TTL=254
Reply from 30.0.0.1: bytes=32 time=1ms TTL=254
Reply from 30.0.0.1: bytes=32 time=1ms TTL=254
Reply from 30.0.0.1: bytes=32 time=2ms TTL=254

Ping statistics for 30.0.0.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 2ms, Average = 1ms

C:\>ping 30.0.0.2

Pinging 30.0.0.2 with 32 bytes of data:

Reply from 30.0.0.2: bytes=32 time=2ms TTL=253
Reply from 30.0.0.2: bytes=32 time=1ms TTL=253
Reply from 30.0.0.2: bytes=32 time=1ms TTL=253
Reply from 30.0.0.2: bytes=32 time=2ms TTL=253

Ping statistics for 30.0.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 2ms, Average = 1ms

C:\>ping 30.0.0.10

Pinging 30.0.0.10 with 32 bytes of data:

Reply from 30.0.0.10: bytes=32 time=5ms TTL=61
Reply from 30.0.0.10: bytes=32 time=3ms TTL=61
Reply from 30.0.0.10: bytes=32 time=3ms TTL=61
Reply from 30.0.0.10: bytes=32 time=4ms TTL=61

Ping statistics for 30.0.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 3ms, Maximum = 5ms, Average = 3ms

C:\>ping 30.0.0.11

Pinging 30.0.0.11 with 32 bytes of data:

Reply from 30.0.0.11: bytes=32 time=5ms TTL=61
Reply from 30.0.0.11: bytes=32 time=3ms TTL=61
Reply from 30.0.0.11: bytes=32 time=3ms TTL=61
Reply from 30.0.0.11: bytes=32 time=3ms TTL=61

Ping statistics for 30.0.0.11:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 3ms, Maximum = 5ms, Average = 3ms
```

Reachabilities

PNETLab | Topology x Terminal x nat x

labs.surennetwork.com/store/public/admin/labs/terminal?terminals=eyJ0YWJzljpbeyJuYW11ljo

HO-EDGE x Win1 x Win2 x DC-EDGE x VPC1 x VPC2 x

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC1>
VPC1> ip 192.168.1.10 255.255.255.0 192.168.1.1
Checking for duplicate address...
VPC1 : 192.168.1.10 255.255.255.0 gateway 192.168.1.1

VPC1> sh ip
NAME      : VPC1[1]
IP/MASK    : 192.168.1.10/24
GATEWAY    : 192.168.1.1
DNS        :
MAC        : 00:50:79:66:68:cc
LPORT     : 20000
RHOST:PORT : 127.0.0.1:30000
MTU        : 1500

VPC1> █
```

Assigned the IP address to VPC1

34°C Mostly sunny Search

PNETLab | Topology x Terminal x nat x

labs.surennetwork.com/store/public/admin/labs/terminal?terminals=eyJ0YWJzljpbeyJuYW11ljo

HO-EDGE x Win1 x Win2 x DC-EDGE x VPC1 x VPC2 x

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC2>
VPC2> ip 192.168.1.20/24 192.168.1.1
Checking for duplicate address...
VPC2 : 192.168.1.20 255.255.255.0 gateway 192.168.1.1

VPC2> sh ip
NAME      : VPC2[1]
IP/MASK    : 192.168.1.20/24
GATEWAY    : 192.168.1.1
DNS        :
MAC        : 00:50:79:66:68:cd
LPORT     : 20000
RHOST:PORT : 127.0.0.1:30000
MTU        : 1500

VPC2> █
```

Assigned the IP address to VPC2

34°C Mostly sunny Search

```
DC-EDGE#sh ip int br
Interface                IP-Address      OK? Method Status
Ethernet0/0              unassigned      YES TFTP  up
Ethernet0/1              unassigned      YES TFTP  up
Ethernet0/2              unassigned      YES TFTP  down
Ethernet0/3              unassigned      YES TFTP  down
DC-EDGE#config t
Enter configuration commands, one per line.  End with CNTL/Z.
DC-EDGE(config)#int e0/0
*Sep 18 10:39:52.953: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
DC-EDGE(config)#int e0/0
DC-EDGE(config-if)#ip add 192.168.1.1 255.255.255.0
DC-EDGE(config-if)#no sh
DC-EDGE(config-if)#ex
DC-EDGE(config)#int e0/1
DC-EDGE(config-if)#ip add 30.0.0.2 255.0.0.0
DC-EDGE(config-if)#no sh
DC-EDGE(config-if)#ex
DC-EDGE(config)#do sh ip int br
Interface                IP-Address      OK? Method Status
Ethernet0/0              192.168.1.1     YES manual  up
Ethernet0/1              30.0.0.2        YES manual  up
Ethernet0/2              unassigned      YES TFTP  down
Ethernet0/3              unassigned      YES TFTP  down
```

```
DC-EDGE(config)#
DC-EDGE(config)#ip route 0.0.0.0 0.0.0.0 30.0.0.1
DC-EDGE(config)#
```

```
DC-EDGE(config)#int e0/0
DC-EDGE(config-if)#ip nat inside
DC-EDGE(config-if)#ex
DC-EDGE(config)#int e0/1
DC-EDGE(config-if)#ip nat outside
DC-EDGE(config-if)#ex
DC-EDGE(config)#
DC-EDGE(config)#ip nat inside source static 192.168.1.10 30.0.0.10
DC-EDGE(config)#ip nat inside source static 192.168.1.20 30.0.0.11
DC-EDGE(config)#
```

Step1:
Configuring on DC

HO-EDGE x Win1 x Win2 x DC-EDGE x VPC1 x VPC2 x

```
DC-EDGE#sh ip int br
Interface                IP-Address      OK? Method Status      Protocol
Ethernet0/0              unassigned      YES TFTP    up          up
Ethernet0/1              unassigned      YES TFTP    up          up
Ethernet0/2              unassigned      YES TFTP    down        down
Ethernet0/3              unassigned      YES TFTP    down        down

DC-EDGE#config t
Enter configuration commands, one per line.  End with CNTL/Z.
DC-EDGE(config)#int e0/0
*Sep 18 10:39:52.953: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
DC-EDGE(config)#int e0/0
DC-EDGE(config-if)#ip add 192.168.1.1 255.255.255.0
DC-EDGE(config-if)#no sh
DC-EDGE(config-if)#ex
DC-EDGE(config)#int e0/1
DC-EDGE(config-if)#ip add 30.0.0.2 255.0.0.0
DC-EDGE(config-if)#no sh
DC-EDGE(config-if)#ex
DC-EDGE(config)#do sh ip int br
Interface                IP-Address      OK? Method Status      Protocol
Ethernet0/0              192.168.1.1     YES manual  up          up
Ethernet0/1              30.0.0.2        YES manual  up          up
Ethernet0/2              unassigned      YES TFTP    down        down
Ethernet0/3              unassigned      YES TFTP    down        down

DC-EDGE(config)#
DC-EDGE(config)#ip route 0.0.0.0 0.0.0.0 30.0.0.1
DC-EDGE(config)#
```

```
DC-EDGE(config)#int e0/0
DC-EDGE(config-if)#ip nat inside
DC-EDGE(config-if)#ex
DC-EDGE(config)#int e0/1
DC-EDGE(config-if)#ip nat outside
DC-EDGE(config-if)#ex
DC-EDGE(config)#
DC-EDGE(config)#ip nat inside source static 192.168.1.10 30.0.0.10
DC-EDGE(config)#ip nat inside source static 192.168.1.20 30.0.0.11
DC-EDGE(config)#
```


NAT

Step 1 : Assign ip address for HO router

```
HO-EDGE#show ip int brief
Interface      IP-Address      OK? Method Status
GigabitEthernet0/0  10.0.0.1        YES manual up
GigabitEthernet0/1  20.0.0.1        YES manual up
```

Step 2 : Add default route in head office router

```
Router(config)# ip route 0.0.0.0 0.0.0.0 20.0.0.2
```

Step 3 : Create dynamic overload nat in head office router

```
Router(config)# interface e0/0
Router(config-if)# ip nat inside
Router(config-if)# exit
Router(config)#
Router(config)# interface e0/1
Router(config-if)# ip nat outside
Router(config-if)# exit
Router(config)#
Router(config)# access-list 10 permit 10.0.0.0 0.255.255.255
Router(config)# ip nat inside source list 10 interface e0/1 overload
```

Step 4 : Enable dhcp in HO router for lan pc

```
Router(config)# ip dhcp pool LAN
Router(config-dhcp)# network 10.0.0.0 255.0.0.0
Router(config-dhcp)# default-router 10.0.0.1
Router(config-dhcp)# dns-server 8.8.8.8
Router(config-dhcp)# exit
Router(config)#
```

Step 5 : After getting ip from dhcp access internet



Step 6 : Create static nat in datacenter router

```
Router(config)# ip route 0.0.0.0 0.0.0.0 30.0.0.1
Router(config)#
Router(config)# interface e0/0
Router(config-if)# ip nat inside
Router(config-if)# exit
Router(config)#
Router(config)# interface e0/1
Router(config-if)# ip nat outside
Router(config-if)# exit
Router(config)#
Router(config)# ip nat inside source static 192.168.1.10 30.0.0.10
Router(config)# ip nat inside source static 192.168.1.20 30.0.0.11
```

Step 7 : Access datacenter server from head office pc

```
C:\>ping 30.0.0.10
Pinging 30.0.0.10 with 32 bytes of data:
Reply from 30.0.0.10: bytes=32 time=4ms TTL=61
Reply from 30.0.0.10: bytes=32 time=4ms TTL=61
Reply from 30.0.0.10: bytes=32 time=2ms TTL=61
Reply from 30.0.0.10: bytes=32 time=2ms TTL=61
```

```
C:\>ping 30.0.0.11
Pinging 30.0.0.11 with 32 bytes of data:
Reply from 30.0.0.11: bytes=32 time=3ms TTL=61
Reply from 30.0.0.11: bytes=32 time=4ms TTL=61
Reply from 30.0.0.11: bytes=32 time=3ms TTL=61
Reply from 30.0.0.11: bytes=32 time=3ms TTL=61
```