

[pdf2docx documentation](#)**USER GUIDE**[Installation](#)[Quickstart](#)[Convert PDF](#)[Extract table](#)**Command Line Interface**[Graphic User Interface](#)[Technical Documentation](#)[License and Copyright](#)**API DOCUMENTATION**[pdf2docx](#)[Skip to content](#)[Try PyMuPDF](#)

Command Line Interface

```
$ pdf2docx --help
```

NAME

pdf2docx - Command line interface for pdf2docx.

SYNOPSIS

pdf2docx COMMAND | -

DESCRIPTION

Command line interface for pdf2docx.

COMMANDS

COMMAND is one of the following:

convert

Convert pdf file to docx file.

debug

Convert one PDF page and plot layout information for debugging.

table

Extract table content from pdf pages.

 [latest](#) ▼

By range of pages

Specify pages range by `--start` (from the first page if omitted) and `--end` (to the last page if omitted).

Note

The page index is zero-based by default, but can turn it off by `--zero_based_index=False`, i.e. the first page index starts from 1.

Convert all pages:

```
$ pdf2docx convert test.pdf test.docx
```

Convert pages from the second to the end:

```
$ pdf2docx convert test.pdf test.docx --start=1
```

Convert pages from the first to the third (index=2):

```
$ pdf2docx convert test.pdf test.docx --end=3
```

Convert second and third pages:

```
$ pdf2docx convert test.pdf test.docx --start=1 --end=3
```

Convert the first and second pages with zero-based index turn off:

```
$ pdf2docx convert test.pdf test.docx --start=1 --end=3 --zero_based_index=False
```



[Skip to content](#)

By page numbers

Convert the first, third and 5th pages:

```
$ pdf2docx convert test.pdf test.docx --pages=0,2,4
```

Multi-Processing

Turn on multi-processing with default count of CPU:

```
$ pdf2docx convert test.pdf test.docx --multi_processing=True
```

Specify the count of CPUs:

```
$ pdf2docx convert test.pdf test.docx --multi_processing=True --cpu_count=4
```

This documentation covers all versions up to 0.5.13.

Copyright © 2026, Artifex