

ACME Floor Indicator - External Indicators & Lanterns Script

New version: 5 June 2026 (Added directional arrows next to the floor indicators)

Script inclusion code: <Include data/Melvin/ACME_PI_2026/Indicators.txt>

*For best results, the floor indicators' texts have to be created in the specially sized indicator textures, which can be found in the "data/ACME Floor Indicator/Resized" folder.

1. Internal indicator function

To create an internal indicator set with both the floor indicator and directional arrow, please use the following function *inside the elevator section*:

`ACME_PI_InternalInd(Direction, CenterX, CenterZ, Offset, FLInd-Prefix, ArrowBlankTex, ArrowUpTex, ArrowDownTex)`

Parameters for this function:

1. **Direction** is the direction that the indicators face.
2. **CenterX** and **CenterZ** are the center points of the indicators (*relative* to the elevator, as this function create the indicators inside the elevator itself).
3. **Offset** specifies the indicators' offset from the elevator's floor.
4. **FLInd-Prefix** is the texture prefix for the floor indicator.
5. **ArrowBlankTex** is the texture used for the arrow next to the floor indicator when it is not displayed, such as a blank or black texture.
6. **ArrowUpTex** and **ArrowDownTex** are the textures for the arrows that appear next to the floor indicators when the elevator is moving up or down respectively.

2. Texture specification function

Before inserting any function for creating the external indicators, the following function must be inserted first to specify the textures:

`ACME_PI_LanternTex(UpTexture, UpLitTexture, DownTexture, DownTextureLit, PanelTexture, FLInd-Prefix, ArrowBlankTex, ArrowUpTex, ArrowDownTex)`

After inserting this function, the textures' names are stored in variables. Hence, the function doesn't need to be inserted anymore unless you want to change the textures.

Parameters for this function:

1. **UpTexture** and **UpLitTexture** are the textures for the lanterns when the elevator arrives at a floor going up, when unlit and lit respectively.
2. **DownTexture** and **DownLitTexture** are the textures for the lantern when the elevator arrives at a floor going down, when unlit and lit respectively.
3. **PanelTexture** is the texture used for the indicators' back panel.
4. **FLInd-Prefix** is the texture prefix for the floor indicator*. *This parameter can be ignored if the full indicator set function is not used.*
5. **ArrowBlankTex** is the texture used for the arrow next to the floor indicator when it is not displayed, such as a blank or black texture. *This parameter can be ignored if the full indicator set function is not used.*
7. **ArrowUpTex** and **ArrowDownTex** are the textures for the arrows that appear next to the floor indicators when the elevator is moving up or down. *They can be ignored if the full indicator set function is not in use.*

3. Indicator set/lantern functions

To insert a full indicator set, the following function can be inserted *in the floor section*:

```
ACME_PI_LobbyInds(Direction, ElevNo, CenterX, CenterZ, Offset, LowestFloor, HighestFloor)
```

To insert only lanterns *without* floor indicators, the following function can be inserted *in the floor section*:

```
ACME_PI_LobbyLanterns(Direction, ElevNo, CenterX, CenterZ, Offset, LowestFloor, HighestFloor)
```

Parameters for both functions:

1. **Direction** is the direction that the indicators face.
2. **ElevNo** is the elevator number for the indicators to be created.
3. **CenterX** and **CenterZ** are the center points of the indicators (*not* relative to the elevator).
4. **Offset** specifies the indicators' offset from the floor.
5. **LowestFloor** and **HighestFloor** set the elevator's lowest and highest serviced floors, so that the up and down lanterns are created correctly on each floor.