

Configuration

✓ NVIC ✓ Code generation

- ✔ Code generation

☐ Sort by interrupts names

- ✓ Force DMA channels Interrupts

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
Non maskable interrupt	☒	0	0
Hard fault interrupt	☒	0	0
Memory management fault	☒	0	0
Prefetch fault, memory access fault	☒	0	0
Undefined instruction or illegal state	☒	0	0
System service call via SWI instruction	☒	0	0
Debug monitor	☒	0	0
Pendable request for system service	☒	0	0
Time base: System tick timer	☒	15	0
PVD interrupt through EXTI line 16	☐	0	0
Flash global interrupt	☐	0	0
RCC global interrupt	☐	0	0
TIM3 global interrupt	☒	0	0
I2C2 event interrupt	☒	0	0
I2C2 error interrupt	☒	0	0

Mode

High Speed Clock (HSE) Crystal/Ceramic Resonator



Reset Configuration

[✔ Parameter Settings](#)
[✔ User Constants](#)
[✔ NVIC Settings](#)
[✔ GPIO Settings](#)

✓ GPIO Settings

Search (Ctrl+F) ⏪ ⏩ ⓘ

VDD voltage (V)	3.3 V
-----------------	-------

3.3 V

Enabled

2 WS (3 CPU cycle)

HSI Calibration Value	16
-----------------------	----

16

100

5000

Mode

Slave Mode

Disable

Trigger Source

Disable

☒ Internal Clock

Channel1

Disable

Channel2

Disable

Channel3

Disable

Channel4

Disable

Combined Channels

Disable

☐ XOR activation

☐ One Pulse Mode

Configuration

Reset Configuration

☒ Parameter Settings

☒ User Constants

☒ NVIC Settings

☒ DMA Settings

Configure the below parameters :

Search (Ctrl+F)

Counter Settings

Prescaler (PSC - 16 bits value)

7199

Counter Mode

Up

Counter Period (AutoReload Register - 16 bits v...

4999

Internal Clock Division (CKD)

No Division

auto-reload preload

Disable

Trigger Output (TRGO) Parameters

Master/Slave Mode (MSM bit)

Disable (Trigger input effect not delayed)

Trigger Event Selection

Reset (IIG bit from TIMx_EGR)

TIM3 Mode and Configuration

Mode

Slave Mode

Disable

Trigger Source

Disable

☒ Internal Clock

Channel1

Disable

Channel2

Disable

Channel3

Disable

Channel4

Disable

Combined Channels

Disable

☐ XOR activation

☐ One Pulse Mode

Configuration

Reset Configuration

☒ Parameter Settings

☒ User Constants

☒ NVIC Settings

☒ DMA Settings

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

I2C2 Mode and Configuration

Mode

I2C I2C

Configuration

Reset Configuration

☒ Parameter Settings
 ☒ User Constants
 ☒ NVIC Settings
 ☒ DMA Settings
 ☒ GPIO Settings

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
I2C2 event interrupt	☒	0	0
I2C2 error interrupt	☒	0	0

