

```
VInetR1(config)#access-list 1 permit 192.168.1.0 0.0.0.255
```



VinetR1



Physical

Config

CLI

Attributes

```
cisco Systems, Inc.  
170 West Tasman Drive  
San Jose, California 95134-1706
```

```
Cisco IOS Software, C1900 Software (C1900-UNIVERSALK9-M), Version 15.1(4)M4, RELEASE  
SOFTWARE (fc2)
```

```
Technical Support: http://www.cisco.com/techsupport
```

```
Copyright (c) 1986-2012 by Cisco Systems, Inc.
```

```
Compiled Thurs 5-Jan-12 15:41 by pt_team
```

```
Image text-base: 0x2100F918, data-base: 0x24729040
```

```
This product contains cryptographic features and is subject to United  
States and local country laws governing import, export, transfer and  
use. Delivery of Cisco cryptographic products does not imply  
third-party authority to import, export, distribute or use encryption.  
Importers, exporters, distributors and users are responsible for  
compliance with U.S. and local country laws. By using this product you  
agree to comply with applicable laws and regulations. If you are unable  
to comply with U.S. and local laws, return this product immediately.
```

```
A summary of U.S. laws governing Cisco cryptographic products may be found at:  
http://www.cisco.com/wwl/export/crypto/tool/stqrg.html
```

```
If you require further assistance please contact us by sending email to  
export@cisco.com.
```

```
Cisco CISCO1941/K9 (revision 1.0) with 491520K/32768K bytes of memory.  
Processor board ID FTX152400KS  
2 Gigabit Ethernet interfaces  
DRAM configuration is 64 bits wide with parity disabled.  
255K bytes of non-volatile configuration memory.  
249856K bytes of ATA System CompactFlash 0 (Read/Write)
```

```
Press RETURN to get started!
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
```

Copy

Paste


Top

```
VInetR1 (config)#interface g0/1|
VInetR1 (config-if)#ip nat inside
VInetR1 (config-if)#exit
VInetR1 (config)#interface g0/0
VInetR1 (config-if)#ip nat outside
VInetR1 (config-if)#exit
VInetR1 (config)#
```

VInetR1#show ip nat translations

Pro	Inside global	Inside local	Outside local	Outside global
icmp	172.16.0.2:5	192.168.1.3:5	172.16.0.1:5	172.16.0.1:5
icmp	172.16.0.2:6	192.168.1.3:6	172.16.0.1:6	172.16.0.1:6
icmp	172.16.0.2:7	192.168.1.3:7	172.16.0.1:7	172.16.0.1:7
icmp	172.16.0.2:8	192.168.1.3:8	172.16.0.1:8	172.16.0.1:8

VInetR1#



```
VIInetR1(config)#ip nat inside source list 1 interface g0/0 overload
VIInetR1(config)#exit
VIInetR1#
%SYS-5-CONFIG_I: Configured from console by console

VIInetR1#write
Building configuration...
[OK]
VIInetR1#
```

```
C:\> ping 172.16.0.1
```

```
Pinging 172.16.0.1 with 32 bytes of data:
```

```
Reply from 172.16.0.1: bytes=32 time<1ms TTL=254
```

```
Reply from 172.16.0.1: bytes=32 time<1ms TTL=254
```

```
Reply from 172.16.0.1: bytes=32 time<1ms TTL=254
```

```
Reply from 172.16.0.1: bytes=32 time<1ms TTL=254
```

```
Ping statistics for 172.16.0.1:
```

```
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
```

```
Approximate round trip times in milli-seconds:
```

```
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
```

```
C:\>
```

Command Prompt

Cisco Packet Tracer PC Command Line 1.0

C:\>ping 172.16.0.1

Pinging 172.16.0.1 with 32 bytes of data:

Reply from 172.16.0.1: bytes=32 time<1ms TTL=254

Reply from 172.16.0.1: bytes=32 time<1ms TTL=254

Reply from 172.16.0.1: bytes=32 time<1ms TTL=254

Reply from 172.16.0.1: bytes=32 time<1ms TTL=254

Ping statistics for 172.16.0.1:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>